

Spinnaker C

2.0.0.0

Generated by Doxygen 1.8.13

Contents

1	Module Index	1
1.1	Modules	1
2	Data Structure Index	3
2.1	Data Structures	3
3	File Index	5
3.1	File List	5
4	Module Documentation	7
4.1	Spinnaker C Definitions	7
4.1.1	Detailed Description	8
4.1.2	Typedef Documentation	8
4.1.2.1	bool8_t	8
4.1.3	Variable Documentation	8
4.1.3.1	False	8
4.1.3.2	True	8
4.2	Camera Enumerations	9
4.2.1	Detailed Description	41
4.2.2	Enumeration Type Documentation	41
4.2.2.1	spinAcquisitionModeEnums	41
4.2.2.2	spinAcquisitionStatusSelectorEnums	41
4.2.2.3	spinActionUnconditionalModeEnums	42
4.2.2.4	spinAdcBitDepthEnums	42
4.2.2.5	spinAutoAlgorithmSelectorEnums	42

4.2.2.6	spinAutoExposureControlPriorityEnums	43
4.2.2.7	spinAutoExposureLightingModeEnums	43
4.2.2.8	spinAutoExposureMeteringModeEnums	43
4.2.2.9	spinAutoExposureTargetGreyValueAutoEnums	44
4.2.2.10	spinBalanceRatioSelectorEnums	44
4.2.2.11	spinBalanceWhiteAutoEnums	45
4.2.2.12	spinBalanceWhiteAutoProfileEnums	45
4.2.2.13	spinBinningHorizontalModeEnums	45
4.2.2.14	spinBinningSelectorEnums	46
4.2.2.15	spinBinningVerticalModeEnums	46
4.2.2.16	spinBlackLevelAutoBalanceEnums	46
4.2.2.17	spinBlackLevelAutoEnums	47
4.2.2.18	spinBlackLevelSelectorEnums	47
4.2.2.19	spinChunkBlackLevelSelectorEnums	47
4.2.2.20	spinChunkCounterSelectorEnums	48
4.2.2.21	spinChunkEncoderSelectorEnums	48
4.2.2.22	spinChunkEncoderStatusEnums	48
4.2.2.23	spinChunkExposureTimeSelectorEnums	48
4.2.2.24	spinChunkGainSelectorEnums	49
4.2.2.25	spinChunkImageComponentEnums	49
4.2.2.26	spinChunkPixelFormatEnums	50
4.2.2.27	spinChunkRegionIDEnums	50
4.2.2.28	spinChunkScan3dCoordinateReferenceSelectorEnums	51
4.2.2.29	spinChunkScan3dCoordinateSelectorEnums	51
4.2.2.30	spinChunkScan3dCoordinateSystemEnums	51
4.2.2.31	spinChunkScan3dCoordinateSystemReferenceEnums	52
4.2.2.32	spinChunkScan3dCoordinateTransformSelectorEnums	52
4.2.2.33	spinChunkScan3dDistanceUnitEnums	52
4.2.2.34	spinChunkScan3dOutputModeEnums	53
4.2.2.35	spinChunkSelectorEnums	54

4.2.2.36	spinChunkSourceIDEnums	54
4.2.2.37	spinChunkTimerSelectorEnums	54
4.2.2.38	spinChunkTransferStreamIDEnums	55
4.2.2.39	spinCIConfigurationEnums	55
4.2.2.40	spinCITimeSlotsCountEnums	56
4.2.2.41	spinColorTransformationSelectorEnums	56
4.2.2.42	spinColorTransformationValueSelectorEnums	56
4.2.2.43	spinCounterEventActivationEnums	57
4.2.2.44	spinCounterEventSourceEnums	57
4.2.2.45	spinCounterResetActivationEnums	58
4.2.2.46	spinCounterResetSourceEnums	58
4.2.2.47	spinCounterSelectorEnums	59
4.2.2.48	spinCounterStatusEnums	59
4.2.2.49	spinCounterTriggerActivationEnums	59
4.2.2.50	spinCounterTriggerSourceEnums	60
4.2.2.51	spinCxpConnectionTestModeEnums	60
4.2.2.52	spinCxpLinkConfigurationEnums	60
4.2.2.53	spinCxpLinkConfigurationPreferredEnums	61
4.2.2.54	spinCxpLinkConfigurationStatusEnums	62
4.2.2.55	spinCxpPoCxpStatusEnums	63
4.2.2.56	spinDecimationHorizontalModeEnums	64
4.2.2.57	spinDecimationSelectorEnums	64
4.2.2.58	spinDecimationVerticalModeEnums	64
4.2.2.59	spinDefectCorrectionModeEnums	65
4.2.2.60	spinDeinterlacingEnums	65
4.2.2.61	spinDeviceCharacterSetEnums	65
4.2.2.62	spinDeviceClockSelectorEnums	66
4.2.2.63	spinDeviceConnectionStatusEnums	66
4.2.2.64	spinDeviceIndicatorModeEnums	66
4.2.2.65	spinDeviceLinkHeartbeatModeEnums	66

4.2.2.66	spinDeviceLinkThroughputLimitModeEnums	68
4.2.2.67	spinDevicePowerSupplySelectorEnums	68
4.2.2.68	spinDeviceRegistersEndiannessEnums	68
4.2.2.69	spinDeviceScanTypeEnums	69
4.2.2.70	spinDeviceSerialPortBaudRateEnums	69
4.2.2.71	spinDeviceSerialPortSelectorEnums	69
4.2.2.72	spinDeviceStreamChannelEndiannessEnums	70
4.2.2.73	spinDeviceStreamChannelTypeEnums	70
4.2.2.74	spinDeviceTapGeometryEnums	70
4.2.2.75	spinDeviceTemperatureSelectorEnums	71
4.2.2.76	spinDeviceTLTypeEnums	72
4.2.2.77	spinDeviceTypeEnums	72
4.2.2.78	spinEncoderModeEnums	72
4.2.2.79	spinEncoderOutputModeEnums	73
4.2.2.80	spinEncoderResetActivationEnums	73
4.2.2.81	spinEncoderResetSourceEnums	74
4.2.2.82	spinEncoderSelectorEnums	75
4.2.2.83	spinEncoderSourceAEnums	75
4.2.2.84	spinEncoderSourceBEnums	75
4.2.2.85	spinEncoderStatusEnums	76
4.2.2.86	spinEventNotificationEnums	76
4.2.2.87	spinEventSelectorEnums	76
4.2.2.88	spinExposureActiveModeEnums	77
4.2.2.89	spinExposureAutoEnums	77
4.2.2.90	spinExposureModeEnums	77
4.2.2.91	spinExposureTimeModeEnums	78
4.2.2.92	spinExposureTimeSelectorEnums	78
4.2.2.93	spinFileOpenModeEnums	79
4.2.2.94	spinFileOperationSelectorEnums	79
4.2.2.95	spinFileOperationStatusEnums	79

4.2.2.96 spinFileSelectorEnums	80
4.2.2.97 spinGainAutoBalanceEnums	80
4.2.2.98 spinGainAutoEnums	80
4.2.2.99 spinGainSelectorEnums	81
4.2.2.100 spinGevCCPEnums	81
4.2.2.101 spinGevCurrentPhysicalLinkConfigurationEnums	81
4.2.2.102 spinGevGVCPExtendedStatusCodesSelectorEnums	82
4.2.2.103 spinGevGVSPExtendedIDModeEnums	82
4.2.2.104 spinGevIEEE1588ClockAccuracyEnums	82
4.2.2.105 spinGevIEEE1588ModeEnums	82
4.2.2.106 spinGevIEEE1588StatusEnums	83
4.2.2.107 spinGevIPConfigurationStatusEnums	83
4.2.2.108 spinGevPhysicalLinkConfigurationEnums	84
4.2.2.109 spinGevSupportedOptionSelectorEnums	84
4.2.2.110 spinImageComponentSelectorEnums	85
4.2.2.111 spinImageCompressionJPEGFormatOptionEnums	85
4.2.2.112 spinImageCompressionModeEnums	86
4.2.2.113 spinImageCompressionRateOptionEnums	86
4.2.2.114 spinLineFormatEnums	86
4.2.2.115 spinLineInputFilterSelectorEnums	87
4.2.2.116 spinLineModeEnums	87
4.2.2.117 spinLineSelectorEnums	87
4.2.2.118 spinLineSourceEnums	88
4.2.2.119 spinLogicBlockLUTInputActivationEnums	88
4.2.2.120 spinLogicBlockLUTInputSelectorEnums	89
4.2.2.121 spinLogicBlockLUTInputSourceEnums	89
4.2.2.122 spinLogicBlockLUTSelectorEnums	90
4.2.2.123 spinLogicBlockSelectorEnums	90
4.2.2.124 spinLUTSelectorEnums	90
4.2.2.125 spinPixelColorFilterEnums	91

4.2.2.126 spinPixelFormatEnums	91
4.2.2.127 spinPixelFormatInfoSelectorEnums	97
4.2.2.128 spinPixelFormatSizeEnums	102
4.2.2.129 spinRegionDestinationEnums	103
4.2.2.130 spinRegionModeEnums	103
4.2.2.131 spinRegionSelectorEnums	104
4.2.2.132 spinRgbTransformLightSourceEnums	104
4.2.2.133 spinScan3dCoordinateReferenceSelectorEnums	105
4.2.2.134 spinScan3dCoordinateSelectorEnums	105
4.2.2.135 spinScan3dCoordinateSystemEnums	105
4.2.2.136 spinScan3dCoordinateSystemReferenceEnums	106
4.2.2.137 spinScan3dCoordinateTransformSelectorEnums	106
4.2.2.138 spinScan3dDistanceUnitEnums	106
4.2.2.139 spinScan3dOutputModeEnums	107
4.2.2.140 spinSensorDigitizationTapsEnums	107
4.2.2.141 spinSensorShutterModeEnums	108
4.2.2.142 spinSensorTapsEnums	108
4.2.2.143 spinSequencerConfigurationModeEnums	109
4.2.2.144 spinSequencerConfigurationValidEnums	109
4.2.2.145 spinSequencerModeEnums	109
4.2.2.146 spinSequencerSetValidEnums	109
4.2.2.147 spinSequencerTriggerActivationEnums	110
4.2.2.148 spinSequencerTriggerSourceEnums	110
4.2.2.149 spinSerialPortBaudRateEnums	110
4.2.2.150 spinSerialPortParityEnums	111
4.2.2.151 spinSerialPortSelectorEnums	111
4.2.2.152 spinSerialPortSourceEnums	112
4.2.2.153 spinSerialPortStopBitsEnums	112
4.2.2.154 spinSoftwareSignalSelectorEnums	112
4.2.2.155 spinSourceSelectorEnums	113

4.2.2.156 spinTestPatternEnums	113
4.2.2.157 spinTestPatternGeneratorSelectorEnums	113
4.2.2.158 spinTimerSelectorEnums	114
4.2.2.159 spinTimerStatusEnums	114
4.2.2.160 spinTimerTriggerActivationEnums	114
4.2.2.161 spinTimerTriggerSourceEnums	115
4.2.2.162 spinTransferComponentSelectorEnums	116
4.2.2.163 spinTransferControlModeEnums	116
4.2.2.164 spinTransferOperationModeEnums	117
4.2.2.165 spinTransferQueueModeEnums	117
4.2.2.166 spinTransferSelectorEnums	117
4.2.2.167 spinTransferStatusSelectorEnums	118
4.2.2.168 spinTransferTriggerActivationEnums	118
4.2.2.169 spinTransferTriggerModeEnums	118
4.2.2.170 spinTransferTriggerSelectorEnums	119
4.2.2.171 spinTransferTriggerSourceEnums	119
4.2.2.172 spinTriggerActivationEnums	120
4.2.2.173 spinTriggerModeEnums	121
4.2.2.174 spinTriggerOverlapEnums	121
4.2.2.175 spinTriggerSelectorEnums	121
4.2.2.176 spinTriggerSourceEnums	122
4.2.2.177 spinUserOutputSelectorEnums	122
4.2.2.178 spinUserSetDefaultEnums	122
4.2.2.179 spinUserSetSelectorEnums	123
4.2.2.180 spinWhiteClipSelectorEnums	123
4.3 Chunk Data Structures	124
4.3.1 Detailed Description	124
4.4 Spinnaker C QuickSpin API	125
4.4.1 Detailed Description	125
4.5 QuickSpin Access	126

4.5.1	Detailed Description	126
4.5.2	Function Documentation	126
4.5.2.1	quickSpinInit()	126
4.5.2.2	quickSpinInitEx()	127
4.5.2.3	quickSpinTLDeviceInit()	127
4.5.2.4	quickSpinTLInterfaceInit()	127
4.5.2.5	quickSpinTLStreamInit()	127
4.5.2.6	quickSpinTLSystemInit()	127
4.6	Spinnaker C API	128
4.6.1	Detailed Description	129
4.6.2	Function Documentation	129
4.6.2.1	spinCameraDiscoverMaxPacketSize()	129
4.7	Error Handling	130
4.7.1	Detailed Description	130
4.7.2	Function Documentation	130
4.7.2.1	spinErrorGetLast()	130
4.7.2.2	spinErrorGetLastBuildDate()	131
4.7.2.3	spinErrorGetLastBuildTime()	131
4.7.2.4	spinErrorGetLastFileName()	132
4.7.2.5	spinErrorGetLastFullMessage()	132
4.7.2.6	spinErrorGetLastFunctionName()	133
4.7.2.7	spinErrorGetLastLineNumber()	133
4.7.2.8	spinErrorGetLastMessage()	134
4.8	System Access	135
4.8.1	Detailed Description	136
4.8.2	Function Documentation	136
4.8.2.1	spinSystemGetCameras()	136
4.8.2.2	spinSystemGetCamerasEx()	137
4.8.2.3	spinSystemGetInstance()	137
4.8.2.4	spinSystemGetInterfaces()	139

4.8.2.5	spinSystemGetLibraryVersion()	139
4.8.2.6	spinSystemGetLoggingLevel()	140
4.8.2.7	spinSystemGetTLNodeMap()	140
4.8.2.8	spinSystemIsInUse()	141
4.8.2.9	spinSystemRegisterDeviceArrivalEventHandler()	141
4.8.2.10	spinSystemRegisterDeviceRemovalEventHandler()	142
4.8.2.11	spinSystemRegisterInterfaceEventHandler()	142
4.8.2.12	spinSystemRegisterLogEventHandler()	143
4.8.2.13	spinSystemReleaseInstance()	143
4.8.2.14	spinSystemSendActionCommand()	143
4.8.2.15	spinSystemSetLoggingLevel()	144
4.8.2.16	spinSystemUnregisterAllLogEventHandlers()	145
4.8.2.17	spinSystemUnregisterDeviceArrivalEventHandler()	145
4.8.2.18	spinSystemUnregisterDeviceRemovalEventHandler()	146
4.8.2.19	spinSystemUnregisterInterfaceEventHandler()	146
4.8.2.20	spinSystemUnregisterLogEventHandler()	147
4.8.2.21	spinSystemUpdateCameras()	147
4.8.2.22	spinSystemUpdateCamerasEx()	147
4.9	InterfaceList Access	149
4.9.1	Detailed Description	149
4.9.2	Function Documentation	149
4.9.2.1	spinInterfaceListClear()	149
4.9.2.2	spinInterfaceListCreateEmpty()	150
4.9.2.3	spinInterfaceListDestroy()	150
4.9.2.4	spinInterfaceListGet()	151
4.9.2.5	spinInterfaceListGetSize()	151
4.10	CameraList Access	153
4.10.1	Detailed Description	153
4.10.2	Function Documentation	153
4.10.2.1	spinCameraListAppend()	154

4.10.2.2	spinCameraListClear()	154
4.10.2.3	spinCameraListCreateEmpty()	154
4.10.2.4	spinCameraListDestroy()	155
4.10.2.5	spinCameraListGet()	155
4.10.2.6	spinCameraListGetBySerial()	156
4.10.2.7	spinCameraListGetSize()	156
4.10.2.8	spinCameraListRemove()	157
4.10.2.9	spinCameraListRemoveBySerial()	157
4.11	Interface Access	159
4.11.1	Detailed Description	160
4.11.2	Function Documentation	160
4.11.2.1	spinInterfaceGetCameras()	160
4.11.2.2	spinInterfaceGetCamerasEx()	160
4.11.2.3	spinInterfaceGetTLNodeMap()	161
4.11.2.4	spinInterfaceIsInUse()	161
4.11.2.5	spinInterfaceRegisterDeviceArrivalEventHandler()	162
4.11.2.6	spinInterfaceRegisterDeviceRemovalEventHandler()	162
4.11.2.7	spinInterfaceRegisterInterfaceEventHandler()	163
4.11.2.8	spinInterfaceRelease()	163
4.11.2.9	spinInterfaceSendActionCommand()	164
4.11.2.10	spinInterfaceUnregisterDeviceArrivalEventHandler()	164
4.11.2.11	spinInterfaceUnregisterDeviceRemovalEventHandler()	165
4.11.2.12	spinInterfaceUnregisterInterfaceEventHandler()	165
4.11.2.13	spinInterfaceUpdateCameras()	166
4.12	Camera Access	167
4.12.1	Detailed Description	168
4.12.2	Function Documentation	168
4.12.2.1	spinCameraBeginAcquisition()	168
4.12.2.2	spinCameraDeInit()	169
4.12.2.3	spinCameraEndAcquisition()	169

4.12.2.4	spinCameraGetAccessMode()	170
4.12.2.5	spinCameraGetGuiXml()	170
4.12.2.6	spinCameraGetNextImage()	171
4.12.2.7	spinCameraGetNextImageEx()	171
4.12.2.8	spinCameraGetNodeMap()	172
4.12.2.9	spinCameraGetTLDeviceNodeMap()	172
4.12.2.10	spinCameraGetTLStreamNodeMap()	173
4.12.2.11	spinCameraGetUniqueID()	173
4.12.2.12	spinCameraInit()	174
4.12.2.13	spinCameralIsInitialized()	174
4.12.2.14	spinCameralIsStreaming()	174
4.12.2.15	spinCameralIsValid()	175
4.12.2.16	spinCameraReadPort()	175
4.12.2.17	spinCameraRegisterDeviceEventHandler()	176
4.12.2.18	spinCameraRegisterDeviceEventHandlerEx()	176
4.12.2.19	spinCameraRegisterImageEventHandler()	177
4.12.2.20	spinCameraRelease()	177
4.12.2.21	spinCameraUnregisterDeviceEventHandler()	177
4.12.2.22	spinCameraUnregisterImageEventHandler()	178
4.12.2.23	spinCameraWritePort()	178
4.13	Image Access	179
4.13.1	Detailed Description	181
4.13.2	Function Documentation	181
4.13.2.1	spinImageCalculateStatistics()	181
4.13.2.2	spinImageCheckCRC()	182
4.13.2.3	spinImageConvert()	182
4.13.2.4	spinImageConvertEx()	183
4.13.2.5	spinImageCreate()	183
4.13.2.6	spinImageCreateEmpty()	184
4.13.2.7	spinImageCreateEx()	184

4.13.2.8 spinImageDeepCopy()	185
4.13.2.9 spinImageDestroy()	185
4.13.2.10 spinImageGetBitsPerPixel()	186
4.13.2.11 spinImageGetBufferSize()	186
4.13.2.12 spinImageGetChunkLayoutID()	187
4.13.2.13 spinImageGetColorProcessing()	187
4.13.2.14 spinImageGetData()	188
4.13.2.15 spinImageGetDefaultColorProcessing()	188
4.13.2.16 spinImageGetFrameID()	189
4.13.2.17 spinImageGetHeight()	189
4.13.2.18 spinImageGetID()	190
4.13.2.19 spinImageGetOffsetX()	190
4.13.2.20 spinImageGetOffsetY()	191
4.13.2.21 spinImageGetPaddingX()	191
4.13.2.22 spinImageGetPaddingY()	192
4.13.2.23 spinImageGetPayloadType()	192
4.13.2.24 spinImageGetPixelFormat()	193
4.13.2.25 spinImageGetPixelFormatName()	193
4.13.2.26 spinImageGetPrivateData()	194
4.13.2.27 spinImageGetSize()	194
4.13.2.28 spinImageGetStatus()	195
4.13.2.29 spinImageGetStatusDescription()	195
4.13.2.30 spinImageGetStride()	196
4.13.2.31 spinImageGetTimeStamp()	196
4.13.2.32 spinImageGetTLPayloadType()	197
4.13.2.33 spinImageGetTLPixelFormat()	197
4.13.2.34 spinImageGetTLPixelFormatNamespace()	198
4.13.2.35 spinImageGetValidPayloadSize()	198
4.13.2.36 spinImageGetWidth()	199
4.13.2.37 spinImageHasCRC()	199

4.13.2.38 spinImageIsIncomplete()	200
4.13.2.39 spinImageRelease()	200
4.13.2.40 spinImageReset()	200
4.13.2.41 spinImageResetEx()	201
4.13.2.42 spinImageSave()	202
4.13.2.43 spinImageSaveBmp()	202
4.13.2.44 spinImageSaveFromExt()	203
4.13.2.45 spinImageSaveJpeg()	203
4.13.2.46 spinImageSaveJpg2()	204
4.13.2.47 spinImageSavePgm()	204
4.13.2.48 spinImageSavePng()	205
4.13.2.49 spinImageSavePpm()	205
4.13.2.50 spinImageSaveTiff()	206
4.13.2.51 spinImageSetDefaultColorProcessing()	206
4.14 Event Access	208
4.14.1 Detailed Description	208
4.14.2 Function Documentation	208
4.14.2.1 spinDeviceArrivalEventHandlerCreate()	209
4.14.2.2 spinDeviceArrivalEventHandlerDestroy()	209
4.14.2.3 spinDeviceEventHandlerCreate()	210
4.14.2.4 spinDeviceEventHandlerDestroy()	210
4.14.2.5 spinDeviceRemovalEventHandlerCreate()	211
4.14.2.6 spinDeviceRemovalEventHandlerDestroy()	211
4.14.2.7 spinImageEventHandlerCreate()	212
4.14.2.8 spinImageEventHandlerDestroy()	212
4.14.2.9 spinInterfaceEventHandlerCreate()	213
4.14.2.10 spinInterfaceEventHandlerDestroy()	213
4.14.2.11 spinLogEventHandlerCreate()	214
4.14.2.12 spinLogEventHandlerDestroy()	214
4.15 ImageStatistics Access	215

4.15.1 Detailed Description	215
4.15.2 Function Documentation	216
4.15.2.1 spinImageStatisticsCreate()	216
4.15.2.2 spinImageStatisticsDestroy()	216
4.15.2.3 spinImageStatisticsDisableAll()	216
4.15.2.4 spinImageStatisticsEnableAll()	217
4.15.2.5 spinImageStatisticsEnableGreyOnly()	217
4.15.2.6 spinImageStatisticsEnableHslOnly()	218
4.15.2.7 spinImageStatisticsEnableRgbOnly()	218
4.15.2.8 spinImageStatisticsGetAll()	219
4.15.2.9 spinImageStatisticsGetChannelStatus()	219
4.15.2.10 spinImageStatisticsGetHistogram()	220
4.15.2.11 spinImageStatisticsGetMean()	220
4.15.2.12 spinImageStatisticsGetNumPixelValues()	221
4.15.2.13 spinImageStatisticsGetPixelValueRange()	221
4.15.2.14 spinImageStatisticsGetRange()	222
4.15.2.15 spinImageStatisticsSetChannelStatus()	222
4.16 Logging Event Data Access	224
4.16.1 Detailed Description	224
4.16.2 Function Documentation	224
4.16.2.1 spinLogDataGetCategoryName()	224
4.16.2.2 spinLogDataGetLogMessage()	225
4.16.2.3 spinLogDataGetNDC()	225
4.16.2.4 spinLogDataGetPriority()	226
4.16.2.5 spinLogDataGetPriorityName()	226
4.16.2.6 spinLogDataGetThreadName()	227
4.16.2.7 spinLogDataGetTimestamp()	227
4.17 Device Event Data Access	229
4.17.1 Detailed Description	229
4.17.2 Function Documentation	229

4.17.2.1	spinDeviceEventGetId()	229
4.17.2.2	spinDeviceEventGetName()	230
4.17.2.3	spinDeviceEventGetPayloadData()	230
4.17.2.4	spinDeviceEventGetPayloadDataSize()	231
4.18	Chunk data access	232
4.18.1	Detailed Description	232
4.18.2	Function Documentation	232
4.18.2.1	spinImageChunkDataGetFloatValue()	232
4.18.2.2	spinImageChunkDataGetIntValue()	232
4.19	Spinnaker C Handles	233
4.19.1	Detailed Description	234
4.19.2	Typedef Documentation	234
4.19.2.1	spinCamera	234
4.19.2.2	spinCameraList	234
4.19.2.3	spinDeviceArrivalEventHandler	234
4.19.2.4	spinDeviceEventData	234
4.19.2.5	spinDeviceEventHandler	235
4.19.2.6	spinDeviceRemovalEventHandler	235
4.19.2.7	spinImage	235
4.19.2.8	spinImageEventHandler	235
4.19.2.9	spinImageStatistics	235
4.19.2.10	spinInterface	235
4.19.2.11	spinInterfaceEventHandler	236
4.19.2.12	spinInterfaceList	236
4.19.2.13	spinLogEventData	236
4.19.2.14	spinLogEventHandler	236
4.19.2.15	spinSystem	236
4.19.2.16	spinVideo	236
4.20	Spinnaker C Function Signatures	237
4.20.1	Detailed Description	237

4.20.2	Typedef Documentation	237
4.20.2.1	spinArrivalEventFunction	237
4.20.2.2	spinDeviceEventFunction	237
4.20.2.3	spinImageEventFunction	238
4.20.2.4	spinLogEventFunction	238
4.20.2.5	spinRemovalEventFunction	238
4.21	Spinnaker C Enumerations	239
4.21.1	Detailed Description	241
4.21.2	Enumeration Type Documentation	241
4.21.2.1	spinColorProcessingAlgorithm	241
4.21.2.2	spinError	242
4.21.2.3	spinImageFileFormat	243
4.21.2.4	spinImageStatus	244
4.21.2.5	spinnakerLogLevel	244
4.21.2.6	spinPayloadTypeInfoIds	245
4.21.2.7	spinPixelFormatNamespaceID	245
4.21.2.8	spinStatisticsChannel	246
4.22	Spinnaker C Structures	247
4.22.1	Detailed Description	248
4.22.2	Enumeration Type Documentation	248
4.22.2.1	actionCommandStatus	248
4.22.2.2	spinCompressionMethod	248
4.23	Spinnaker C GenICam API	249
4.23.1	Detailed Description	250
4.24	Node Map Access	251
4.24.1	Detailed Description	251
4.24.2	Function Documentation	251
4.24.2.1	spinNodeMapGetNode()	251
4.24.2.2	spinNodeMapGetNodeByIndex()	252
4.24.2.3	spinNodeMapGetNumNodes()	252

4.24.2.4	<code>spinNodeMapPoll()</code>	253
4.25	Node Access	254
4.25.1	Detailed Description	255
4.25.2	Function Documentation	255
4.25.2.1	<code>spinNodeDeregisterCallback()</code>	255
4.25.2.2	<code>spinNodeGetAccessMode()</code>	256
4.25.2.3	<code>spinNodeGetCachingMode()</code>	256
4.25.2.4	<code>spinNodeGetDescription()</code>	257
4.25.2.5	<code>spinNodeGetDisplayName()</code>	257
4.25.2.6	<code>spinNodeGetImposedAccessMode()</code>	258
4.25.2.7	<code>spinNodeGetImposedVisibility()</code>	258
4.25.2.8	<code>spinNodeGetName()</code>	259
4.25.2.9	<code>spinNodeGetNameSpace()</code>	259
4.25.2.10	<code>spinNodeGetPollingTime()</code>	260
4.25.2.11	<code>spinNodeGetToolTip()</code>	260
4.25.2.12	<code>spinNodeGetType()</code>	261
4.25.2.13	<code>spinNodeGetVisibility()</code>	261
4.25.2.14	<code>spinNodeInvalidateNode()</code>	262
4.25.2.15	<code>spinNodesAvailable()</code>	262
4.25.2.16	<code>spinNodesEqual()</code>	262
4.25.2.17	<code>spinNodesImplemented()</code>	263
4.25.2.18	<code>spinNodesReadable()</code>	263
4.25.2.19	<code>spinNodesWritable()</code>	264
4.25.2.20	<code>spinNodeRegisterCallback()</code>	264
4.26	IValue Access	266
4.26.1	Detailed Description	266
4.26.2	Function Documentation	266
4.26.2.1	<code>spinNodeFromString()</code>	266
4.26.2.2	<code>spinNodeFromStringEx()</code>	267
4.26.2.3	<code>spinNodeToString()</code>	267

4.26.2.4	<code>spinNodeToStringEx()</code>	268
4.27	String Access	269
4.27.1	Detailed Description	269
4.27.2	Function Documentation	269
4.27.2.1	<code>spinStringGetMaxLength()</code>	269
4.27.2.2	<code>spinStringGetValue()</code>	270
4.27.2.3	<code>spinStringGetValueEx()</code>	270
4.27.2.4	<code>spinStringSetValue()</code>	271
4.27.2.5	<code>spinStringSetValueEx()</code>	271
4.28	Integer Access	273
4.28.1	Detailed Description	273
4.28.2	Function Documentation	273
4.28.2.1	<code>spinIntegerGetInc()</code>	273
4.28.2.2	<code>spinIntegerGetMax()</code>	274
4.28.2.3	<code>spinIntegerGetMin()</code>	274
4.28.2.4	<code>spinIntegerGetRepresentation()</code>	275
4.28.2.5	<code>spinIntegerGetValue()</code>	275
4.28.2.6	<code>spinIntegerGetValueEx()</code>	276
4.28.2.7	<code>spinIntegerSetValue()</code>	276
4.28.2.8	<code>spinIntegerSetValueEx()</code>	277
4.29	IFloat Access	278
4.29.1	Detailed Description	278
4.29.2	Function Documentation	278
4.29.2.1	<code>spinFloatGetMax()</code>	278
4.29.2.2	<code>spinFloatGetMin()</code>	279
4.29.2.3	<code>spinFloatGetRepresentation()</code>	279
4.29.2.4	<code>spinFloatGetUnit()</code>	280
4.29.2.5	<code>spinFloatGetValue()</code>	280
4.29.2.6	<code>spinFloatGetValueEx()</code>	281
4.29.2.7	<code>spinFloatSetValue()</code>	281

4.29.2.8	spinFloatSetValueEx()	282
4.30	IEnumeration Access	283
4.30.1	Detailed Description	283
4.30.2	Function Documentation	283
4.30.2.1	spinEnumerationGetCurrentEntry()	283
4.30.2.2	spinEnumerationGetEntryByIndex()	284
4.30.2.3	spinEnumerationGetEntryByName()	284
4.30.2.4	spinEnumerationGetNumEntries()	285
4.30.2.5	spinEnumerationSetEnumValue()	285
4.30.2.6	spinEnumerationSetIntValue()	286
4.31	IEnumEntry Access	287
4.31.1	Detailed Description	287
4.31.2	Function Documentation	287
4.31.2.1	spinEnumerationEntryGetEnumValue()	287
4.31.2.2	spinEnumerationEntryGetIntValue()	288
4.31.2.3	spinEnumerationEntryGetSymbolic()	288
4.32	IBoolean Access	290
4.32.1	Detailed Description	290
4.32.2	Function Documentation	290
4.32.2.1	spinBooleanGetValue()	290
4.32.2.2	spinBooleanSetValue()	291
4.33	ICommand Access	292
4.33.1	Detailed Description	292
4.33.2	Function Documentation	292
4.33.2.1	spinCommandExecute()	292
4.33.2.2	spinCommandIsDone()	293
4.34	ICategory Access	294
4.34.1	Detailed Description	294
4.34.2	Function Documentation	294
4.34.2.1	spinCategoryGetFeatureByIndex()	294

4.34.2.2	spinCategoryGetNumFeatures()	295
4.35	IRegister Access	296
4.35.1	Detailed Description	296
4.35.2	Function Documentation	296
4.35.2.1	spinRegisterGet()	297
4.35.2.2	spinRegisterGetAddress()	297
4.35.2.3	spinRegisterGetEx()	298
4.35.2.4	spinRegisterGetLength()	298
4.35.2.5	spinRegisterSet()	299
4.35.2.6	spinRegisterSetEx()	299
4.35.2.7	spinRegisterSetReference()	300
4.36	Spinnaker C GenICam Handles	301
4.36.1	Detailed Description	301
4.36.2	Typedef Documentation	301
4.36.2.1	spinNodeCallbackFunction	301
4.36.2.2	spinNodeCallbackHandle	301
4.36.2.3	spinNodeHandle	302
4.36.2.4	spinNodeMapHandle	302
4.37	Spinnaker C GenICam Enumerations	303
4.37.1	Detailed Description	305
4.37.2	Enumeration Type Documentation	305
4.37.2.1	spinAccessMode	305
4.37.2.2	spinCachingMode	306
4.37.2.3	spinDisplayNotation	306
4.37.2.4	spinEndianess	306
4.37.2.5	spinIncMode	307
4.37.2.6	spinInputDirection	307
4.37.2.7	spinInterfaceType	307
4.37.2.8	spinLinkType	308
4.37.2.9	spinNameSpace	309

4.37.2.10 spinNodeType	309
4.37.2.11 spinRepresentation	310
4.37.2.12 spinSign	310
4.37.2.13 spinSlope	310
4.37.2.14 spinStandardNameSpace	311
4.37.2.15 spinVisibility	311
4.37.2.16 spinXMLValidation	311
4.37.2.17 spinYesNo	313
4.38 SpinVideo Recording Access	314
4.38.1 Detailed Description	314
4.38.2 Function Documentation	314
4.38.2.1 spinVideoAppend()	314
4.38.2.2 spinVideoClose()	315
4.38.2.3 spinVideoOpenH264()	315
4.38.2.4 spinVideoOpenMJPEG()	315
4.38.2.5 spinVideoOpenUncompressed()	315
4.38.2.6 spinVideoSetMaximumFileSize()	315
4.39 Transport Layer Enumerations	317
4.39.1 Detailed Description	318
4.39.2 Enumeration Type Documentation	318
4.39.2.1 spinTLDeviceAccessStatusEnums	319
4.39.2.2 spinTLDeviceCurrentSpeedEnums	320
4.39.2.3 spinTLDeviceEndianessMechanismEnums	320
4.39.2.4 spinTLDeviceTypeEnums	321
4.39.2.5 spinTLFilterDriverStatusEnums	321
4.39.2.6 spinTLGenICamXMLLocationEnums	321
4.39.2.7 spinTLGevCCPEnums	322
4.39.2.8 spinTLGUIXMLLocationEnums	322
4.39.2.9 spinTLInterfaceTypeEnums	322
4.39.2.10 spinTLPOEStatusEnums	323
4.39.2.11 spinTLStreamBufferCountModeEnums	323
4.39.2.12 spinTLStreamBufferHandlingModeEnums	323
4.39.2.13 spinTLStreamTypeEnums	324
4.39.2.14 spinTLTLTypeEnums	324
4.40 TLDevice Structures	326
4.40.1 Detailed Description	326
4.41 TLInterface Structures	327
4.41.1 Detailed Description	327
4.42 TLStream Structures	328
4.42.1 Detailed Description	328
4.43 TLSystem Structures	329
4.43.1 Detailed Description	329

5	Data Structure Documentation	331
5.1	actionCommandResult Struct Reference	331
5.1.1	Detailed Description	331
5.1.2	Field Documentation	331
5.1.2.1	DeviceAddress	331
5.1.2.2	Status	331
5.2	quickSpin Struct Reference	332
5.2.1	Field Documentation	344
5.2.1.1	AasRoiEnable	344
5.2.1.2	AasRoiHeight	344
5.2.1.3	AasRoiOffsetX	344
5.2.1.4	AasRoiOffsetY	344
5.2.1.5	AasRoiWidth	345
5.2.1.6	AcquisitionAbort	345
5.2.1.7	AcquisitionArm	345
5.2.1.8	AcquisitionBurstFrameCount	345
5.2.1.9	AcquisitionFrameCount	345
5.2.1.10	AcquisitionFrameRate	345
5.2.1.11	AcquisitionFrameRateEnable	345
5.2.1.12	AcquisitionLineRate	345
5.2.1.13	AcquisitionMode	346
5.2.1.14	AcquisitionResultingFrameRate	346
5.2.1.15	AcquisitionStart	346
5.2.1.16	AcquisitionStatus	346
5.2.1.17	AcquisitionStatusSelector	346
5.2.1.18	AcquisitionStop	346
5.2.1.19	ActionDeviceKey	346
5.2.1.20	ActionGroupKey	346
5.2.1.21	ActionGroupMask	347
5.2.1.22	ActionQueueSize	347

5.2.1.23	ActionSelector	347
5.2.1.24	ActionUnconditionalMode	347
5.2.1.25	AdaptiveCompressionEnable	347
5.2.1.26	AdcBitDepth	347
5.2.1.27	aPAUSEMACCtrlFramesReceived	347
5.2.1.28	aPAUSEMACCtrlFramesTransmitted	347
5.2.1.29	AutoAlgorithmSelector	348
5.2.1.30	AutoExposureControlLoopDamping	348
5.2.1.31	AutoExposureControlPriority	348
5.2.1.32	AutoExposureEVCompensation	348
5.2.1.33	AutoExposureExposureTimeLowerLimit	348
5.2.1.34	AutoExposureExposureTimeUpperLimit	348
5.2.1.35	AutoExposureGainLowerLimit	348
5.2.1.36	AutoExposureGainUpperLimit	348
5.2.1.37	AutoExposureGreyValueLowerLimit	349
5.2.1.38	AutoExposureGreyValueUpperLimit	349
5.2.1.39	AutoExposureLightingMode	349
5.2.1.40	AutoExposureMeteringMode	349
5.2.1.41	AutoExposureTargetGreyValue	349
5.2.1.42	AutoExposureTargetGreyValueAuto	349
5.2.1.43	BalanceRatio	349
5.2.1.44	BalanceRatioSelector	349
5.2.1.45	BalanceWhiteAuto	350
5.2.1.46	BalanceWhiteAutoDamping	350
5.2.1.47	BalanceWhiteAutoLowerLimit	350
5.2.1.48	BalanceWhiteAutoProfile	350
5.2.1.49	BalanceWhiteAutoUpperLimit	350
5.2.1.50	BinningHorizontal	350
5.2.1.51	BinningHorizontalMode	350
5.2.1.52	BinningSelector	350

5.2.1.53	BinningVertical	351
5.2.1.54	BinningVerticalMode	351
5.2.1.55	BlackLevel	351
5.2.1.56	BlackLevelAuto	351
5.2.1.57	BlackLevelAutoBalance	351
5.2.1.58	BlackLevelClampingEnable	351
5.2.1.59	BlackLevelRaw	351
5.2.1.60	BlackLevelSelector	351
5.2.1.61	ChunkBlackLevel	352
5.2.1.62	ChunkBlackLevelSelector	352
5.2.1.63	ChunkCounterSelector	352
5.2.1.64	ChunkCounterValue	352
5.2.1.65	ChunkCRC	352
5.2.1.66	ChunkEnable	352
5.2.1.67	ChunkEncoderSelector	352
5.2.1.68	ChunkEncoderStatus	352
5.2.1.69	ChunkEncoderValue	353
5.2.1.70	ChunkExposureEndLineStatusAll	353
5.2.1.71	ChunkExposureTime	353
5.2.1.72	ChunkExposureTimeSelector	353
5.2.1.73	ChunkFrameID	353
5.2.1.74	ChunkGain	353
5.2.1.75	ChunkGainSelector	353
5.2.1.76	ChunkHeight	353
5.2.1.77	ChunkImage	354
5.2.1.78	ChunkImageComponent	354
5.2.1.79	ChunkInferenceBoundingBoxResult	354
5.2.1.80	ChunkInferenceConfidence	354
5.2.1.81	ChunkInferenceFrameId	354
5.2.1.82	ChunkInferenceResult	354

5.2.1.83	ChunkLinePitch	354
5.2.1.84	ChunkLineStatusAll	354
5.2.1.85	ChunkModeActive	355
5.2.1.86	ChunkOffsetX	355
5.2.1.87	ChunkOffsetY	355
5.2.1.88	ChunkPartSelector	355
5.2.1.89	ChunkPixelDynamicRangeMax	355
5.2.1.90	ChunkPixelDynamicRangeMin	355
5.2.1.91	ChunkPixelFormat	355
5.2.1.92	ChunkRegionID	355
5.2.1.93	ChunkScan3dAxisMax	356
5.2.1.94	ChunkScan3dAxisMin	356
5.2.1.95	ChunkScan3dCoordinateOffset	356
5.2.1.96	ChunkScan3dCoordinateReferenceSelector	356
5.2.1.97	ChunkScan3dCoordinateReferenceValue	356
5.2.1.98	ChunkScan3dCoordinateScale	356
5.2.1.99	ChunkScan3dCoordinateSelector	356
5.2.1.100	ChunkScan3dCoordinateSystem	356
5.2.1.101	ChunkScan3dCoordinateSystemReference	357
5.2.1.102	ChunkScan3dCoordinateTransformSelector	357
5.2.1.103	ChunkScan3dDistanceUnit	357
5.2.1.104	ChunkScan3dInvalidDataFlag	357
5.2.1.105	ChunkScan3dInvalidDataValue	357
5.2.1.106	ChunkScan3dOutputMode	357
5.2.1.107	ChunkScan3dTransformValue	357
5.2.1.108	ChunkScanLineSelector	357
5.2.1.109	ChunkSelector	358
5.2.1.110	ChunkSequencerSetActive	358
5.2.1.111	ChunkSerialData	358
5.2.1.112	ChunkSerialDataLength	358

5.2.1.113 ChunkSerialReceiveOverflow	358
5.2.1.114 ChunkSourceID	358
5.2.1.115 ChunkStreamChannelID	358
5.2.1.116 ChunkTimerSelector	358
5.2.1.117 ChunkTimerValue	359
5.2.1.118 ChunkTimestamp	359
5.2.1.119 ChunkTimestampLatchValue	359
5.2.1.120 ChunkTransferBlockID	359
5.2.1.121 ChunkTransferQueueCurrentBlockCount	359
5.2.1.122 ChunkTransferStreamID	359
5.2.1.123 ChunkWidth	359
5.2.1.124 CIConfiguration	359
5.2.1.125 CITimeSlotsCount	360
5.2.1.126 ColorTransformationEnable	360
5.2.1.127 ColorTransformationSelector	360
5.2.1.128 ColorTransformationValue	360
5.2.1.129 ColorTransformationValueSelector	360
5.2.1.130 CompressionRatio	360
5.2.1.131 CounterDelay	360
5.2.1.132 CounterDuration	360
5.2.1.133 CounterEventActivation	361
5.2.1.134 CounterEventSource	361
5.2.1.135 CounterReset	361
5.2.1.136 CounterResetActivation	361
5.2.1.137 CounterResetSource	361
5.2.1.138 CounterSelector	361
5.2.1.139 CounterStatus	361
5.2.1.140 CounterTriggerActivation	361
5.2.1.141 CounterTriggerSource	362
5.2.1.142 CounterValue	362

5.2.1.143 CounterValueAtReset	362
5.2.1.144 CxpConnectionSelector	362
5.2.1.145 CxpConnectionTestErrorCount	362
5.2.1.146 CxpConnectionTestMode	362
5.2.1.147 CxpConnectionTestPacketCount	362
5.2.1.148 CxpLinkConfiguration	362
5.2.1.149 CxpLinkConfigurationPreferred	363
5.2.1.150 CxpLinkConfigurationStatus	363
5.2.1.151 CxpPoCxpAuto	363
5.2.1.152 CxpPoCxpStatus	363
5.2.1.153 CxpPoCxpTripReset	363
5.2.1.154 CxpPoCxpTurnOff	363
5.2.1.155 DecimationHorizontal	363
5.2.1.156 DecimationHorizontalMode	363
5.2.1.157 DecimationSelector	364
5.2.1.158 DecimationVertical	364
5.2.1.159 DecimationVerticalMode	364
5.2.1.160 DefectCorrectionMode	364
5.2.1.161 DefectCorrectStaticEnable	364
5.2.1.162 DefectTableApply	364
5.2.1.163 DefectTableCoordinateX	364
5.2.1.164 DefectTableCoordinateY	364
5.2.1.165 DefectTableFactoryRestore	365
5.2.1.166 DefectTableIndex	365
5.2.1.167 DefectTablePixelCount	365
5.2.1.168 DefectTableSave	365
5.2.1.169 Deinterlacing	365
5.2.1.170 DeviceCharacterSet	365
5.2.1.171 DeviceClockFrequency	365
5.2.1.172 DeviceClockSelector	365

5.2.1.173 DeviceConnectionSelector	366
5.2.1.174 DeviceConnectionSpeed	366
5.2.1.175 DeviceConnectionStatus	366
5.2.1.176 DeviceEventChannelCount	366
5.2.1.177 DeviceFamilyName	366
5.2.1.178 DeviceFeaturePersistenceEnd	366
5.2.1.179 DeviceFeaturePersistenceStart	366
5.2.1.180 DeviceFirmwareVersion	366
5.2.1.181 DeviceGenCPVersionMajor	367
5.2.1.182 DeviceGenCPVersionMinor	367
5.2.1.183 DeviceID	367
5.2.1.184 DeviceIndicatorMode	367
5.2.1.185 DeviceLinkBandwidthReserve	367
5.2.1.186 DeviceLinkCommandTimeout	367
5.2.1.187 DeviceLinkConnectionCount	367
5.2.1.188 DeviceLinkCurrentThroughput	367
5.2.1.189 DeviceLinkHeartbeatMode	368
5.2.1.190 DeviceLinkHeartbeatTimeout	368
5.2.1.191 DeviceLinkSelector	368
5.2.1.192 DeviceLinkSpeed	368
5.2.1.193 DeviceLinkThroughputLimit	368
5.2.1.194 DeviceLinkThroughputLimitMode	368
5.2.1.195 DeviceManifestEntrySelector	368
5.2.1.196 DeviceManifestPrimaryURL	368
5.2.1.197 DeviceManifestSchemaMajorVersion	369
5.2.1.198 DeviceManifestSchemaMinorVersion	369
5.2.1.199 DeviceManifestSecondaryURL	369
5.2.1.200 DeviceManifestXMLMajorVersion	369
5.2.1.201 DeviceManifestXMLMinorVersion	369
5.2.1.202 DeviceManifestXMLSubMinorVersion	369

5.2.1.203 DeviceManufacturerInfo	369
5.2.1.204 DeviceMaxThroughput	369
5.2.1.205 DeviceModelName	370
5.2.1.206 DevicePowerSupplySelector	370
5.2.1.207 DeviceRegistersCheck	370
5.2.1.208 DeviceRegistersEndianness	370
5.2.1.209 DeviceRegistersStreamingEnd	370
5.2.1.210 DeviceRegistersStreamingStart	370
5.2.1.211 DeviceRegistersValid	370
5.2.1.212 DeviceReset	370
5.2.1.213 DeviceScanType	371
5.2.1.214 DeviceSerialNumber	371
5.2.1.215 DeviceSerialPortBaudRate	371
5.2.1.216 DeviceSerialPortSelector	371
5.2.1.217 DeviceSFNCVersionMajor	371
5.2.1.218 DeviceSFNCVersionMinor	371
5.2.1.219 DeviceSFNCVersionSubMinor	371
5.2.1.220 DeviceStreamChannelCount	371
5.2.1.221 DeviceStreamChannelEndianness	372
5.2.1.222 DeviceStreamChannelLink	372
5.2.1.223 DeviceStreamChannelPacketSize	372
5.2.1.224 DeviceStreamChannelSelector	372
5.2.1.225 DeviceStreamChannelType	372
5.2.1.226 DeviceTapGeometry	372
5.2.1.227 DeviceTemperature	372
5.2.1.228 DeviceTemperatureSelector	372
5.2.1.229 DeviceTLType	373
5.2.1.230 DeviceTLVersionMajor	373
5.2.1.231 DeviceTLVersionMinor	373
5.2.1.232 DeviceTLVersionSubMinor	373

5.2.1.233 DeviceType	373
5.2.1.234 DeviceUptime	373
5.2.1.235 DeviceUserID	373
5.2.1.236 DeviceVendorName	373
5.2.1.237 DeviceVersion	374
5.2.1.238 EncoderDivider	374
5.2.1.239 EncoderMode	374
5.2.1.240 EncoderOutputMode	374
5.2.1.241 EncoderReset	374
5.2.1.242 EncoderResetActivation	374
5.2.1.243 EncoderResetSource	374
5.2.1.244 EncoderSelector	374
5.2.1.245 EncoderSourceA	375
5.2.1.246 EncoderSourceB	375
5.2.1.247 EncoderStatus	375
5.2.1.248 EncoderTimeout	375
5.2.1.249 EncoderValue	375
5.2.1.250 EncoderValueAtReset	375
5.2.1.251 EnumerationCount	375
5.2.1.252 EventAcquisitionEnd	375
5.2.1.253 EventAcquisitionEndFrameID	376
5.2.1.254 EventAcquisitionEndTimestamp	376
5.2.1.255 EventAcquisitionError	376
5.2.1.256 EventAcquisitionErrorFrameID	376
5.2.1.257 EventAcquisitionErrorTimestamp	376
5.2.1.258 EventAcquisitionStart	376
5.2.1.259 EventAcquisitionStartFrameID	376
5.2.1.260 EventAcquisitionStartTimestamp	376
5.2.1.261 EventAcquisitionTransferEnd	377
5.2.1.262 EventAcquisitionTransferEndFrameID	377

5.2.1.263 EventAcquisitionTransferEndTimestamp	377
5.2.1.264 EventAcquisitionTransferStart	377
5.2.1.265 EventAcquisitionTransferStartFrameID	377
5.2.1.266 EventAcquisitionTransferStartTimestamp	377
5.2.1.267 EventAcquisitionTrigger	377
5.2.1.268 EventAcquisitionTriggerFrameID	377
5.2.1.269 EventAcquisitionTriggerTimestamp	378
5.2.1.270 EventActionLate	378
5.2.1.271 EventActionLateFrameID	378
5.2.1.272 EventActionLateTimestamp	378
5.2.1.273 EventCounter0End	378
5.2.1.274 EventCounter0EndFrameID	378
5.2.1.275 EventCounter0EndTimestamp	378
5.2.1.276 EventCounter0Start	378
5.2.1.277 EventCounter0StartFrameID	379
5.2.1.278 EventCounter0StartTimestamp	379
5.2.1.279 EventCounter1End	379
5.2.1.280 EventCounter1EndFrameID	379
5.2.1.281 EventCounter1EndTimestamp	379
5.2.1.282 EventCounter1Start	379
5.2.1.283 EventCounter1StartFrameID	379
5.2.1.284 EventCounter1StartTimestamp	379
5.2.1.285 EventEncoder0Restarted	380
5.2.1.286 EventEncoder0RestartedFrameID	380
5.2.1.287 EventEncoder0RestartedTimestamp	380
5.2.1.288 EventEncoder0Stopped	380
5.2.1.289 EventEncoder0StoppedFrameID	380
5.2.1.290 EventEncoder0StoppedTimestamp	380
5.2.1.291 EventEncoder1Restarted	380
5.2.1.292 EventEncoder1RestartedFrameID	380

5.2.1.293 EventEncoder1RestartedTimestamp	381
5.2.1.294 EventEncoder1Stopped	381
5.2.1.295 EventEncoder1StoppedFrameID	381
5.2.1.296 EventEncoder1StoppedTimestamp	381
5.2.1.297 EventError	381
5.2.1.298 EventErrorCode	381
5.2.1.299 EventErrorFrameID	381
5.2.1.300 EventErrorTimestamp	381
5.2.1.301 EventExposureEnd	382
5.2.1.302 EventExposureEndFrameID	382
5.2.1.303 EventExposureEndTimestamp	382
5.2.1.304 EventExposureStart	382
5.2.1.305 EventExposureStartFrameID	382
5.2.1.306 EventExposureStartTimestamp	382
5.2.1.307 EventFrameBurstEnd	382
5.2.1.308 EventFrameBurstEndFrameID	382
5.2.1.309 EventFrameBurstEndTimestamp	383
5.2.1.310 EventFrameBurstStart	383
5.2.1.311 EventFrameBurstStartFrameID	383
5.2.1.312 EventFrameBurstStartTimestamp	383
5.2.1.313 EventFrameEnd	383
5.2.1.314 EventFrameEndFrameID	383
5.2.1.315 EventFrameEndTimestamp	383
5.2.1.316 EventFrameStart	383
5.2.1.317 EventFrameStartFrameID	384
5.2.1.318 EventFrameStartTimestamp	384
5.2.1.319 EventFrameTransferEnd	384
5.2.1.320 EventFrameTransferEndFrameID	384
5.2.1.321 EventFrameTransferEndTimestamp	384
5.2.1.322 EventFrameTransferStart	384

5.2.1.323 EventFrameTransferStartFrameID	384
5.2.1.324 EventFrameTransferStartTimestamp	384
5.2.1.325 EventFrameTrigger	385
5.2.1.326 EventFrameTriggerFrameID	385
5.2.1.327 EventFrameTriggerTimestamp	385
5.2.1.328 EventLine0AnyEdge	385
5.2.1.329 EventLine0AnyEdgeFrameID	385
5.2.1.330 EventLine0AnyEdgeTimestamp	385
5.2.1.331 EventLine0FallingEdge	385
5.2.1.332 EventLine0FallingEdgeFrameID	385
5.2.1.333 EventLine0FallingEdgeTimestamp	386
5.2.1.334 EventLine0RisingEdge	386
5.2.1.335 EventLine0RisingEdgeFrameID	386
5.2.1.336 EventLine0RisingEdgeTimestamp	386
5.2.1.337 EventLine1AnyEdge	386
5.2.1.338 EventLine1AnyEdgeFrameID	386
5.2.1.339 EventLine1AnyEdgeTimestamp	386
5.2.1.340 EventLine1FallingEdge	386
5.2.1.341 EventLine1FallingEdgeFrameID	387
5.2.1.342 EventLine1FallingEdgeTimestamp	387
5.2.1.343 EventLine1RisingEdge	387
5.2.1.344 EventLine1RisingEdgeFrameID	387
5.2.1.345 EventLine1RisingEdgeTimestamp	387
5.2.1.346 EventLinkSpeedChange	387
5.2.1.347 EventLinkSpeedChangeFrameID	387
5.2.1.348 EventLinkSpeedChangeTimestamp	387
5.2.1.349 EventLinkTrigger0	388
5.2.1.350 EventLinkTrigger0FrameID	388
5.2.1.351 EventLinkTrigger0Timestamp	388
5.2.1.352 EventLinkTrigger1	388

5.2.1.353 EventLinkTrigger1FrameID	388
5.2.1.354 EventLinkTrigger1Timestamp	388
5.2.1.355 EventNotification	388
5.2.1.356 EventSelector	388
5.2.1.357 EventSequencerSetChange	389
5.2.1.358 EventSequencerSetChangeFrameID	389
5.2.1.359 EventSequencerSetChangeTimestamp	389
5.2.1.360 EventSerialData	389
5.2.1.361 EventSerialDataLength	389
5.2.1.362 EventSerialPortReceive	389
5.2.1.363 EventSerialPortReceiveTimestamp	389
5.2.1.364 EventSerialReceiveOverflow	389
5.2.1.365 EventStream0TransferBlockEnd	390
5.2.1.366 EventStream0TransferBlockEndFrameID	390
5.2.1.367 EventStream0TransferBlockEndTimestamp	390
5.2.1.368 EventStream0TransferBlockStart	390
5.2.1.369 EventStream0TransferBlockStartFrameID	390
5.2.1.370 EventStream0TransferBlockStartTimestamp	390
5.2.1.371 EventStream0TransferBlockTrigger	390
5.2.1.372 EventStream0TransferBlockTriggerFrameID	390
5.2.1.373 EventStream0TransferBlockTriggerTimestamp	391
5.2.1.374 EventStream0TransferBurstEnd	391
5.2.1.375 EventStream0TransferBurstEndFrameID	391
5.2.1.376 EventStream0TransferBurstEndTimestamp	391
5.2.1.377 EventStream0TransferBurstStart	391
5.2.1.378 EventStream0TransferBurstStartFrameID	391
5.2.1.379 EventStream0TransferBurstStartTimestamp	391
5.2.1.380 EventStream0TransferEnd	391
5.2.1.381 EventStream0TransferEndFrameID	392
5.2.1.382 EventStream0TransferEndTimestamp	392

5.2.1.383 EventStream0TransferOverflow	392
5.2.1.384 EventStream0TransferOverflowFrameID	392
5.2.1.385 EventStream0TransferOverflowTimestamp	392
5.2.1.386 EventStream0TransferPause	392
5.2.1.387 EventStream0TransferPauseFrameID	392
5.2.1.388 EventStream0TransferPauseTimestamp	392
5.2.1.389 EventStream0TransferResume	393
5.2.1.390 EventStream0TransferResumeFrameID	393
5.2.1.391 EventStream0TransferResumeTimestamp	393
5.2.1.392 EventStream0TransferStart	393
5.2.1.393 EventStream0TransferStartFrameID	393
5.2.1.394 EventStream0TransferStartTimestamp	393
5.2.1.395 EventTest	393
5.2.1.396 EventTestTimestamp	393
5.2.1.397 EventTimer0End	394
5.2.1.398 EventTimer0EndFrameID	394
5.2.1.399 EventTimer0EndTimestamp	394
5.2.1.400 EventTimer0Start	394
5.2.1.401 EventTimer0StartFrameID	394
5.2.1.402 EventTimer0StartTimestamp	394
5.2.1.403 EventTimer1End	394
5.2.1.404 EventTimer1EndFrameID	394
5.2.1.405 EventTimer1EndTimestamp	395
5.2.1.406 EventTimer1Start	395
5.2.1.407 EventTimer1StartFrameID	395
5.2.1.408 EventTimer1StartTimestamp	395
5.2.1.409 ExposureActiveMode	395
5.2.1.410 ExposureAuto	395
5.2.1.411 ExposureMode	395
5.2.1.412 ExposureTime	395

5.2.1.413 ExposureTimeMode	396
5.2.1.414 ExposureTimeSelector	396
5.2.1.415 FactoryReset	396
5.2.1.416 FileAccessBuffer	396
5.2.1.417 FileAccessLength	396
5.2.1.418 FileAccessOffset	396
5.2.1.419 FileOpenMode	396
5.2.1.420 FileOperationExecute	396
5.2.1.421 FileOperationResult	397
5.2.1.422 FileOperationSelector	397
5.2.1.423 FileOperationStatus	397
5.2.1.424 FileSelector	397
5.2.1.425 FileSize	397
5.2.1.426 Gain	397
5.2.1.427 GainAuto	397
5.2.1.428 GainAutoBalance	397
5.2.1.429 GainSelector	398
5.2.1.430 Gamma	398
5.2.1.431 GammaEnable	398
5.2.1.432 GevActiveLinkCount	398
5.2.1.433 GevCCP	398
5.2.1.434 GevCurrentDefaultGateway	398
5.2.1.435 GevCurrentIPAddress	398
5.2.1.436 GevCurrentIPConfigurationDHCP	398
5.2.1.437 GevCurrentIPConfigurationLLA	399
5.2.1.438 GevCurrentIPConfigurationPersistentIP	399
5.2.1.439 GevCurrentPhysicalLinkConfiguration	399
5.2.1.440 GevCurrentSubnetMask	399
5.2.1.441 GevDiscoveryAckDelay	399
5.2.1.442 GevFirstURL	399

5.2.1.443	GevGVCPExtendedStatusCodes	399
5.2.1.444	GevGVCPExtendedStatusCodesSelector	399
5.2.1.445	GevGVCPHeartbeatDisable	400
5.2.1.446	GevGVCPPendingAck	400
5.2.1.447	GevGVCPPendingTimeout	400
5.2.1.448	GevGVSPExtendedIDMode	400
5.2.1.449	GevHeartbeatTimeout	400
5.2.1.450	GevIEEE1588	400
5.2.1.451	GevIEEE1588ClockAccuracy	400
5.2.1.452	GevIEEE1588Mode	400
5.2.1.453	GevIEEE1588Status	401
5.2.1.454	GevInterfaceSelector	401
5.2.1.455	GevIPConfigurationStatus	401
5.2.1.456	GevMACAddress	401
5.2.1.457	GevMCDA	401
5.2.1.458	GevMCPHostPort	401
5.2.1.459	GevMCRC	401
5.2.1.460	GevMCSP	401
5.2.1.461	GevMCTT	402
5.2.1.462	GevNumberOfInterfaces	402
5.2.1.463	GevPAUSEFrameReception	402
5.2.1.464	GevPAUSEFrameTransmission	402
5.2.1.465	GevPersistentDefaultGateway	402
5.2.1.466	GevPersistentIPAddress	402
5.2.1.467	GevPersistentSubnetMask	402
5.2.1.468	GevPhysicalLinkConfiguration	402
5.2.1.469	GevPrimaryApplicationIPAddress	403
5.2.1.470	GevPrimaryApplicationSocket	403
5.2.1.471	GevPrimaryApplicationSwitchoverKey	403
5.2.1.472	GevSCCFGAllInTransmission	403

5.2.1.473	GevSCCFGExtendedChunkData	403
5.2.1.474	GevSCCFGPacketResendDestination	403
5.2.1.475	GevSCCFGUnconditionalStreaming	403
5.2.1.476	GevSCDA	403
5.2.1.477	GevSCPD	404
5.2.1.478	GevSCPDDirection	404
5.2.1.479	GevSCPHostPort	404
5.2.1.480	GevSCPIInterfaceIndex	404
5.2.1.481	GevSCPSBigEndian	404
5.2.1.482	GevSCPSDoNotFragment	404
5.2.1.483	GevSCPSFireTestPacket	404
5.2.1.484	GevSCPSPacketSize	404
5.2.1.485	GevSCSP	405
5.2.1.486	GevSCZoneConfigurationLock	405
5.2.1.487	GevSCZoneCount	405
5.2.1.488	GevSCZoneDirectionAll	405
5.2.1.489	GevSecondURL	405
5.2.1.490	GevStreamChannelSelector	405
5.2.1.491	GevSupportedOption	405
5.2.1.492	GevSupportedOptionSelector	405
5.2.1.493	GevTimestampTickFrequency	406
5.2.1.494	GuiXmlManifestAddress	406
5.2.1.495	Height	406
5.2.1.496	HeightMax	406
5.2.1.497	ImageComponentEnable	406
5.2.1.498	ImageComponentSelector	406
5.2.1.499	ImageCompressionBitrate	406
5.2.1.500	ImageCompressionJPEGFormatOption	406
5.2.1.501	ImageCompressionMode	407
5.2.1.502	ImageCompressionQuality	407

5.2.1.503 ImageCompressionRateOption	407
5.2.1.504 IspEnable	407
5.2.1.505 LineFilterWidth	407
5.2.1.506 LineFormat	407
5.2.1.507 LineInputFilterSelector	407
5.2.1.508 LineInverter	407
5.2.1.509 LineMode	408
5.2.1.510 LinePitch	408
5.2.1.511 LineSelector	408
5.2.1.512 LineSource	408
5.2.1.513 LineStatus	408
5.2.1.514 LineStatusAll	408
5.2.1.515 LinkErrorCount	408
5.2.1.516 LinkUptime	408
5.2.1.517 LogicBlockLUTInputActivation	409
5.2.1.518 LogicBlockLUTInputSelector	409
5.2.1.519 LogicBlockLUTInputSource	409
5.2.1.520 LogicBlockLUTOutputValue	409
5.2.1.521 LogicBlockLUTOutputValueAll	409
5.2.1.522 LogicBlockLUTRowIndex	409
5.2.1.523 LogicBlockLUTSelector	409
5.2.1.524 LogicBlockSelector	409
5.2.1.525 LUTEnable	410
5.2.1.526 LUTIndex	410
5.2.1.527 LUTSelector	410
5.2.1.528 LUTValue	410
5.2.1.529 LUTValueAll	410
5.2.1.530 MaxDeviceResetTime	410
5.2.1.531 OffsetX	410
5.2.1.532 OffsetY	410

5.2.1.533 PacketResendRequestCount	411
5.2.1.534 PayloadSize	411
5.2.1.535 PixelColorFilter	411
5.2.1.536 PixelDynamicRangeMax	411
5.2.1.537 PixelDynamicRangeMin	411
5.2.1.538 PixelFormat	411
5.2.1.539 PixelFormatInfoID	411
5.2.1.540 PixelFormatInfoSelector	411
5.2.1.541 PixelSize	412
5.2.1.542 PowerSupplyCurrent	412
5.2.1.543 PowerSupplyVoltage	412
5.2.1.544 RegionDestination	412
5.2.1.545 RegionMode	412
5.2.1.546 RegionSelector	412
5.2.1.547 ReverseX	412
5.2.1.548 ReverseY	412
5.2.1.549 RgbTransformLightSource	413
5.2.1.550 Saturation	413
5.2.1.551 SaturationEnable	413
5.2.1.552 Scan3dAxisMax	413
5.2.1.553 Scan3dAxisMin	413
5.2.1.554 Scan3dCoordinateOffset	413
5.2.1.555 Scan3dCoordinateReferenceSelector	413
5.2.1.556 Scan3dCoordinateReferenceValue	413
5.2.1.557 Scan3dCoordinateScale	414
5.2.1.558 Scan3dCoordinateSelector	414
5.2.1.559 Scan3dCoordinateSystem	414
5.2.1.560 Scan3dCoordinateSystemReference	414
5.2.1.561 Scan3dCoordinateTransformSelector	414
5.2.1.562 Scan3dDistanceUnit	414

5.2.1.563 Scan3dInvalidDataFlag	414
5.2.1.564 Scan3dInvalidDataValue	414
5.2.1.565 Scan3dOutputMode	415
5.2.1.566 Scan3dTransformValue	415
5.2.1.567 SensorDescription	415
5.2.1.568 SensorDigitizationTaps	415
5.2.1.569 SensorHeight	415
5.2.1.570 SensorShutterMode	415
5.2.1.571 SensorTaps	415
5.2.1.572 SensorWidth	415
5.2.1.573 SequencerConfigurationMode	416
5.2.1.574 SequencerConfigurationValid	416
5.2.1.575 SequencerFeatureEnable	416
5.2.1.576 SequencerMode	416
5.2.1.577 SequencerPathSelector	416
5.2.1.578 SequencerSetActive	416
5.2.1.579 SequencerSetLoad	416
5.2.1.580 SequencerSetNext	416
5.2.1.581 SequencerSetSave	417
5.2.1.582 SequencerSetSelector	417
5.2.1.583 SequencerSetStart	417
5.2.1.584 SequencerSetValid	417
5.2.1.585 SequencerTriggerActivation	417
5.2.1.586 SequencerTriggerSource	417
5.2.1.587 SerialPortBaudRate	417
5.2.1.588 SerialPortDataBits	417
5.2.1.589 SerialPortParity	418
5.2.1.590 SerialPortSelector	418
5.2.1.591 SerialPortSource	418
5.2.1.592 SerialPortStopBits	418

5.2.1.593 SerialReceiveFramingErrorCount	418
5.2.1.594 SerialReceiveParityErrorCount	418
5.2.1.595 SerialReceiveQueueClear	418
5.2.1.596 SerialReceiveQueueCurrentCharacterCount	418
5.2.1.597 SerialReceiveQueueMaxCharacterCount	419
5.2.1.598 SerialTransmitQueueCurrentCharacterCount	419
5.2.1.599 SerialTransmitQueueMaxCharacterCount	419
5.2.1.600 Sharpening	419
5.2.1.601 SharpeningAuto	419
5.2.1.602 SharpeningEnable	419
5.2.1.603 SharpeningThreshold	419
5.2.1.604 SoftwareSignalPulse	419
5.2.1.605 SoftwareSignalSelector	420
5.2.1.606 SourceCount	420
5.2.1.607 SourceSelector	420
5.2.1.608 Test0001	420
5.2.1.609 TestEventGenerate	420
5.2.1.610 TestPattern	420
5.2.1.611 TestPatternGeneratorSelector	420
5.2.1.612 TestPendingAck	420
5.2.1.613 TimerDelay	421
5.2.1.614 TimerDuration	421
5.2.1.615 TimerReset	421
5.2.1.616 TimerSelector	421
5.2.1.617 TimerStatus	421
5.2.1.618 TimerTriggerActivation	421
5.2.1.619 TimerTriggerSource	421
5.2.1.620 TimerValue	421
5.2.1.621 Timestamp	422
5.2.1.622 TimestampLatch	422

5.2.1.623 TimestampLatchValue	422
5.2.1.624 TimestampReset	422
5.2.1.625 TLParamsLocked	422
5.2.1.626 TransferAbort	422
5.2.1.627 TransferBlockCount	422
5.2.1.628 TransferBurstCount	422
5.2.1.629 TransferComponentSelector	423
5.2.1.630 TransferControlMode	423
5.2.1.631 TransferOperationMode	423
5.2.1.632 TransferPause	423
5.2.1.633 TransferQueueCurrentBlockCount	423
5.2.1.634 TransferQueueMaxBlockCount	423
5.2.1.635 TransferQueueMode	423
5.2.1.636 TransferQueueOverflowCount	423
5.2.1.637 TransferResume	424
5.2.1.638 TransferSelector	424
5.2.1.639 TransferStart	424
5.2.1.640 TransferStatus	424
5.2.1.641 TransferStatusSelector	424
5.2.1.642 TransferStop	424
5.2.1.643 TransferStreamChannel	424
5.2.1.644 TransferTriggerActivation	424
5.2.1.645 TransferTriggerMode	425
5.2.1.646 TransferTriggerSelector	425
5.2.1.647 TransferTriggerSource	425
5.2.1.648 TriggerActivation	425
5.2.1.649 TriggerDelay	425
5.2.1.650 TriggerDivider	425
5.2.1.651 TriggerEventTest	425
5.2.1.652 TriggerMode	425

5.2.1.653 TriggerMultiplier	426
5.2.1.654 TriggerOverlap	426
5.2.1.655 TriggerSelector	426
5.2.1.656 TriggerSoftware	426
5.2.1.657 TriggerSource	426
5.2.1.658 UserOutputSelector	426
5.2.1.659 UserOutputValue	426
5.2.1.660 UserOutputValueAll	426
5.2.1.661 UserOutputValueAllMask	427
5.2.1.662 UserSetDefault	427
5.2.1.663 UserSetFeatureEnable	427
5.2.1.664 UserSetLoad	427
5.2.1.665 UserSetSave	427
5.2.1.666 UserSetSelector	427
5.2.1.667 V3_3Enable	427
5.2.1.668 WhiteClip	427
5.2.1.669 WhiteClipSelector	428
5.2.1.670 Width	428
5.2.1.671 WidthMax	428
5.3 quickSpinTLDevice Struct Reference	428
5.3.1 Field Documentation	429
5.3.1.1 DeviceAccessStatus	429
5.3.1.2 DeviceCurrentSpeed	429
5.3.1.3 DeviceDisplayName	429
5.3.1.4 DeviceDriverVersion	429
5.3.1.5 DeviceEndiannessMechanism	430
5.3.1.6 DeviceID	430
5.3.1.7 DeviceInstanceld	430
5.3.1.8 DevicesUpdater	430
5.3.1.9 DeviceLinkSpeed	430

5.3.1.10	DeviceLocation	430
5.3.1.11	DeviceModelName	430
5.3.1.12	DeviceMulticastMonitorMode	430
5.3.1.13	DeviceSerialNumber	431
5.3.1.14	DeviceType	431
5.3.1.15	DeviceU3VProtocol	431
5.3.1.16	DeviceUserID	431
5.3.1.17	DeviceVendorName	431
5.3.1.18	DeviceVersion	431
5.3.1.19	GenICamXMLLocation	431
5.3.1.20	GenICamXMLPath	431
5.3.1.21	GevCCP	432
5.3.1.22	GevDeviceAutoForceIP	432
5.3.1.23	GevDeviceDiscoverMaximumPacketSize	432
5.3.1.24	GevDeviceForceGateway	432
5.3.1.25	GevDeviceForceIP	432
5.3.1.26	GevDeviceForceIPAddress	432
5.3.1.27	GevDeviceForceSubnetMask	432
5.3.1.28	GevDeviceGateway	432
5.3.1.29	GevDeviceIPAddress	433
5.3.1.30	GevDeviceIsWrongSubnet	433
5.3.1.31	GevDeviceMACAddress	433
5.3.1.32	GevDeviceMaximumPacketSize	433
5.3.1.33	GevDeviceMaximumRetryCount	433
5.3.1.34	GevDeviceModelsBigEndian	433
5.3.1.35	GevDevicePort	433
5.3.1.36	GevDeviceReadAndWriteTimeout	433
5.3.1.37	GevDeviceSubnetMask	434
5.3.1.38	GevVersionMajor	434
5.3.1.39	GevVersionMinor	434

5.3.1.40	GUIXMLLocation	434
5.3.1.41	GUIXMLPath	434
5.4	quickSpinTLInterface Struct Reference	434
5.4.1	Field Documentation	435
5.4.1.1	ActionCommand	435
5.4.1.2	DeviceAccessStatus	435
5.4.1.3	DeviceCount	436
5.4.1.4	DeviceID	436
5.4.1.5	DeviceModelName	436
5.4.1.6	DeviceSelector	436
5.4.1.7	DeviceSerialNumber	436
5.4.1.8	DeviceUnlock	436
5.4.1.9	DeviceUpdateList	436
5.4.1.10	DeviceVendorName	436
5.4.1.11	FilterDriverStatus	437
5.4.1.12	GevActionDeviceKey	437
5.4.1.13	GevActionGroupKey	437
5.4.1.14	GevActionGroupMask	437
5.4.1.15	GevActionTime	437
5.4.1.16	GevDeviceAutoForceIP	437
5.4.1.17	GevDeviceForceGateway	437
5.4.1.18	GevDeviceForceIP	437
5.4.1.19	GevDeviceForceIPAddress	438
5.4.1.20	GevDeviceForceSubnetMask	438
5.4.1.21	GevDeviceGateway	438
5.4.1.22	GevDeviceIPAddress	438
5.4.1.23	GevDeviceMACAddress	438
5.4.1.24	GevDeviceSubnetMask	438
5.4.1.25	GevInterfaceGateway	438
5.4.1.26	GevInterfaceGatewaySelector	438

5.4.1.27	GevInterfaceMACAddress	439
5.4.1.28	GevInterfaceMTU	439
5.4.1.29	GevInterfaceReceiveLinkSpeed	439
5.4.1.30	GevInterfaceSubnetIPAddress	439
5.4.1.31	GevInterfaceSubnetMask	439
5.4.1.32	GevInterfaceSubnetSelector	439
5.4.1.33	GevInterfaceTransmitLinkSpeed	439
5.4.1.34	HostAdapterDriverVersion	439
5.4.1.35	HostAdapterName	440
5.4.1.36	HostAdapterVendor	440
5.4.1.37	IncompatibleDeviceCount	440
5.4.1.38	IncompatibleDeviceID	440
5.4.1.39	IncompatibleDeviceModelName	440
5.4.1.40	IncompatibleDeviceSelector	440
5.4.1.41	IncompatibleDeviceVendorName	440
5.4.1.42	IncompatibleGevDeviceIPAddress	440
5.4.1.43	IncompatibleGevDeviceMACAddress	441
5.4.1.44	IncompatibleGevDeviceSubnetMask	441
5.4.1.45	InterfaceDisplayName	441
5.4.1.46	InterfaceID	441
5.4.1.47	InterfaceType	441
5.4.1.48	POEStatus	441
5.5	quickSpinTLStream Struct Reference	442
5.5.1	Field Documentation	442
5.5.1.1	GevFailedPacketCount	442
5.5.1.2	GevMaximumNumberResendRequests	442
5.5.1.3	GevPacketResendMode	443
5.5.1.4	GevPacketResendTimeout	443
5.5.1.5	GevResendPacketCount	443
5.5.1.6	GevResendRequestCount	443

5.5.1.7	GevTotalPacketCount	443
5.5.1.8	StreamAnnounceBufferMinimum	443
5.5.1.9	StreamAnnouncedBufferCount	443
5.5.1.10	StreamBlockTransferSize	443
5.5.1.11	StreamBufferAlignment	444
5.5.1.12	StreamBufferCountManual	444
5.5.1.13	StreamBufferCountMax	444
5.5.1.14	StreamBufferCountMode	444
5.5.1.15	StreamBufferCountResult	444
5.5.1.16	StreamBufferHandlingMode	444
5.5.1.17	StreamChunkCountMaximum	444
5.5.1.18	StreamCRCCheckEnable	444
5.5.1.19	StreamDeliveredFrameCount	445
5.5.1.20	StreamFailedBufferCount	445
5.5.1.21	StreamID	445
5.5.1.22	StreamInputBufferCount	445
5.5.1.23	StreamIsGrabbing	445
5.5.1.24	StreamLostFrameCount	445
5.5.1.25	StreamOutputBufferCount	445
5.5.1.26	StreamStartedFrameCount	445
5.5.1.27	StreamType	446
5.6	quickSpinTLSysSystem Struct Reference	446
5.6.1	Field Documentation	446
5.6.1.1	EnumerateGEVInterfaces	446
5.6.1.2	GenTLSFNCVersionMajor	447
5.6.1.3	GenTLSFNCVersionMinor	447
5.6.1.4	GenTLSFNCVersionSubMinor	447
5.6.1.5	GenTLVersionMajor	447
5.6.1.6	GenTLVersionMinor	447
5.6.1.7	GevInterfaceDefaultGateway	447

5.6.1.8	GevInterfaceDefaultIPAddress	447
5.6.1.9	GevInterfaceDefaultSubnetMask	447
5.6.1.10	GevInterfaceMACAddress	448
5.6.1.11	GevVersionMajor	448
5.6.1.12	GevVersionMinor	448
5.6.1.13	InterfaceDisplayName	448
5.6.1.14	InterfaceID	448
5.6.1.15	InterfaceSelector	448
5.6.1.16	InterfaceUpdateList	448
5.6.1.17	TLDisplayName	448
5.6.1.18	TLFileName	449
5.6.1.19	TLID	449
5.6.1.20	TLModelName	449
5.6.1.21	TLPath	449
5.6.1.22	TLType	449
5.6.1.23	TLVendorName	449
5.6.1.24	TLVersion	449
5.7	spinAVIOption Struct Reference	450
5.7.1	Detailed Description	450
5.7.2	Field Documentation	450
5.7.2.1	frameRate	450
5.7.2.2	reserved	450
5.8	spinBMPOption Struct Reference	450
5.8.1	Detailed Description	451
5.8.2	Field Documentation	451
5.8.2.1	indexedColor_8bit	451
5.8.2.2	reserved	451
5.9	spinChunkData Struct Reference	451
5.9.1	Detailed Description	452
5.9.2	Field Documentation	452

5.9.2.1	m_blackLevel	452
5.9.2.2	m_counterValue	453
5.9.2.3	m_cRC	453
5.9.2.4	m_encoderValue	453
5.9.2.5	m_exposureEndLineStatusAll	453
5.9.2.6	m_exposureTime	453
5.9.2.7	m_frameID	453
5.9.2.8	m_gain	453
5.9.2.9	m_height	453
5.9.2.10	m_image	454
5.9.2.11	m_inferenceConfidence	454
5.9.2.12	m_inferenceFrameId	454
5.9.2.13	m_inferenceResult	454
5.9.2.14	m_linePitch	454
5.9.2.15	m_lineStatusAll	454
5.9.2.16	m_offsetX	454
5.9.2.17	m_offsetY	454
5.9.2.18	m_partSelector	455
5.9.2.19	m_pixelDynamicRangeMax	455
5.9.2.20	m_pixelDynamicRangeMin	455
5.9.2.21	m_scan3dAxisMax	455
5.9.2.22	m_scan3dAxisMin	455
5.9.2.23	m_scan3dCoordinateOffset	455
5.9.2.24	m_scan3dCoordinateReferenceValue	455
5.9.2.25	m_scan3dCoordinateScale	455
5.9.2.26	m_scan3dInvalidDataValue	456
5.9.2.27	m_scan3dTransformValue	456
5.9.2.28	m_scanLineSelector	456
5.9.2.29	m_sequencerSetActive	456
5.9.2.30	m_serialDataLength	456

5.9.2.31	m_streamChannelID	456
5.9.2.32	m_timerValue	456
5.9.2.33	m_timestamp	456
5.9.2.34	m_timestampLatchValue	457
5.9.2.35	m_transferBlockID	457
5.9.2.36	m_transferQueueCurrentBlockCount	457
5.9.2.37	m_width	457
5.10	spinH264Option Struct Reference	457
5.10.1	Detailed Description	458
5.10.2	Field Documentation	458
5.10.2.1	bitrate	458
5.10.2.2	frameRate	458
5.10.2.3	height	458
5.10.2.4	reserved	458
5.10.2.5	width	458
5.11	spinJPEGOption Struct Reference	459
5.11.1	Detailed Description	459
5.11.2	Field Documentation	459
5.11.2.1	progressive	459
5.11.2.2	quality	459
5.11.2.3	reserved	460
5.12	spinJPG2Option Struct Reference	460
5.12.1	Detailed Description	460
5.12.2	Field Documentation	460
5.12.2.1	quality	460
5.12.2.2	reserved	460
5.13	spinLibraryVersion Struct Reference	461
5.13.1	Detailed Description	461
5.13.2	Field Documentation	461
5.13.2.1	build	461

5.13.2.2	major	461
5.13.2.3	minor	461
5.13.2.4	type	462
5.14	spinMJPGOOption Struct Reference	462
5.14.1	Detailed Description	462
5.14.2	Field Documentation	462
5.14.2.1	frameRate	462
5.14.2.2	quality	462
5.14.2.3	reserved	463
5.15	spinPGMOOption Struct Reference	463
5.15.1	Detailed Description	463
5.15.2	Field Documentation	463
5.15.2.1	binaryFile	463
5.15.2.2	reserved	463
5.16	spinPNGOption Struct Reference	464
5.16.1	Detailed Description	464
5.16.2	Field Documentation	464
5.16.2.1	compressionLevel	464
5.16.2.2	interlaced	464
5.16.2.3	reserved	464
5.17	spinPPMOption Struct Reference	465
5.17.1	Detailed Description	465
5.17.2	Field Documentation	465
5.17.2.1	binaryFile	465
5.17.2.2	reserved	465
5.18	spinTIFFOption Struct Reference	465
5.18.1	Detailed Description	466
5.18.2	Field Documentation	466
5.18.2.1	compression	466
5.18.2.2	reserved	466

6 File Documentation	467
6.1 include/spinc/CameraDefsC.h File Reference	467
6.2 include/spinc/ChunkDataDefC.h File Reference	500
6.3 include/spinc/QuickSpinC.h File Reference	501
6.4 include/spinc/QuickSpinDefsC.h File Reference	501
6.4.1 Typedef Documentation	502
6.4.1.1 quickSpinBooleanNode	502
6.4.1.2 quickSpinCommandNode	502
6.4.1.3 quickSpinEnumerationNode	502
6.4.1.4 quickSpinFloatNode	503
6.4.1.5 quickSpinIntegerNode	503
6.4.1.6 quickSpinRegisterNode	503
6.4.1.7 quickSpinStringNode	503
6.5 include/spinc/SpinnakerC.h File Reference	503
6.5.1 Function Documentation	512
6.5.1.1 spinCameraForceIP()	512
6.6 include/spinc/SpinnakerDefsC.h File Reference	512
6.7 include/spinc/SpinnakerGenApiC.h File Reference	517
6.8 include/spinc/SpinnakerGenApiDefsC.h File Reference	521
6.9 include/spinc/SpinnakerPlatformC.h File Reference	524
6.9.1 Macro Definition Documentation	524
6.9.1.1 SPINNAKERC_API	525
6.10 include/spinc/SpinVideoC.h File Reference	525
6.11 include/spinc/TransportLayerDefsC.h File Reference	526
6.12 include/spinc/TransportLayerDeviceC.h File Reference	528
6.13 include/spinc/TransportLayerInterfaceC.h File Reference	528
6.14 include/spinc/TransportLayerStreamC.h File Reference	529
6.15 include/spinc/TransportLayerSystemC.h File Reference	530
Index	531

Chapter 1

Module Index

1.1 Modules

Here is a list of all modules:

Spinnaker C QuickSpin API	125
QuickSpin Access	126
Transport Layer Enumerations	317
TLDevice Structures	326
TLInterface Structures	327
TLStream Structures	328
TLSystem Structures	329
Spinnaker C API	128
Spinnaker C Definitions	7
Camera Enumerations	9
Chunk Data Structures	124
Spinnaker C Handles	233
Spinnaker C Function Signatures	237
Spinnaker C Enumerations	239
Spinnaker C Structures	247
Error Handling	130
System Access	135
InterfaceList Access	149
CameraList Access	153
Interface Access	159
Camera Access	167
SpinVideo Recording Access	314
Image Access	179
Event Access	208
ImageStatistics Access	215
Logging Event Data Access	224
Device Event Data Access	229
Chunk data access	232
Spinnaker C GenICam API	249
Node Map Access	251
Node Access	254
IValue Access	266
String Access	269
Integer Access	273

IFloat Access	278
IEnumeration Access	283
IEnumEntry Access	287
IBoolean Access	290
ICommand Access	292
ICategory Access	294
IRegister Access	296
Spinnaker C GenICam Handles	301
Spinnaker C GenICam Enumerations	303

Chapter 2

Data Structure Index

2.1 Data Structures

Here are the data structures with brief descriptions:

actionCommandResult	
Action Command Result	331
quickSpin	332
quickSpinTLDevice	428
quickSpinTLInterface	434
quickSpinTLStream	442
quickSpinTLSystem	446
spinAVIOption	
Options for saving uncompressed videos	450
spinBMPOption	
Options for saving BMP images	450
spinChunkData	
The type of information that can be obtained from image chunk data	451
spinH264Option	
Options for saving H264 videos	457
spinJPEGOption	
Options for saving JPEG images	459
spinJPG2Option	
Options for saving JPEG 2000 images	460
spinLibraryVersion	
Provides easier access to the current version of Spinnaker	461
spinMJPGOption	
Options for saving MJPG videos	462
spinPGMOption	
Options for saving PGM images	463
spinPNGOption	
Options for saving PNG images	464
spinPPMOption	
Options for saving PPM images	465
spinTIFFOption	
Options for saving TIFF images	465

Chapter 3

File Index

3.1 File List

Here is a list of all files with brief descriptions:

include/spinc/ CameraDefsC.h	467
include/spinc/ ChunkDataDefC.h	500
include/spinc/ QuickSpinC.h	501
include/spinc/ QuickSpinDefsC.h	501
include/spinc/ SpinnakerC.h	503
include/spinc/ SpinnakerDefsC.h	512
include/spinc/ SpinnakerGenApiC.h	517
include/spinc/ SpinnakerGenApiDefsC.h	521
include/spinc/ SpinnakerPlatformC.h	524
include/spinc/ SpinVideoC.h	525
include/spinc/ TransportLayerDefsC.h	526
include/spinc/ TransportLayerDeviceC.h	528
include/spinc/ TransportLayerInterfaceC.h	528
include/spinc/ TransportLayerStreamC.h	529
include/spinc/ TransportLayerSystemC.h	530


Chapter 4

Module Documentation

4.1 Spinnaker C Definitions

Definitions for Spinnaker C.

Collaboration diagram for Spinnaker C Definitions:



Modules

- [Camera Enumerations](#)
- [Chunk Data Structures](#)
- [Spinnaker C Handles](#)
Spinnaker C handle definitions.
- [Spinnaker C Function Signatures](#)
Spinnaker C function signature definitions.
- [Spinnaker C Enumerations](#)
Spinnaker C enumeration definitions.
- [Spinnaker C Structures](#)
Spinnaker C structure definitions.

Data Structures

- struct [spinChunkData](#)
The type of information that can be obtained from image chunk data.
- struct [spinPNGOption](#)
Options for saving PNG images.

Typedefs

- typedef uint8_t [bool8_t](#)

Variables

- static const [bool8_t](#) [False](#) = 0
- static const [bool8_t](#) [True](#) = 1

4.1.1 Detailed Description

Definitions for Spinnaker C.

Definitions for Spinnaker C API.

Holds enumerations, typedefs and structures that are used across the Spinnaker C API wrapper.

4.1.2 Typedef Documentation

4.1.2.1 bool8_t

```
typedef uint8_t bool8_t
```

4.1.3 Variable Documentation

4.1.3.1 False

```
const bool8_t False = 0 [static]
```

4.1.3.2 True

```
const bool8_t True = 1 [static]
```


4.2 Camera Enumerations

Collaboration diagram for Camera Enumerations:



Enumerations

- enum `spinLUTSelectorEnums` {
`LUTSelector_LUT1`,
`NUM_LUTSELECTOR` }

The enum definitions for camera nodes.

- enum `spinExposureModeEnums` {
`ExposureMode_Timed`,
`ExposureMode_TriggerWidth`,
`NUM_EXPOSUREMODE` }
- enum `spinAcquisitionModeEnums` {
`AcquisitionMode_Continuous`,
`AcquisitionMode_SingleFrame`,
`AcquisitionMode_MultiFrame`,
`NUM_ACQUISITIONMODE` }
- enum `spinTriggerSourceEnums` {
`TriggerSource_Software`,
`TriggerSource_Line0`,
`TriggerSource_Line1`,
`TriggerSource_Line2`,
`TriggerSource_Line3`,
`TriggerSource_UserOutput0`,
`TriggerSource_UserOutput1`,
`TriggerSource_UserOutput2`,
`TriggerSource_UserOutput3`,
`TriggerSource_Counter0Start`,
`TriggerSource_Counter1Start`,
`TriggerSource_Counter0End`,
`TriggerSource_Counter1End`,
`TriggerSource_LogicBlock0`,
`TriggerSource_LogicBlock1`,
`TriggerSource_Action0`,
`NUM_TRIGGERSOURCE` }
- enum `spinTriggerActivationEnums` {
`TriggerActivation_LevelLow`,
`TriggerActivation_LevelHigh`,
`TriggerActivation_FallingEdge`,
`TriggerActivation_RisingEdge`,
`TriggerActivation_AnyEdge`,
`NUM_TRIGGERACTIVATION` }

- enum `spinSensorShutterModeEnums` {
 `SensorShutterMode_Global`,
 `SensorShutterMode_Rolling`,
 `SensorShutterMode_GlobalReset`,
 `NUM_SENSORSHUTTERMODE` }
- enum `spinTriggerModeEnums` {
 `TriggerMode_Off`,
 `TriggerMode_On`,
 `NUM_TRIGGERMODE` }
- enum `spinTriggerOverlapEnums` {
 `TriggerOverlap_Off`,
 `TriggerOverlap_ReadOut`,
 `TriggerOverlap_PreviousFrame`,
 `NUM_TRIGGEROVERLAP` }
- enum `spinTriggerSelectorEnums` {
 `TriggerSelector_AcquisitionStart`,
 `TriggerSelector_FrameStart`,
 `TriggerSelector_FrameBurstStart`,
 `NUM_TRIGGERSELECTOR` }
- enum `spinExposureAutoEnums` {
 `ExposureAuto_Off`,
 `ExposureAuto_Once`,
 `ExposureAuto_Continuous`,
 `NUM_EXPOSUREAUTO` }
- enum `spinEventSelectorEnums` {
 `EventSelector_Error`,
 `EventSelector_ExposureEnd`,
 `EventSelector_SerialPortReceive`,
 `NUM_EVENTSELECTOR` }
- enum `spinEventNotificationEnums` {
 `EventNotification_On`,
 `EventNotification_Off`,
 `NUM_EVENTNOTIFICATION` }
- enum `spinLogicBlockSelectorEnums` {
 `LogicBlockSelector_LogicBlock0`,
 `LogicBlockSelector_LogicBlock1`,
 `NUM_LOGICBLOCKSELECTOR` }
- enum `spinLogicBlockLUTInputActivationEnums` {
 `LogicBlockLUTInputActivation_LevelLow`,
 `LogicBlockLUTInputActivation_LevelHigh`,
 `LogicBlockLUTInputActivation_FallingEdge`,
 `LogicBlockLUTInputActivation_RisingEdge`,
 `LogicBlockLUTInputActivation_AnyEdge`,
 `NUM_LOGICBLOCKLUTINPUTACTIVATION` }
- enum `spinLogicBlockLUTInputSelectorEnums` {
 `LogicBlockLUTInputSelector_Input0`,
 `LogicBlockLUTInputSelector_Input1`,
 `LogicBlockLUTInputSelector_Input2`,
 `LogicBlockLUTInputSelector_Input3`,
 `NUM_LOGICBLOCKLUTINPUTSELECTOR` }
- enum `spinLogicBlockLUTInputSourceEnums` {
 `LogicBlockLUTInputSource_Zero`,
 `LogicBlockLUTInputSource_Line0`,
 `LogicBlockLUTInputSource_Line1`,
 `LogicBlockLUTInputSource_Line2`,
 `LogicBlockLUTInputSource_Line3`,
 `LogicBlockLUTInputSource_UserOutput0`,
 `LogicBlockLUTInputSource_UserOutput1`,

```

LogicBlockLUTInputSource_UserOutput2,
LogicBlockLUTInputSource_UserOutput3,
LogicBlockLUTInputSource_Counter0Start,
LogicBlockLUTInputSource_Counter1Start,
LogicBlockLUTInputSource_Counter0End,
LogicBlockLUTInputSource_Counter1End,
LogicBlockLUTInputSource_LogicBlock0,
LogicBlockLUTInputSource_LogicBlock1,
LogicBlockLUTInputSource_ExposureStart,
LogicBlockLUTInputSource_ExposureEnd,
LogicBlockLUTInputSource_FrameTriggerWait,
LogicBlockLUTInputSource_AcquisitionActive,
NUM_LOGICBLOCKLUTINPUTSOURCE }

• enum spinLogicBlockLUTSelectorEnums {
    LogicBlockLUTSelector_Value,
    LogicBlockLUTSelector_Enable,
    NUM_LOGICBLOCKLUTSELECTOR }

• enum spinColorTransformationSelectorEnums {
    ColorTransformationSelector_RGBtoRGB,
    ColorTransformationSelector_RGBtoYUV,
    NUM_COLORTRANSFORMATIONSELECTOR }

• enum spinRgbTransformLightSourceEnums {
    RgbTransformLightSource_General,
    RgbTransformLightSource_Tungsten2800K,
    RgbTransformLightSource_WarmFluorescent3000K,
    RgbTransformLightSource_CoolFluorescent4000K,
    RgbTransformLightSource_Daylight5000K,
    RgbTransformLightSource_Cloudy6500K,
    RgbTransformLightSource_Shade8000K,
    RgbTransformLightSource_Custom,
    NUM_RGBTRANSFORMLIGHTSOURCE }

• enum spinColorTransformationValueSelectorEnums {
    ColorTransformationValueSelector_Gain00,
    ColorTransformationValueSelector_Gain01,
    ColorTransformationValueSelector_Gain02,
    ColorTransformationValueSelector_Gain10,
    ColorTransformationValueSelector_Gain11,
    ColorTransformationValueSelector_Gain12,
    ColorTransformationValueSelector_Gain20,
    ColorTransformationValueSelector_Gain21,
    ColorTransformationValueSelector_Gain22,
    ColorTransformationValueSelector_Offset0,
    ColorTransformationValueSelector_Offset1,
    ColorTransformationValueSelector_Offset2,
    NUM_COLORTRANSFORMATIONVALUESELECTOR }

• enum spinDeviceRegistersEndiannessEnums {
    DeviceRegistersEndianness_Little,
    DeviceRegistersEndianness_Big,
    NUM_DEVICEREGISTERSENDIANNES }

• enum spinDeviceScanTypeEnums {
    DeviceScanType_Areascan,
    NUM_DEVICESCANTYPE }

• enum spinDeviceCharacterSetEnums {
    DeviceCharacterSet_UTF8,
    DeviceCharacterSet_ASCII,
    NUM_DEVICECHARACTERSET }

• enum spinDeviceTLTypeEnums {
    DeviceTLType_GigEVision,

```

```

DeviceTLType_CameraLink,
DeviceTLType_CameraLinkHS,
DeviceTLType_CoaXPress,
DeviceTLType_USB3Vision,
DeviceTLType_Custom,
NUM_DEVICE TLTYPE }

• enum spinDevicePowerSupplySelectorEnums {
    DevicePowerSupplySelector_External,
    NUM_DEVICEPOWERSUPPLYSELECTOR }

• enum spinDeviceTemperatureSelectorEnums {
    DeviceTemperatureSelector_Sensor,
    NUM_DEVICE TEMPERATURESELECTOR }

• enum spinDeviceIndicatorModeEnums {
    DeviceIndicatorMode_Inactive,
    DeviceIndicatorMode_Active,
    DeviceIndicatorMode_ErrorStatus,
    NUM_DEVICE INDICATORMODE }

• enum spinAutoExposureControlPriorityEnums {
    AutoExposureControlPriority_Gain,
    AutoExposureControlPriority_ExposureTime,
    NUM_AUTOEXPOSURECONTROLPRIORITY }

• enum spinAutoExposureMeteringModeEnums {
    AutoExposureMeteringMode_Average,
    AutoExposureMeteringMode_Spot,
    AutoExposureMeteringMode_Partial,
    AutoExposureMeteringMode_CenterWeighted,
    AutoExposureMeteringMode_HistogramPeak,
    NUM_AUTOEXPOSUREMETERINGMODE }

• enum spinBalanceWhiteAutoProfileEnums {
    BalanceWhiteAutoProfile_Indoor,
    BalanceWhiteAutoProfile_Outdoor,
    NUM_BALANCEWHITEAUTOPROFILE }

• enum spinAutoAlgorithmSelectorEnums {
    AutoAlgorithmSelector_Awb,
    AutoAlgorithmSelector_Ae,
    NUM_AUTOALGORITHMSELECTOR }

• enum spinAutoExposureTargetGreyValueAutoEnums {
    AutoExposureTargetGreyValueAuto_Off,
    AutoExposureTargetGreyValueAuto_Continuous,
    NUM_AUTOEXPOSURETARGETGREYVALUEAUTO }

• enum spinAutoExposureLightingModeEnums {
    AutoExposureLightingMode_AutoDetect,
    AutoExposureLightingMode_Backlight,
    AutoExposureLightingMode_Frontlight,
    AutoExposureLightingMode_Normal,
    NUM_AUTOEXPOSURELIGHTINGMODE }

• enum spinGevIEEE1588StatusEnums {
    GevIEEE1588Status_Initializing,
    GevIEEE1588Status_Faulty,
    GevIEEE1588Status_Disabled,
    GevIEEE1588Status_Listening,
    GevIEEE1588Status_PreMaster,
    GevIEEE1588Status_Master,
    GevIEEE1588Status_Passive,
    GevIEEE1588Status_Uncalibrated,
    GevIEEE1588Status_Slave,
    NUM_GEVIEEE1588STATUS }

```

- enum spinGevIEEE1588ModeEnums {
GevIEEE1588Mode_Auto,
GevIEEE1588Mode_SlaveOnly,
NUM_GEVIEEE1588MODE }
- enum spinGevIEEE1588ClockAccuracyEnums {
GevIEEE1588ClockAccuracy_Unknown,
NUM_GEVIEEE1588CLOCKACCURACY }
- enum spinGevCCPEnums {
GevCCP_OpenAccess,
GevCCP_ExclusiveAccess,
GevCCP_ControlAccess,
NUM_GEVCCP }
- enum spinGevSupportedOptionSelectorEnums {
GevSupportedOptionSelector_UserDefinedName,
GevSupportedOptionSelector_SerialNumber,
GevSupportedOptionSelector_HeartbeatDisable,
GevSupportedOptionSelector_LinkSpeed,
GevSupportedOptionSelector_CCPApplicationSocket,
GevSupportedOptionSelector_ManifestTable,
GevSupportedOptionSelector_TestData,
GevSupportedOptionSelector_DiscoveryAckDelay,
GevSupportedOptionSelector_DiscoveryAckDelayWritable,
GevSupportedOptionSelector_ExtendedStatusCodes,
GevSupportedOptionSelector_Action,
GevSupportedOptionSelector_PendingAck,
GevSupportedOptionSelector_EventData,
GevSupportedOptionSelector_Event,
GevSupportedOptionSelector_PacketResend,
GevSupportedOptionSelector_WriteMem,
GevSupportedOptionSelector_CommandsConcatenation,
GevSupportedOptionSelector_IPConfigurationLLA,
GevSupportedOptionSelector_IPConfigurationDHCP,
GevSupportedOptionSelector_IPConfigurationPersistentIP,
GevSupportedOptionSelector_StreamChannelSourceSocket,
GevSupportedOptionSelector_MessageChannelSourceSocket,
NUM_GEVSUPPORTEDOPTIONSELECTOR }
- enum spinBlackLevelSelectorEnums {
BlackLevelSelector_All,
BlackLevelSelector_Analog,
BlackLevelSelector_Digital,
NUM_BLACKLEVELSELECTOR }
- enum spinBalanceWhiteAutoEnums {
BalanceWhiteAuto_Off,
BalanceWhiteAuto_Once,
BalanceWhiteAuto_Continuous,
NUM_BALANCEWHITEAUTO }
- enum spinGainAutoEnums {
GainAuto_Off,
GainAuto_Once,
GainAuto_Continuous,
NUM_GAINAUTO }
- enum spinBalanceRatioSelectorEnums {
BalanceRatioSelector_Red,
BalanceRatioSelector_Blue,
NUM_BALANCERATIOSELECTOR }
- enum spinGainSelectorEnums {
GainSelector_All,
NUM_GAINSELECTOR }

- enum [spinDefectCorrectionModeEnums](#) {
 [DefectCorrectionMode_Average](#),
 [DefectCorrectionMode_Highlight](#),
 [DefectCorrectionMode_Zero](#),
 [NUM_DEFECTCORRECTIONMODE](#) }
- enum [spinUserSetSelectorEnums](#) {
 [UserSetSelector_Default](#),
 [UserSetSelector_UserSet0](#),
 [UserSetSelector_UserSet1](#),
 [NUM_USERSETSELECTOR](#) }
- enum [spinUserSetDefaultEnums](#) {
 [UserSetDefault_Default](#),
 [UserSetDefault_UserSet0](#),
 [UserSetDefault_UserSet1](#),
 [NUM_USERSETDEFAULT](#) }
- enum [spinSerialPortBaudRateEnums](#) {
 [SerialPortBaudRate_Baud300](#),
 [SerialPortBaudRate_Baud600](#),
 [SerialPortBaudRate_Baud1200](#),
 [SerialPortBaudRate_Baud2400](#),
 [SerialPortBaudRate_Baud4800](#),
 [SerialPortBaudRate_Baud9600](#),
 [SerialPortBaudRate_Baud14400](#),
 [SerialPortBaudRate_Baud19200](#),
 [SerialPortBaudRate_Baud38400](#),
 [SerialPortBaudRate_Baud57600](#),
 [SerialPortBaudRate_Baud115200](#),
 [SerialPortBaudRate_Baud230400](#),
 [SerialPortBaudRate_Baud460800](#),
 [SerialPortBaudRate_Baud921600](#),
 [NUM_SERIALPORTBAUDRATE](#) }
- enum [spinSerialPortParityEnums](#) {
 [SerialPortParity_None](#),
 [SerialPortParity_Odd](#),
 [SerialPortParity_Even](#),
 [SerialPortParity_Mark](#),
 [SerialPortParity_Space](#),
 [NUM_SERIALPORTPARITY](#) }
- enum [spinSerialPortSelectorEnums](#) {
 [SerialPortSelector_SerialPort0](#),
 [NUM_SERIALPORTSELECTOR](#) }
- enum [spinSerialPortStopBitsEnums](#) {
 [SerialPortStopBits_Bits1](#),
 [SerialPortStopBits_Bits1AndAHalf](#),
 [SerialPortStopBits_Bits2](#),
 [NUM_SERIALPORTSTOPBITS](#) }
- enum [spinSerialPortSourceEnums](#) {
 [SerialPortSource_Line0](#),
 [SerialPortSource_Line1](#),
 [SerialPortSource_Line2](#),
 [SerialPortSource_Line3](#),
 [SerialPortSource_Off](#),
 [NUM_SERIALPORTSOURCE](#) }
- enum [spinSequencerModeEnums](#) {
 [SequencerMode_Off](#),
 [SequencerMode_On](#),
 [NUM_SEQUENCERMODE](#) }

- enum spinSequencerConfigurationValidEnums {
SequencerConfigurationValid_No,
SequencerConfigurationValid_Yes,
NUM_SEQUENCERCONFIGURATIONVALID }
- enum spinSequencerSetValidEnums {
SequencerSetValid_No,
SequencerSetValid_Yes,
NUM_SEQUENCERSETVALID }
- enum spinSequencerTriggerActivationEnums {
SequencerTriggerActivation_RisingEdge,
SequencerTriggerActivation_FallingEdge,
SequencerTriggerActivation_AnyEdge,
SequencerTriggerActivation_LevelHigh,
SequencerTriggerActivation_LevelLow,
NUM_SEQUENCERTRIGGERACTIVATION }
- enum spinSequencerConfigurationModeEnums {
SequencerConfigurationMode_Off,
SequencerConfigurationMode_On,
NUM_SEQUENCERCONFIGURATIONMODE }
- enum spinSequencerTriggerSourceEnums {
SequencerTriggerSource_Off,
SequencerTriggerSource_FrameStart,
NUM_SEQUENCERTRIGGERSOURCE }
- enum spinTransferQueueModeEnums {
TransferQueueMode_FirstInFirstOut,
NUM_TRANSFERQUEUEMODE }
- enum spinTransferOperationModeEnums {
TransferOperationMode_Continuous,
TransferOperationMode_MultiBlock,
NUM_TRANSFEROPERATIONMODE }
- enum spinTransferControlModeEnums {
TransferControlMode_Basic,
TransferControlMode_Automatic,
TransferControlMode_UserControlled,
NUM_TRANSFERCONTROLMODE }
- enum spinChunkGainSelectorEnums {
ChunkGainSelector_All,
ChunkGainSelector_Red,
ChunkGainSelector_Green,
ChunkGainSelector_Blue,
NUM_CHUNKGAINSELECTOR }
- enum spinChunkSelectorEnums {
ChunkSelector_Image,
ChunkSelector_CRC,
ChunkSelector_FrameID,
ChunkSelector_OffsetX,
ChunkSelector_OffsetY,
ChunkSelector_Width,
ChunkSelector_Height,
ChunkSelector_ExposureTime,
ChunkSelector_Gain,
ChunkSelector_BlackLevel,
ChunkSelector_PixelFormat,
ChunkSelector_Timestamp,
ChunkSelector_SequencerSetActive,
ChunkSelector_SerialData,
ChunkSelector_ExposureEndLineStatusAll,
NUM_CHUNKSELECTOR }

- enum `spinChunkBlackLevelSelectorEnums` {
`ChunkBlackLevelSelector_All`,
`NUM_CHUNKBLACKLEVELSELECTOR` }
- enum `spinChunkPixelFormatEnums` {
`ChunkPixelFormat_Mono8`,
`ChunkPixelFormat_Mono12Packed`,
`ChunkPixelFormat_Mono16`,
`ChunkPixelFormat_RGB8Packed`,
`ChunkPixelFormat_YUV422Packed`,
`ChunkPixelFormat_BayerGR8`,
`ChunkPixelFormat_BayerRG8`,
`ChunkPixelFormat_BayerGB8`,
`ChunkPixelFormat_BayerBG8`,
`ChunkPixelFormat_YCbCr601_422_8_CbYCrY`,
`NUM_CHUNKPIXELFORMAT` }
- enum `spinFileOperationStatusEnums` {
`FileOperationStatus_Success`,
`FileOperationStatus_Failure`,
`FileOperationStatus_Overflow`,
`NUM_FILEOPERATIONSTATUS` }
- enum `spinFileOpenModeEnums` {
`FileOpenMode_Read`,
`FileOpenMode_Write`,
`FileOpenMode_ReadWrite`,
`NUM_FILEOPENMODE` }
- enum `spinFileOperationSelectorEnums` {
`FileOperationSelector_Open`,
`FileOperationSelector_Close`,
`FileOperationSelector_Read`,
`FileOperationSelector_Write`,
`FileOperationSelector_Delete`,
`NUM_FILEOPERATIONSELECTOR` }
- enum `spinFileSelectorEnums` {
`FileSelector_UserSetDefault`,
`FileSelector_UserSet0`,
`FileSelector_UserSet1`,
`FileSelector_UserFile1`,
`FileSelector_SerialPort0`,
`NUM_FILESELECTOR` }
- enum `spinBinningSelectorEnums` {
`BinningSelector_All`,
`BinningSelector_Sensor`,
`BinningSelector_ISP`,
`NUM_BINNINGSELECTOR` }
- enum `spinTestPatternGeneratorSelectorEnums` {
`TestPatternGeneratorSelector_Sensor`,
`TestPatternGeneratorSelector_PipelineStart`,
`NUM_TESTPATTERNGENERATORSELECTOR` }
- enum `spinTestPatternEnums` {
`TestPattern_Off`,
`TestPattern_Increment`,
`TestPattern_SensorTestPattern`,
`NUM_TESTPATTERN` }
- enum `spinPixelColorFilterEnums` {
`PixelColorFilter_None`,
`PixelColorFilter_BayerRG`,
`PixelColorFilter_BayerGB`,
`PixelColorFilter_BayerGR`,


```
PixelColorFilter_BayerBG,  
NUM_PIXELCOLORFILTER }  
• enum spinAdcBitDepthEnums {  
    AdcBitDepth_Bit8,  
    AdcBitDepth_Bit10,  
    AdcBitDepth_Bit12,  
    AdcBitDepth_Bit14,  
    NUM_ADCBITDEPTH }  
• enum spinDecimationHorizontalModeEnums {  
    DecimationHorizontalMode_Discard,  
    NUM_DECIMATIONHORIZONTALMODE }  
• enum spinBinningVerticalModeEnums {  
    BinningVerticalMode_Sum,  
    BinningVerticalMode_Average,  
    NUM_BINNINGVERTICALMODE }  
• enum spinPixelSizeEnums {  
    PixelSize_Bpp1,  
    PixelSize_Bpp2,  
    PixelSize_Bpp4,  
    PixelSize_Bpp8,  
    PixelSize_Bpp10,  
    PixelSize_Bpp12,  
    PixelSize_Bpp14,  
    PixelSize_Bpp16,  
    PixelSize_Bpp20,  
    PixelSize_Bpp24,  
    PixelSize_Bpp30,  
    PixelSize_Bpp32,  
    PixelSize_Bpp36,  
    PixelSize_Bpp48,  
    PixelSize_Bpp64,  
    PixelSize_Bpp96,  
    NUM_PIXELSIZE }  
• enum spinDecimationSelectorEnums {  
    DecimationSelector_All,  
    DecimationSelector_Sensor,  
    NUM_DECIMATIONSELECTOR }  
• enum spinImageCompressionModeEnums {  
    ImageCompressionMode_Off,  
    ImageCompressionMode_Lossless,  
    NUM_IMAGECOMPRESSIONMODE }  
• enum spinBinningHorizontalModeEnums {  
    BinningHorizontalMode_Sum,  
    BinningHorizontalMode_Average,  
    NUM_BINNINGHORIZONTALMODE }  
• enum spinPixelFormatEnums {  
    PixelFormat_Mono8,  
    PixelFormat_Mono16,  
    PixelFormat_RGB8Packed,  
    PixelFormat_BayerGR8,  
    PixelFormat_BayerRG8,  
    PixelFormat_BayerGB8,  
    PixelFormat_BayerBG8,  
    PixelFormat_BayerGR16,  
    PixelFormat_BayerRG16,  
    PixelFormat_BayerGB16,  
    PixelFormat_BayerBG16,  
    PixelFormat_Mono12Packed,
```

PixelFormat_BayerGR12Packed,
PixelFormat_BayerRG12Packed,
PixelFormat_BayerGB12Packed,
PixelFormat_BayerBG12Packed,
PixelFormat_YUV411Packed,
PixelFormat_YUV422Packed,
PixelFormat_YUV444Packed,
PixelFormat_Mono12p,
PixelFormat_BayerGR12p,
PixelFormat_BayerRG12p,
PixelFormat_BayerGB12p,
PixelFormat_BayerBG12p,
PixelFormat_YCbCr8,
PixelFormat_YCbCr422_8,
PixelFormat_YCbCr411_8,
PixelFormat_BGR8,
PixelFormat_BGRa8,
PixelFormat_Mono10Packed,
PixelFormat_BayerGR10Packed,
PixelFormat_BayerRG10Packed,
PixelFormat_BayerGB10Packed,
PixelFormat_BayerBG10Packed,
PixelFormat_Mono10p,
PixelFormat_BayerGR10p,
PixelFormat_BayerRG10p,
PixelFormat_BayerGB10p,
PixelFormat_BayerBG10p,
PixelFormat_Mono1p,
PixelFormat_Mono2p,
PixelFormat_Mono4p,
PixelFormat_Mono8s,
PixelFormat_Mono10,
PixelFormat_Mono12,
PixelFormat_Mono14,
PixelFormat_Mono16s,
PixelFormat_Mono32f,
PixelFormat_BayerBG10,
PixelFormat_BayerBG12,
PixelFormat_BayerGB10,
PixelFormat_BayerGB12,
PixelFormat_BayerGR10,
PixelFormat_BayerGR12,
PixelFormat_BayerRG10,
PixelFormat_BayerRG12,
PixelFormat_RGBa8,
PixelFormat_RGBa10,
PixelFormat_RGBa10p,
PixelFormat_RGBa12,
PixelFormat_RGBa12p,
PixelFormat_RGBa14,
PixelFormat_RGBa16,
PixelFormat_RGB8,
PixelFormat_RGB8_Planar,
PixelFormat_RGB10,
PixelFormat_RGB10_Planar,
PixelFormat_RGB10p,
PixelFormat_RGB10p32,
PixelFormat_RGB12,

PixelFormat_RGB12_Planar,
PixelFormat_RGB12p,
PixelFormat_RGB14,
PixelFormat_RGB16,
PixelFormat_RGB16s,
PixelFormat_RGB32f,
PixelFormat_RGB16_Planar,
PixelFormat_RGB565p,
PixelFormat_BGRa10,
PixelFormat_BGRa10p,
PixelFormat_BGRa12,
PixelFormat_BGRa12p,
PixelFormat_BGRa14,
PixelFormat_BGRa16,
PixelFormat_RGBa32f,
PixelFormat_BGR10,
PixelFormat_BGR10p,
PixelFormat_BGR12,
PixelFormat_BGR12p,
PixelFormat_BGR14,
PixelFormat_BGR16,
PixelFormat_BGR565p,
PixelFormat_R8,
PixelFormat_R10,
PixelFormat_R12,
PixelFormat_R16,
PixelFormat_G8,
PixelFormat_G10,
PixelFormat_G12,
PixelFormat_G16,
PixelFormat_B8,
PixelFormat_B10,
PixelFormat_B12,
PixelFormat_B16,
PixelFormat_Coord3D_ABC8,
PixelFormat_Coord3D_ABC8_Planar,
PixelFormat_Coord3D_ABC10p,
PixelFormat_Coord3D_ABC10p_Planar,
PixelFormat_Coord3D_ABC12p,
PixelFormat_Coord3D_ABC12p_Planar,
PixelFormat_Coord3D_ABC16,
PixelFormat_Coord3D_ABC16_Planar,
PixelFormat_Coord3D_ABC32f,
PixelFormat_Coord3D_ABC32f_Planar,
PixelFormat_Coord3D_AC8,
PixelFormat_Coord3D_AC8_Planar,
PixelFormat_Coord3D_AC10p,
PixelFormat_Coord3D_AC10p_Planar,
PixelFormat_Coord3D_AC12p,
PixelFormat_Coord3D_AC12p_Planar,
PixelFormat_Coord3D_AC16,
PixelFormat_Coord3D_AC16_Planar,
PixelFormat_Coord3D_AC32f,
PixelFormat_Coord3D_AC32f_Planar,
PixelFormat_Coord3D_A8,
PixelFormat_Coord3D_A10p,
PixelFormat_Coord3D_A12p,
PixelFormat_Coord3D_A16,

[PixelFormat_Coord3D_A32f](#),
[PixelFormat_Coord3D_B8](#),
[PixelFormat_Coord3D_B10p](#),
[PixelFormat_Coord3D_B12p](#),
[PixelFormat_Coord3D_B16](#),
[PixelFormat_Coord3D_B32f](#),
[PixelFormat_Coord3D_C8](#),
[PixelFormat_Coord3D_C10p](#),
[PixelFormat_Coord3D_C12p](#),
[PixelFormat_Coord3D_C16](#),
[PixelFormat_Coord3D_C32f](#),
[PixelFormat_Confidence1](#),
[PixelFormat_Confidence1p](#),
[PixelFormat_Confidence8](#),
[PixelFormat_Confidence16](#),
[PixelFormat_Confidence32f](#),
[PixelFormat_BiColorBGRG8](#),
[PixelFormat_BiColorBGRG10](#),
[PixelFormat_BiColorBGRG10p](#),
[PixelFormat_BiColorBGRG12](#),
[PixelFormat_BiColorBGRG12p](#),
[PixelFormat_BiColorRGBG8](#),
[PixelFormat_BiColorRGBG10](#),
[PixelFormat_BiColorRGBG10p](#),
[PixelFormat_BiColorRGBG12](#),
[PixelFormat_BiColorRGBG12p](#),
[PixelFormat_SCF1WBWG8](#),
[PixelFormat_SCF1WBWG10](#),
[PixelFormat_SCF1WBWG10p](#),
[PixelFormat_SCF1WBWG12](#),
[PixelFormat_SCF1WBWG12p](#),
[PixelFormat_SCF1WBWG14](#),
[PixelFormat_SCF1WBWG16](#),
[PixelFormat_SCF1WGWB8](#),
[PixelFormat_SCF1WGWB10](#),
[PixelFormat_SCF1WGWB10p](#),
[PixelFormat_SCF1WGWB12](#),
[PixelFormat_SCF1WGWB12p](#),
[PixelFormat_SCF1WGWB14](#),
[PixelFormat_SCF1WGWB16](#),
[PixelFormat_SCF1WGWR8](#),
[PixelFormat_SCF1WGWR10](#),
[PixelFormat_SCF1WGWR10p](#),
[PixelFormat_SCF1WGWR12](#),
[PixelFormat_SCF1WGWR12p](#),
[PixelFormat_SCF1WGWR14](#),
[PixelFormat_SCF1WGWR16](#),
[PixelFormat_SCF1WRWG8](#),
[PixelFormat_SCF1WRWG10](#),
[PixelFormat_SCF1WRWG10p](#),
[PixelFormat_SCF1WRWG12](#),
[PixelFormat_SCF1WRWG12p](#),
[PixelFormat_SCF1WRWG14](#),
[PixelFormat_SCF1WRWG16](#),
[PixelFormat_YCbCr8_CbYCr](#),
[PixelFormat_YCbCr10_CbYCr](#),
[PixelFormat_YCbCr10p_CbYCr](#),
[PixelFormat_YCbCr12_CbYCr](#),

PixelFormat_YCbCr12p_CbYCr,
PixelFormat_YCbCr411_8_CbYYCrYY,
PixelFormat_YCbCr422_8_CbYCrY,
PixelFormat_YCbCr422_10,
PixelFormat_YCbCr422_10_CbYCrY,
PixelFormat_YCbCr422_10p,
PixelFormat_YCbCr422_10p_CbYCrY,
PixelFormat_YCbCr422_12,
PixelFormat_YCbCr422_12_CbYCrY,
PixelFormat_YCbCr422_12p,
PixelFormat_YCbCr422_12p_CbYCrY,
PixelFormat_YCbCr601_8_CbYCr,
PixelFormat_YCbCr601_10_CbYCr,
PixelFormat_YCbCr601_10p_CbYCr,
PixelFormat_YCbCr601_12_CbYCr,
PixelFormat_YCbCr601_12p_CbYCr,
PixelFormat_YCbCr601_411_8_CbYYCrYY,
PixelFormat_YCbCr601_422_8,
PixelFormat_YCbCr601_422_8_CbYCrY,
PixelFormat_YCbCr601_422_10,
PixelFormat_YCbCr601_422_10_CbYCrY,
PixelFormat_YCbCr601_422_10p,
PixelFormat_YCbCr601_422_10p_CbYCrY,
PixelFormat_YCbCr601_422_12,
PixelFormat_YCbCr601_422_12_CbYCrY,
PixelFormat_YCbCr601_422_12p,
PixelFormat_YCbCr601_422_12p_CbYCrY,
PixelFormat_YCbCr709_8_CbYCr,
PixelFormat_YCbCr709_10_CbYCr,
PixelFormat_YCbCr709_10p_CbYCr,
PixelFormat_YCbCr709_12_CbYCr,
PixelFormat_YCbCr709_12p_CbYCr,
PixelFormat_YCbCr709_411_8_CbYYCrYY,
PixelFormat_YCbCr709_422_8,
PixelFormat_YCbCr709_422_8_CbYCrY,
PixelFormat_YCbCr709_422_10,
PixelFormat_YCbCr709_422_10_CbYCrY,
PixelFormat_YCbCr709_422_10p,
PixelFormat_YCbCr709_422_10p_CbYCrY,
PixelFormat_YCbCr709_422_12,
PixelFormat_YCbCr709_422_12_CbYCrY,
PixelFormat_YCbCr709_422_12p,
PixelFormat_YCbCr709_422_12p_CbYCrY,
PixelFormat_YUV8_UYV,
PixelFormat_YUV411_8_UYYVYY,
PixelFormat_YUV422_8,
PixelFormat_YUV422_8_UYVY,
PixelFormat_Polarized8,
PixelFormat_Polarized10p,
PixelFormat_Polarized12p,
PixelFormat_Polarized16,
PixelFormat_BayerRGPolarized8,
PixelFormat_BayerRGPolarized10p,
PixelFormat_BayerRGPolarized12p,
PixelFormat_BayerRGPolarized16,
PixelFormat_LLCMono8,
PixelFormat_LLCBayerRG8,
PixelFormat_JPEGMono8,

```

PixelFormat_JPEGColor8,
PixelFormat_Raw16,
PixelFormat_Raw8,
PixelFormat_R12_Jpeg,
PixelFormat_GR12_Jpeg,
PixelFormat_GB12_Jpeg,
PixelFormat_B12_Jpeg,
UNKNOWN_PIXELFORMAT,
NUM_PIXELFORMAT }

• enum spinDecimationVerticalModeEnums {
    DecimationVerticalMode_Discard,
    NUM_DECIMATIONVERTICALMODE }

• enum spinLineModeEnums {
    LineMode_Input,
    LineMode_Output,
    NUM_LINEMODE }

• enum spinLineSourceEnums {
    LineSource_Off,
    LineSource_Line0,
    LineSource_Line1,
    LineSource_Line2,
    LineSource_Line3,
    LineSource_UserOutput0,
    LineSource_UserOutput1,
    LineSource_UserOutput2,
    LineSource_UserOutput3,
    LineSource_Counter0Active,
    LineSource_Counter1Active,
    LineSource_LogicBlock0,
    LineSource_LogicBlock1,
    LineSource_ExposureActive,
    LineSource_FrameTriggerWait,
    LineSource_SerialPort0,
    LineSource_PPSSignal,
    LineSource_AllPixel,
    LineSource_AnyPixel,
    NUM_LINESOURCE }

• enum spinLineInputFilterSelectorEnums {
    LineInputFilterSelector_Deglintch,
    LineInputFilterSelector_Debounce,
    NUM_LINEINPUTFILTERSELECTOR }

• enum spinUserOutputSelectorEnums {
    UserOutputSelector_UserOutput0,
    UserOutputSelector_UserOutput1,
    UserOutputSelector_UserOutput2,
    UserOutputSelector_UserOutput3,
    NUM_USEROUTPUTSELECTOR }

• enum spinLineFormatEnums {
    LineFormat_NoConnect,
    LineFormat_TriState,
    LineFormat_TTL,
    LineFormat_LVDS,
    LineFormat_RS422,
    LineFormat_OptoCoupled,
    LineFormat_OpenDrain,
    NUM_LINEFORMAT }

• enum spinLineSelectorEnums {
    LineSelector_Line0,

```

```
LineSelector_Line1,  
LineSelector_Line2,  
LineSelector_Line3,  
NUM_LINESELECTOR }  
• enum spinExposureActiveModeEnums {  
    ExposureActiveMode_Line1,  
    ExposureActiveMode_AnyPixels,  
    ExposureActiveMode_AllPixels,  
    NUM_EXPOSUREACTIVEMODE }  
• enum spinCounterTriggerActivationEnums {  
    CounterTriggerActivation_LevelLow,  
    CounterTriggerActivation_LevelHigh,  
    CounterTriggerActivation_FallingEdge,  
    CounterTriggerActivation_RisingEdge,  
    CounterTriggerActivation_AnyEdge,  
    NUM_COUNTERTRIGGERACTIVATION }  
• enum spinCounterSelectorEnums {  
    CounterSelector_Counter0,  
    CounterSelector_Counter1,  
    NUM_COUNTERSELECTOR }  
• enum spinCounterStatusEnums {  
    CounterStatus_CounterIdle,  
    CounterStatus_CounterTriggerWait,  
    CounterStatus_CounterActive,  
    CounterStatus_CounterCompleted,  
    CounterStatus_CounterOverflow,  
    NUM_COUNTERSTATUS }  
• enum spinCounterTriggerSourceEnums {  
    CounterTriggerSource_Off,  
    CounterTriggerSource_Line0,  
    CounterTriggerSource_Line1,  
    CounterTriggerSource_Line2,  
    CounterTriggerSource_Line3,  
    CounterTriggerSource_UserOutput0,  
    CounterTriggerSource_UserOutput1,  
    CounterTriggerSource_UserOutput2,  
    CounterTriggerSource_UserOutput3,  
    CounterTriggerSource_Counter0Start,  
    CounterTriggerSource_Counter1Start,  
    CounterTriggerSource_Counter0End,  
    CounterTriggerSource_Counter1End,  
    CounterTriggerSource_LogicBlock0,  
    CounterTriggerSource_LogicBlock1,  
    CounterTriggerSource_ExposureStart,  
    CounterTriggerSource_ExposureEnd,  
    CounterTriggerSource_FrameTriggerWait,  
    NUM_COUNTERTRIGGERSOURCE }  
• enum spinCounterResetSourceEnums {  
    CounterResetSource_Off,  
    CounterResetSource_Line0,  
    CounterResetSource_Line1,  
    CounterResetSource_Line2,  
    CounterResetSource_Line3,  
    CounterResetSource_UserOutput0,  
    CounterResetSource_UserOutput1,  
    CounterResetSource_UserOutput2,  
    CounterResetSource_UserOutput3,  
    CounterResetSource_Counter0Start,
```

```

CounterResetSource_Counter1Start,
CounterResetSource_Counter0End,
CounterResetSource_Counter1End,
CounterResetSource_LogicBlock0,
CounterResetSource_LogicBlock1,
CounterResetSource_ExposureStart,
CounterResetSource_ExposureEnd,
CounterResetSource_FrameTriggerWait,
NUM_COUNTERRESETSOURCE }

• enum spinCounterEventSourceEnums {
CounterEventSource_Off,
CounterEventSource_MHzTick,
CounterEventSource_Line0,
CounterEventSource_Line1,
CounterEventSource_Line2,
CounterEventSource_Line3,
CounterEventSource_UserOutput0,
CounterEventSource_UserOutput1,
CounterEventSource_UserOutput2,
CounterEventSource_UserOutput3,
CounterEventSource_Counter0Start,
CounterEventSource_Counter1Start,
CounterEventSource_Counter0End,
CounterEventSource_Counter1End,
CounterEventSource_LogicBlock0,
CounterEventSource_LogicBlock1,
CounterEventSource_ExposureStart,
CounterEventSource_ExposureEnd,
CounterEventSource_FrameTriggerWait,
NUM_COUNTEREVENTSOURCE }

• enum spinCounterEventActivationEnums {
CounterEventActivation_LevelLow,
CounterEventActivation_LevelHigh,
CounterEventActivation_FallingEdge,
CounterEventActivation_RisingEdge,
CounterEventActivation_AnyEdge,
NUM_COUNTEREVENTACTIVATION }

• enum spinCounterResetActivationEnums {
CounterResetActivation_LevelLow,
CounterResetActivation_LevelHigh,
CounterResetActivation_FallingEdge,
CounterResetActivation_RisingEdge,
CounterResetActivation_AnyEdge,
NUM_COUNTERRESETACTIVATION }

• enum spinDeviceTypeEnums {
DeviceType_Transmitter,
DeviceType_Receiver,
DeviceType_Transceiver,
DeviceType_Peripheral,
NUM_DEVICETYPE }

• enum spinDeviceConnectionStatusEnums {
DeviceConnectionStatus_Active,
DeviceConnectionStatus_Inactive,
NUM_DEVICECONNECTIONSTATUS }

• enum spinDeviceLinkThroughputLimitModeEnums {
DeviceLinkThroughputLimitMode_On,
DeviceLinkThroughputLimitMode_Off,
NUM_DEVICELINKTHROUGHPUTLIMITMODE }

```


- enum spinDeviceLinkHeartbeatModeEnums {
DeviceLinkHeartbeatMode_On,
DeviceLinkHeartbeatMode_Off,
NUM_DEVICELINKHEARTBEATMODE }
- enum spinDeviceStreamChannelTypeEnums {
DeviceStreamChannelType_Transmitter,
DeviceStreamChannelType_Receiver,
NUM_DEVICESTREAMCHANNELTYPE }
- enum spinDeviceStreamChannelEndiannessEnums {
DeviceStreamChannelEndianness_Big,
DeviceStreamChannelEndianness_Little,
NUM_DEVICESTREAMCHANNELENDIANNESS }
- enum spinDeviceClockSelectorEnums {
DeviceClockSelector_Sensor,
DeviceClockSelector_SensorDigitization,
DeviceClockSelector_CameraLink,
NUM_DEVICECLOCKSELECTOR }
- enum spinDeviceSerialPortSelectorEnums {
DeviceSerialPortSelector_CameraLink,
NUM_DEVICESERIALPORTSELECTOR }
- enum spinDeviceSerialPortBaudRateEnums {
DeviceSerialPortBaudRate_Baud9600,
DeviceSerialPortBaudRate_Baud19200,
DeviceSerialPortBaudRate_Baud38400,
DeviceSerialPortBaudRate_Baud57600,
DeviceSerialPortBaudRate_Baud115200,
DeviceSerialPortBaudRate_Baud230400,
DeviceSerialPortBaudRate_Baud460800,
DeviceSerialPortBaudRate_Baud921600,
NUM_DEVICESERIALPORTBAUDRATE }
- enum spinSensorTapsEnums {
SensorTaps_One,
SensorTaps_Two,
SensorTaps_Three,
SensorTaps_Four,
SensorTaps_Eight,
SensorTaps_Ten,
NUM_SENSORTAPS }
- enum spinSensorDigitizationTapsEnums {
SensorDigitizationTaps_One,
SensorDigitizationTaps_Two,
SensorDigitizationTaps_Three,
SensorDigitizationTaps_Four,
SensorDigitizationTaps_Eight,
SensorDigitizationTaps_Ten,
NUM_SENSORDIGITIZATIONTAPS }
- enum spinRegionSelectorEnums {
RegionSelector_Region0,
RegionSelector_Region1,
RegionSelector_Region2,
RegionSelector_All,
NUM_REGIONSELECTOR }
- enum spinRegionModeEnums {
RegionMode_Off,
RegionMode_On,
NUM_REGIONMODE }
- enum spinRegionDestinationEnums {
RegionDestination_Stream0,

```

RegionDestination_Stream1,
RegionDestination_Stream2,
NUM_REGIONDESTINATION }

```

- `enum spinImageComponentSelectorEnums {`
`ImageComponentSelector_Intensity,`
`ImageComponentSelector_Color,`
`ImageComponentSelector_Infrared,`
`ImageComponentSelector_Ultraviolet,`
`ImageComponentSelector_Range,`
`ImageComponentSelector_Disparity,`
`ImageComponentSelector_Confidence,`
`ImageComponentSelector_Scatter,`
`NUM_IMAGECOMPONENTSELECTOR }`
- `enum spinPixelFormatInfoSelectorEnums {`
`PixelFormatInfoSelector_Mono1p,`
`PixelFormatInfoSelector_Mono2p,`
`PixelFormatInfoSelector_Mono4p,`
`PixelFormatInfoSelector_Mono8,`
`PixelFormatInfoSelector_Mono8s,`
`PixelFormatInfoSelector_Mono10,`
`PixelFormatInfoSelector_Mono10p,`
`PixelFormatInfoSelector_Mono12,`
`PixelFormatInfoSelector_Mono12p,`
`PixelFormatInfoSelector_Mono14,`
`PixelFormatInfoSelector_Mono16,`
`PixelFormatInfoSelector_Mono16s,`
`PixelFormatInfoSelector_Mono32f,`
`PixelFormatInfoSelector_BayerBG8,`
`PixelFormatInfoSelector_BayerBG10,`
`PixelFormatInfoSelector_BayerBG10p,`
`PixelFormatInfoSelector_BayerBG12,`
`PixelFormatInfoSelector_BayerBG12p,`
`PixelFormatInfoSelector_BayerBG16,`
`PixelFormatInfoSelector_BayerGB8,`
`PixelFormatInfoSelector_BayerGB10,`
`PixelFormatInfoSelector_BayerGB10p,`
`PixelFormatInfoSelector_BayerGB12,`
`PixelFormatInfoSelector_BayerGB12p,`
`PixelFormatInfoSelector_BayerGB16,`
`PixelFormatInfoSelector_BayerGR8,`
`PixelFormatInfoSelector_BayerGR10,`
`PixelFormatInfoSelector_BayerGR10p,`
`PixelFormatInfoSelector_BayerGR12,`
`PixelFormatInfoSelector_BayerGR12p,`
`PixelFormatInfoSelector_BayerGR16,`
`PixelFormatInfoSelector_BayerRG8,`
`PixelFormatInfoSelector_BayerRG10,`
`PixelFormatInfoSelector_BayerRG10p,`
`PixelFormatInfoSelector_BayerRG12,`
`PixelFormatInfoSelector_BayerRG12p,`
`PixelFormatInfoSelector_BayerRG16,`
`PixelFormatInfoSelector_RGBa8,`
`PixelFormatInfoSelector_RGBa10,`
`PixelFormatInfoSelector_RGBa10p,`
`PixelFormatInfoSelector_RGBa12,`
`PixelFormatInfoSelector_RGBa12p,`
`PixelFormatInfoSelector_RGBa14,`
`PixelFormatInfoSelector_RGBa16,`

PixelFormatInfoSelector_RGB8,
PixelFormatInfoSelector_RGB8_Planar,
PixelFormatInfoSelector_RGB10,
PixelFormatInfoSelector_RGB10_Planar,
PixelFormatInfoSelector_RGB10p,
PixelFormatInfoSelector_RGB10p32,
PixelFormatInfoSelector_RGB12,
PixelFormatInfoSelector_RGB12_Planar,
PixelFormatInfoSelector_RGB12p,
PixelFormatInfoSelector_RGB14,
PixelFormatInfoSelector_RGB16,
PixelFormatInfoSelector_RGB16s,
PixelFormatInfoSelector_RGB32f,
PixelFormatInfoSelector_RGB16_Planar,
PixelFormatInfoSelector_RGB565p,
PixelFormatInfoSelector_BGRa8,
PixelFormatInfoSelector_BGRa10,
PixelFormatInfoSelector_BGRa10p,
PixelFormatInfoSelector_BGRa12,
PixelFormatInfoSelector_BGRa12p,
PixelFormatInfoSelector_BGRa14,
PixelFormatInfoSelector_BGRa16,
PixelFormatInfoSelector_RGBa32f,
PixelFormatInfoSelector_BGR8,
PixelFormatInfoSelector_BGR10,
PixelFormatInfoSelector_BGR10p,
PixelFormatInfoSelector_BGR12,
PixelFormatInfoSelector_BGR12p,
PixelFormatInfoSelector_BGR14,
PixelFormatInfoSelector_BGR16,
PixelFormatInfoSelector_BGR565p,
PixelFormatInfoSelector_R8,
PixelFormatInfoSelector_R10,
PixelFormatInfoSelector_R12,
PixelFormatInfoSelector_R16,
PixelFormatInfoSelector_G8,
PixelFormatInfoSelector_G10,
PixelFormatInfoSelector_G12,
PixelFormatInfoSelector_G16,
PixelFormatInfoSelector_B8,
PixelFormatInfoSelector_B10,
PixelFormatInfoSelector_B12,
PixelFormatInfoSelector_B16,
PixelFormatInfoSelector_Coord3D_ABC8,
PixelFormatInfoSelector_Coord3D_ABC8_Planar,
PixelFormatInfoSelector_Coord3D_ABC10p,
PixelFormatInfoSelector_Coord3D_ABC10p_Planar,
PixelFormatInfoSelector_Coord3D_ABC12p,
PixelFormatInfoSelector_Coord3D_ABC12p_Planar,
PixelFormatInfoSelector_Coord3D_ABC16,
PixelFormatInfoSelector_Coord3D_ABC16_Planar,
PixelFormatInfoSelector_Coord3D_ABC32f,
PixelFormatInfoSelector_Coord3D_ABC32f_Planar,
PixelFormatInfoSelector_Coord3D_AC8,
PixelFormatInfoSelector_Coord3D_AC8_Planar,
PixelFormatInfoSelector_Coord3D_AC10p,
PixelFormatInfoSelector_Coord3D_AC10p_Planar,
PixelFormatInfoSelector_Coord3D_AC12p,

[PixelFormatInfoSelector_Coord3D_AC12p_Planar](#),
[PixelFormatInfoSelector_Coord3D_AC16](#),
[PixelFormatInfoSelector_Coord3D_AC16_Planar](#),
[PixelFormatInfoSelector_Coord3D_AC32f](#),
[PixelFormatInfoSelector_Coord3D_AC32f_Planar](#),
[PixelFormatInfoSelector_Coord3D_A8](#),
[PixelFormatInfoSelector_Coord3D_A10p](#),
[PixelFormatInfoSelector_Coord3D_A12p](#),
[PixelFormatInfoSelector_Coord3D_A16](#),
[PixelFormatInfoSelector_Coord3D_A32f](#),
[PixelFormatInfoSelector_Coord3D_B8](#),
[PixelFormatInfoSelector_Coord3D_B10p](#),
[PixelFormatInfoSelector_Coord3D_B12p](#),
[PixelFormatInfoSelector_Coord3D_B16](#),
[PixelFormatInfoSelector_Coord3D_B32f](#),
[PixelFormatInfoSelector_Coord3D_C8](#),
[PixelFormatInfoSelector_Coord3D_C10p](#),
[PixelFormatInfoSelector_Coord3D_C12p](#),
[PixelFormatInfoSelector_Coord3D_C16](#),
[PixelFormatInfoSelector_Coord3D_C32f](#),
[PixelFormatInfoSelector_Confidence1](#),
[PixelFormatInfoSelector_Confidence1p](#),
[PixelFormatInfoSelector_Confidence8](#),
[PixelFormatInfoSelector_Confidence16](#),
[PixelFormatInfoSelector_Confidence32f](#),
[PixelFormatInfoSelector_BiColorBGRG8](#),
[PixelFormatInfoSelector_BiColorBGRG10](#),
[PixelFormatInfoSelector_BiColorBGRG10p](#),
[PixelFormatInfoSelector_BiColorBGRG12](#),
[PixelFormatInfoSelector_BiColorBGRG12p](#),
[PixelFormatInfoSelector_BiColorRGBG8](#),
[PixelFormatInfoSelector_BiColorRGBG10](#),
[PixelFormatInfoSelector_BiColorRGBG10p](#),
[PixelFormatInfoSelector_BiColorRGBG12](#),
[PixelFormatInfoSelector_BiColorRGBG12p](#),
[PixelFormatInfoSelector_SCF1WBWG8](#),
[PixelFormatInfoSelector_SCF1WBWG10](#),
[PixelFormatInfoSelector_SCF1WBWG10p](#),
[PixelFormatInfoSelector_SCF1WBWG12](#),
[PixelFormatInfoSelector_SCF1WBWG12p](#),
[PixelFormatInfoSelector_SCF1WBWG14](#),
[PixelFormatInfoSelector_SCF1WBWG16](#),
[PixelFormatInfoSelector_SCF1WGWB8](#),
[PixelFormatInfoSelector_SCF1WGWB10](#),
[PixelFormatInfoSelector_SCF1WGWB10p](#),
[PixelFormatInfoSelector_SCF1WGWB12](#),
[PixelFormatInfoSelector_SCF1WGWB12p](#),
[PixelFormatInfoSelector_SCF1WGWB14](#),
[PixelFormatInfoSelector_SCF1WGWB16](#),
[PixelFormatInfoSelector_SCF1WGWR8](#),
[PixelFormatInfoSelector_SCF1WGWR10](#),
[PixelFormatInfoSelector_SCF1WGWR10p](#),
[PixelFormatInfoSelector_SCF1WGWR12](#),
[PixelFormatInfoSelector_SCF1WGWR12p](#),
[PixelFormatInfoSelector_SCF1WGWR14](#),
[PixelFormatInfoSelector_SCF1WGWR16](#),
[PixelFormatInfoSelector_SCF1WRWG8](#),
[PixelFormatInfoSelector_SCF1WRWG10](#),

PixelFormatInfoSelector_SCF1WRWG10p,
PixelFormatInfoSelector_SCF1WRWG12,
PixelFormatInfoSelector_SCF1WRWG12p,
PixelFormatInfoSelector_SCF1WRWG14,
PixelFormatInfoSelector_SCF1WRWG16,
PixelFormatInfoSelector_YCbCr8,
PixelFormatInfoSelector_YCbCr8_CbYCr,
PixelFormatInfoSelector_YCbCr10_CbYCr,
PixelFormatInfoSelector_YCbCr10p_CbYCr,
PixelFormatInfoSelector_YCbCr12_CbYCr,
PixelFormatInfoSelector_YCbCr12p_CbYCr,
PixelFormatInfoSelector_YCbCr411_8,
PixelFormatInfoSelector_YCbCr411_8_CbYYCrYY,
PixelFormatInfoSelector_YCbCr422_8,
PixelFormatInfoSelector_YCbCr422_8_CbYCrY,
PixelFormatInfoSelector_YCbCr422_10,
PixelFormatInfoSelector_YCbCr422_10_CbYCrY,
PixelFormatInfoSelector_YCbCr422_10p,
PixelFormatInfoSelector_YCbCr422_10p_CbYCrY,
PixelFormatInfoSelector_YCbCr422_12,
PixelFormatInfoSelector_YCbCr422_12_CbYCrY,
PixelFormatInfoSelector_YCbCr422_12p,
PixelFormatInfoSelector_YCbCr422_12p_CbYCrY,
PixelFormatInfoSelector_YCbCr601_8_CbYCr,
PixelFormatInfoSelector_YCbCr601_10_CbYCr,
PixelFormatInfoSelector_YCbCr601_10p_CbYCr,
PixelFormatInfoSelector_YCbCr601_12_CbYCr,
PixelFormatInfoSelector_YCbCr601_12p_CbYCr,
PixelFormatInfoSelector_YCbCr601_411_8_CbYYCrYY,
PixelFormatInfoSelector_YCbCr601_422_8,
PixelFormatInfoSelector_YCbCr601_422_8_CbYCrY,
PixelFormatInfoSelector_YCbCr601_422_10,
PixelFormatInfoSelector_YCbCr601_422_10_CbYCrY,
PixelFormatInfoSelector_YCbCr601_422_10p,
PixelFormatInfoSelector_YCbCr601_422_10p_CbYCrY,
PixelFormatInfoSelector_YCbCr601_422_12,
PixelFormatInfoSelector_YCbCr601_422_12_CbYCrY,
PixelFormatInfoSelector_YCbCr601_422_12p,
PixelFormatInfoSelector_YCbCr601_422_12p_CbYCrY,
PixelFormatInfoSelector_YCbCr709_8_CbYCr,
PixelFormatInfoSelector_YCbCr709_10_CbYCr,
PixelFormatInfoSelector_YCbCr709_10p_CbYCr,
PixelFormatInfoSelector_YCbCr709_12_CbYCr,
PixelFormatInfoSelector_YCbCr709_12p_CbYCr,
PixelFormatInfoSelector_YCbCr709_411_8_CbYYCrYY,
PixelFormatInfoSelector_YCbCr709_422_8,
PixelFormatInfoSelector_YCbCr709_422_8_CbYCrY,
PixelFormatInfoSelector_YCbCr709_422_10,
PixelFormatInfoSelector_YCbCr709_422_10_CbYCrY,
PixelFormatInfoSelector_YCbCr709_422_10p,
PixelFormatInfoSelector_YCbCr709_422_10p_CbYCrY,
PixelFormatInfoSelector_YCbCr709_422_12,
PixelFormatInfoSelector_YCbCr709_422_12_CbYCrY,
PixelFormatInfoSelector_YCbCr709_422_12p,
PixelFormatInfoSelector_YCbCr709_422_12p_CbYCrY,
PixelFormatInfoSelector_YUV8_UYV,
PixelFormatInfoSelector_YUV411_8_UYYVYY,
PixelFormatInfoSelector_YUV422_8,

```

PixelFormatInfoSelector_YUV422_8_UYVY,
PixelFormatInfoSelector_Polarized8,
PixelFormatInfoSelector_Polarized10p,
PixelFormatInfoSelector_Polarized12p,
PixelFormatInfoSelector_Polarized16,
PixelFormatInfoSelector_BayerRGPolarized8,
PixelFormatInfoSelector_BayerRGPolarized10p,
PixelFormatInfoSelector_BayerRGPolarized12p,
PixelFormatInfoSelector_BayerRGPolarized16,
PixelFormatInfoSelector_LLCMono8,
PixelFormatInfoSelector_LLCBayerRG8,
PixelFormatInfoSelector_JPEGMono8,
PixelFormatInfoSelector_JPEGColor8,
NUM_PIXELFORMATINFOSELECTOR }

• enum spinDeinterlacingEnums {
    Deinterlacing_Off,
    Deinterlacing_LineDuplication,
    Deinterlacing_Weave,
    NUM_DEINTERLACING }

• enum spinImageCompressionRateOptionEnums {
    ImageCompressionRateOption_FixBitrate,
    ImageCompressionRateOption_FixQuality,
    NUM_IMAGECOMPRESSIONRATEOPTION }

• enum spinImageCompressionJPEGFormatOptionEnums {
    ImageCompressionJPEGFormatOption_Lossless,
    ImageCompressionJPEGFormatOption_BaselineStandard,
    ImageCompressionJPEGFormatOption_BaselineOptimized,
    ImageCompressionJPEGFormatOption_Progressive,
    NUM_IMAGECOMPRESSIONJPEGFORMATOPTION }

• enum spinAcquisitionStatusSelectorEnums {
    AcquisitionStatusSelector_AcquisitionTriggerWait,
    AcquisitionStatusSelector_AcquisitionActive,
    AcquisitionStatusSelector_AcquisitionTransfer,
    AcquisitionStatusSelector_FrameTriggerWait,
    AcquisitionStatusSelector_FrameActive,
    AcquisitionStatusSelector_ExposureActive,
    NUM_ACQUISITIONSTATUSSELECTOR }

• enum spinExposureTimeModeEnums {
    ExposureTimeMode_Common,
    ExposureTimeMode_Individual,
    NUM_EXPOSURETIMEMODE }

• enum spinExposureTimeSelectorEnums {
    ExposureTimeSelector_Common,
    ExposureTimeSelector_Red,
    ExposureTimeSelector_Green,
    ExposureTimeSelector_Blue,
    ExposureTimeSelector_Cyan,
    ExposureTimeSelector_Magenta,
    ExposureTimeSelector_Yellow,
    ExposureTimeSelector_Infrared,
    ExposureTimeSelector_Ultraviolet,
    ExposureTimeSelector_Stage1,
    ExposureTimeSelector_Stage2,
    NUM_EXPOSURETIMESELECTOR }

• enum spinGainAutoBalanceEnums {
    GainAutoBalance_Off,
    GainAutoBalance_Once,

```

```
GainAutoBalance_Continuous,  
NUM_GAINAUTOBALANCE }  
• enum spinBlackLevelAutoEnums {  
    BlackLevelAuto_Off,  
    BlackLevelAuto_Once,  
    BlackLevelAuto_Continuous,  
    NUM_BLACKLEVELAUTO }  
• enum spinBlackLevelAutoBalanceEnums {  
    BlackLevelAutoBalance_Off,  
    BlackLevelAutoBalance_Once,  
    BlackLevelAutoBalance_Continuous,  
    NUM_BLACKLEVELAUTOBALANCE }  
• enum spinWhiteClipSelectorEnums {  
    WhiteClipSelector_All,  
    WhiteClipSelector_Red,  
    WhiteClipSelector_Green,  
    WhiteClipSelector_Blue,  
    WhiteClipSelector_Y,  
    WhiteClipSelector_U,  
    WhiteClipSelector_V,  
    WhiteClipSelector_Tap1,  
    WhiteClipSelector_Tap2,  
    NUM_WHITECLIPSELECTOR }  
• enum spinTimerSelectorEnums {  
    TimerSelector_Timer0,  
    TimerSelector_Timer1,  
    TimerSelector_Timer2,  
    NUM_TIMERSELECTOR }  
• enum spinTimerStatusEnums {  
    TimerStatus_TimerIdle,  
    TimerStatus_TimerTriggerWait,  
    TimerStatus_TimerActive,  
    TimerStatus_TimerCompleted,  
    NUM_TIMERSTATUS }  
• enum spinTimerTriggerSourceEnums {  
    TimerTriggerSource_Off,  
    TimerTriggerSource_AcquisitionTrigger,  
    TimerTriggerSource_AcquisitionStart,  
    TimerTriggerSource_AcquisitionEnd,  
    TimerTriggerSource_FrameTrigger,  
    TimerTriggerSource_FrameStart,  
    TimerTriggerSource_FrameEnd,  
    TimerTriggerSource_FrameBurstStart,  
    TimerTriggerSource_FrameBurstEnd,  
    TimerTriggerSource_LineTrigger,  
    TimerTriggerSource_LineStart,  
    TimerTriggerSource_LineEnd,  
    TimerTriggerSource_ExposureStart,  
    TimerTriggerSource_ExposureEnd,  
    TimerTriggerSource_Line0,  
    TimerTriggerSource_Line1,  
    TimerTriggerSource_Line2,  
    TimerTriggerSource_UserOutput0,  
    TimerTriggerSource_UserOutput1,  
    TimerTriggerSource_UserOutput2,  
    TimerTriggerSource_Counter0Start,  
    TimerTriggerSource_Counter1Start,  
    TimerTriggerSource_Counter2Start,
```

```

TimerTriggerSource_Counter0End,
TimerTriggerSource_Counter1End,
TimerTriggerSource_Counter2End,
TimerTriggerSource_Timer0Start,
TimerTriggerSource_Timer1Start,
TimerTriggerSource_Timer2Start,
TimerTriggerSource_Timer0End,
TimerTriggerSource_Timer1End,
TimerTriggerSource_Timer2End,
TimerTriggerSource_Encoder0,
TimerTriggerSource_Encoder1,
TimerTriggerSource_Encoder2,
TimerTriggerSource_SoftwareSignal0,
TimerTriggerSource_SoftwareSignal1,
TimerTriggerSource_SoftwareSignal2,
TimerTriggerSource_Action0,
TimerTriggerSource_Action1,
TimerTriggerSource_Action2,
TimerTriggerSource_LinkTrigger0,
TimerTriggerSource_LinkTrigger1,
TimerTriggerSource_LinkTrigger2,
NUM_TIMERTRIGGERSOURCE }

• enum spinTimerTriggerActivationEnums {
    TimerTriggerActivation_RisingEdge,
    TimerTriggerActivation_FallingEdge,
    TimerTriggerActivation_AnyEdge,
    TimerTriggerActivation_LevelHigh,
    TimerTriggerActivation_LevelLow,
    NUM_TIMERTRIGGERACTIVATION }

• enum spinEncoderSelectorEnums {
    EncoderSelector_Encoder0,
    EncoderSelector_Encoder1,
    EncoderSelector_Encoder2,
    NUM_ENCODERSELECTOR }

• enum spinEncoderSourceAEnums {
    EncoderSourceA_Off,
    EncoderSourceA_Line0,
    EncoderSourceA_Line1,
    EncoderSourceA_Line2,
    NUM_ENCODERSOURCEA }

• enum spinEncoderSourceBEnums {
    EncoderSourceB_Off,
    EncoderSourceB_Line0,
    EncoderSourceB_Line1,
    EncoderSourceB_Line2,
    NUM_ENCODERSOURCEB }

• enum spinEncoderModeEnums {
    EncoderMode_FourPhase,
    EncoderMode_HighResolution,
    NUM_ENCODERMODE }

• enum spinEncoderOutputModeEnums {
    EncoderOutputMode_Off,
    EncoderOutputMode_PositionUp,
    EncoderOutputMode_PositionDown,
    EncoderOutputMode_DirectionUp,
    EncoderOutputMode_DirectionDown,
    EncoderOutputMode_Motion,
    NUM_ENCODEROUTPUTMODE }

```


- enum spinEncoderStatusEnums {
EncoderStatus_EncoderUp,
EncoderStatus_EncoderDown,
EncoderStatus_EncoderIdle,
EncoderStatus_EncoderStatic,
NUM_ENCODERSTATUS }
- enum spinEncoderResetSourceEnums {
EncoderResetSource_Off,
EncoderResetSource_AcquisitionTrigger,
EncoderResetSource_AcquisitionStart,
EncoderResetSource_AcquisitionEnd,
EncoderResetSource_FrameTrigger,
EncoderResetSource_FrameStart,
EncoderResetSource_FrameEnd,
EncoderResetSource_ExposureStart,
EncoderResetSource_ExposureEnd,
EncoderResetSource_Line0,
EncoderResetSource_Line1,
EncoderResetSource_Line2,
EncoderResetSource_Counter0Start,
EncoderResetSource_Counter1Start,
EncoderResetSource_Counter2Start,
EncoderResetSource_Counter0End,
EncoderResetSource_Counter1End,
EncoderResetSource_Counter2End,
EncoderResetSource_Timer0Start,
EncoderResetSource_Timer1Start,
EncoderResetSource_Timer2Start,
EncoderResetSource_Timer0End,
EncoderResetSource_Timer1End,
EncoderResetSource_Timer2End,
EncoderResetSource_UserOutput0,
EncoderResetSource_UserOutput1,
EncoderResetSource_UserOutput2,
EncoderResetSource_SoftwareSignal0,
EncoderResetSource_SoftwareSignal1,
EncoderResetSource_SoftwareSignal2,
EncoderResetSource_Action0,
EncoderResetSource_Action1,
EncoderResetSource_Action2,
EncoderResetSource_LinkTrigger0,
EncoderResetSource_LinkTrigger1,
EncoderResetSource_LinkTrigger2,
NUM_ENCODERRESETSOURCE }
- enum spinEncoderResetActivationEnums {
EncoderResetActivation_RisingEdge,
EncoderResetActivation_FallingEdge,
EncoderResetActivation_AnyEdge,
EncoderResetActivation_LevelHigh,
EncoderResetActivation_LevelLow,
NUM_ENCODERRESETACTIVATION }
- enum spinSoftwareSignalSelectorEnums {
SoftwareSignalSelector_SoftwareSignal0,
SoftwareSignalSelector_SoftwareSignal1,
SoftwareSignalSelector_SoftwareSignal2,
NUM_SOFTWARESIGNALSELECTOR }
- enum spinActionUnconditionalModeEnums {
ActionUnconditionalMode_Off,

```

    ActionUnconditionalMode_On,
    NUM_ACTIONUNCONDITIONALMODE }
• enum spinSourceSelectorEnums {
    SourceSelector_Source0,
    SourceSelector_Source1,
    SourceSelector_Source2,
    SourceSelector_All,
    NUM_SOURCESELECTOR }
• enum spinTransferSelectorEnums {
    TransferSelector_Stream0,
    TransferSelector_Stream1,
    TransferSelector_Stream2,
    TransferSelector_All,
    NUM_TRANSFERSELECTOR }
• enum spinTransferTriggerSelectorEnums {
    TransferTriggerSelector_TransferStart,
    TransferTriggerSelector_TransferStop,
    TransferTriggerSelector_TransferAbort,
    TransferTriggerSelector_TransferPause,
    TransferTriggerSelector_TransferResume,
    TransferTriggerSelector_TransferActive,
    TransferTriggerSelector_TransferBurstStart,
    TransferTriggerSelector_TransferBurstStop,
    NUM_TRANSFERTRIGGERSELECTOR }
• enum spinTransferTriggerModeEnums {
    TransferTriggerMode_Off,
    TransferTriggerMode_On,
    NUM_TRANSFERTRIGGERMODE }
• enum spinTransferTriggerSourceEnums {
    TransferTriggerSource_Line0,
    TransferTriggerSource_Line1,
    TransferTriggerSource_Line2,
    TransferTriggerSource_Counter0Start,
    TransferTriggerSource_Counter1Start,
    TransferTriggerSource_Counter2Start,
    TransferTriggerSource_Counter0End,
    TransferTriggerSource_Counter1End,
    TransferTriggerSource_Counter2End,
    TransferTriggerSource_Timer0Start,
    TransferTriggerSource_Timer1Start,
    TransferTriggerSource_Timer2Start,
    TransferTriggerSource_Timer0End,
    TransferTriggerSource_Timer1End,
    TransferTriggerSource_Timer2End,
    TransferTriggerSource_SoftwareSignal0,
    TransferTriggerSource_SoftwareSignal1,
    TransferTriggerSource_SoftwareSignal2,
    TransferTriggerSource_Action0,
    TransferTriggerSource_Action1,
    TransferTriggerSource_Action2,
    NUM_TRANSFERTRIGGERSOURCE }
• enum spinTransferTriggerActivationEnums {
    TransferTriggerActivation_RisingEdge,
    TransferTriggerActivation_FallingEdge,
    TransferTriggerActivation_AnyEdge,
    TransferTriggerActivation_LevelHigh,
    TransferTriggerActivation_LevelLow,
    NUM_TRANSFERTRIGGERACTIVATION }

```

- enum spinTransferStatusSelectorEnums {
TransferStatusSelector_Streaming,
TransferStatusSelector_Paused,
TransferStatusSelector_Stopping,
TransferStatusSelector_Stopped,
TransferStatusSelector_QueueOverflow,
NUM_TRANSFERSTATUSSELECTOR }
- enum spinTransferComponentSelectorEnums {
TransferComponentSelector_Red,
TransferComponentSelector_Green,
TransferComponentSelector_Blue,
TransferComponentSelector_All,
NUM_TRANSFERCOMPONENTSELECTOR }
- enum spinScan3dDistanceUnitEnums {
Scan3dDistanceUnit_Millimeter,
Scan3dDistanceUnit_Inch,
NUM_SCAN3DDISTANCEUNIT }
- enum spinScan3dCoordinateSystemEnums {
Scan3dCoordinateSystem_Cartesian,
Scan3dCoordinateSystem_Spherical,
Scan3dCoordinateSystem_Cylindrical,
NUM_SCAN3DCOORDINATESYSTEM }
- enum spinScan3dOutputModeEnums {
Scan3dOutputMode_UncalibratedC,
Scan3dOutputMode_CalibratedABC_Grid,
Scan3dOutputMode_CalibratedABC_PointCloud,
Scan3dOutputMode_CalibratedAC,
Scan3dOutputMode_CalibratedAC_Linescan,
Scan3dOutputMode_CalibratedC,
Scan3dOutputMode_CalibratedC_Linescan,
Scan3dOutputMode_RectifiedC,
Scan3dOutputMode_RectifiedC_Linescan,
Scan3dOutputMode_DisparityC,
Scan3dOutputMode_DisparityC_Linescan,
NUM_SCAN3DOUTPUTMODE }
- enum spinScan3dCoordinateSystemReferenceEnums {
Scan3dCoordinateSystemReference_Anchor,
Scan3dCoordinateSystemReference_Transformed,
NUM_SCAN3DCOORDINATESYSTEMREFERENCE }
- enum spinScan3dCoordinateSelectorEnums {
Scan3dCoordinateSelector_CoordinateA,
Scan3dCoordinateSelector_CoordinateB,
Scan3dCoordinateSelector_CoordinateC,
NUM_SCAN3DCOORDINATESELECTOR }
- enum spinScan3dCoordinateTransformSelectorEnums {
Scan3dCoordinateTransformSelector_RotationX,
Scan3dCoordinateTransformSelector_RotationY,
Scan3dCoordinateTransformSelector_RotationZ,
Scan3dCoordinateTransformSelector_TranslationX,
Scan3dCoordinateTransformSelector_TranslationY,
Scan3dCoordinateTransformSelector_TranslationZ,
NUM_SCAN3DCOORDINATETRANSFORMSELECTOR }
- enum spinScan3dCoordinateReferenceSelectorEnums {
Scan3dCoordinateReferenceSelector_RotationX,
Scan3dCoordinateReferenceSelector_RotationY,
Scan3dCoordinateReferenceSelector_RotationZ,
Scan3dCoordinateReferenceSelector_TranslationX,
Scan3dCoordinateReferenceSelector_TranslationY,

```

Scan3dCoordinateReferenceSelector_TranslationZ,
NUM_SCAN3DCOORDINATEREFERENCESELECTOR }
• enum spinChunkImageComponentEnums {
    ChunkImageComponent_Intensity,
    ChunkImageComponent_Color,
    ChunkImageComponent_Infrared,
    ChunkImageComponent_Ultraviolet,
    ChunkImageComponent_Range,
    ChunkImageComponent_Disparity,
    ChunkImageComponent_Confidence,
    ChunkImageComponent_Scatter,
    NUM_CHUNKIMAGECOMPONENT }
• enum spinChunkCounterSelectorEnums {
    ChunkCounterSelector_Counter0,
    ChunkCounterSelector_Counter1,
    ChunkCounterSelector_Counter2,
    NUM_CHUNKCOUNTERSELECTOR }
• enum spinChunkTimerSelectorEnums {
    ChunkTimerSelector_Timer0,
    ChunkTimerSelector_Timer1,
    ChunkTimerSelector_Timer2,
    NUM_CHUNKTIMERSELECTOR }
• enum spinChunkEncoderSelectorEnums {
    ChunkEncoderSelector_Encoder0,
    ChunkEncoderSelector_Encoder1,
    ChunkEncoderSelector_Encoder2,
    NUM_CHUNKENCODERSELECTOR }
• enum spinChunkEncoderStatusEnums {
    ChunkEncoderStatus_EncoderUp,
    ChunkEncoderStatus_EncoderDown,
    ChunkEncoderStatus_EncoderIdle,
    ChunkEncoderStatus_EncoderStatic,
    NUM_CHUNKENCODERSTATUS }
• enum spinChunkExposureTimeSelectorEnums {
    ChunkExposureTimeSelector_Common,
    ChunkExposureTimeSelector_Red,
    ChunkExposureTimeSelector_Green,
    ChunkExposureTimeSelector_Blue,
    ChunkExposureTimeSelector_Cyan,
    ChunkExposureTimeSelector_Magenta,
    ChunkExposureTimeSelector_Yellow,
    ChunkExposureTimeSelector_Infrared,
    ChunkExposureTimeSelector_Ultraviolet,
    ChunkExposureTimeSelector_Stage1,
    ChunkExposureTimeSelector_Stage2,
    NUM_CHUNKEXPOSURETIMESELECTOR }
• enum spinChunkSourceIDEnums {
    ChunkSourceID_Source0,
    ChunkSourceID_Source1,
    ChunkSourceID_Source2,
    NUM_CHUNKSOURCEID }
• enum spinChunkRegionIDEnums {
    ChunkRegionID_Region0,
    ChunkRegionID_Region1,
    ChunkRegionID_Region2,
    NUM_CHUNKREGIONID }
• enum spinChunkTransferStreamIDEnums {
    ChunkTransferStreamID_Stream0,

```

```

    ChunkTransferStreamID_Stream1,
    ChunkTransferStreamID_Stream2,
    ChunkTransferStreamID_Stream3,
    NUM_CHUNKTRANSFERSTREAMID }
• enum spinChunkScan3dDistanceUnitEnums {
    ChunkScan3dDistanceUnit_Millimeter,
    ChunkScan3dDistanceUnit_Inch,
    NUM_CHUNKSCAN3DDISTANCEUNIT }
• enum spinChunkScan3dOutputModeEnums {
    ChunkScan3dOutputMode_UncalibratedC,
    ChunkScan3dOutputMode_CalibratedABC_Grid,
    ChunkScan3dOutputMode_CalibratedABC_PointCloud,
    ChunkScan3dOutputMode_CalibratedAC,
    ChunkScan3dOutputMode_CalibratedAC_Linescan,
    ChunkScan3dOutputMode_CalibratedC,
    ChunkScan3dOutputMode_CalibratedC_Linescan,
    ChunkScan3dOutputMode_RectifiedC,
    ChunkScan3dOutputMode_RectifiedC_Linescan,
    ChunkScan3dOutputMode_DisparityC,
    ChunkScan3dOutputMode_DisparityC_Linescan,
    NUM_CHUNKSCAN3DOUTPUTMODE }
• enum spinChunkScan3dCoordinateSystemEnums {
    ChunkScan3dCoordinateSystem_Cartesian,
    ChunkScan3dCoordinateSystem_Spherical,
    ChunkScan3dCoordinateSystem_Cylindrical,
    NUM_CHUNKSCAN3DCOORDINATESYSTEM }
• enum spinChunkScan3dCoordinateSystemReferenceEnums {
    ChunkScan3dCoordinateSystemReference_Anchor,
    ChunkScan3dCoordinateSystemReference_Transformed,
    NUM_CHUNKSCAN3DCOORDINATESYSTEMREFERENCE }
• enum spinChunkScan3dCoordinateSelectorEnums {
    ChunkScan3dCoordinateSelector_CoordinateA,
    ChunkScan3dCoordinateSelector_CoordinateB,
    ChunkScan3dCoordinateSelector_CoordinateC,
    NUM_CHUNKSCAN3DCOORDINATESELECTOR }
• enum spinChunkScan3dCoordinateTransformSelectorEnums {
    ChunkScan3dCoordinateTransformSelector_RotationX,
    ChunkScan3dCoordinateTransformSelector_RotationY,
    ChunkScan3dCoordinateTransformSelector_RotationZ,
    ChunkScan3dCoordinateTransformSelector_TranslationX,
    ChunkScan3dCoordinateTransformSelector_TranslationY,
    ChunkScan3dCoordinateTransformSelector_TranslationZ,
    NUM_CHUNKSCAN3DCOORDINATETRANSFORMSELECTOR }
• enum spinChunkScan3dCoordinateReferenceSelectorEnums {
    ChunkScan3dCoordinateReferenceSelector_RotationX,
    ChunkScan3dCoordinateReferenceSelector_RotationY,
    ChunkScan3dCoordinateReferenceSelector_RotationZ,
    ChunkScan3dCoordinateReferenceSelector_TranslationX,
    ChunkScan3dCoordinateReferenceSelector_TranslationY,
    ChunkScan3dCoordinateReferenceSelector_TranslationZ,
    NUM_CHUNKSCAN3DCOORDINATEREFERENCESELECTOR }
• enum spinDeviceTapGeometryEnums {
    DeviceTapGeometry_Geometry_1X_1Y,
    DeviceTapGeometry_Geometry_1X2_1Y,
    DeviceTapGeometry_Geometry_1X2_1Y2,
    DeviceTapGeometry_Geometry_2X_1Y,
    DeviceTapGeometry_Geometry_2X_1Y2Geometry_2XE_1Y,
    DeviceTapGeometry_Geometry_2XE_1Y2,

```

```

DeviceTapGeometry_Geometry_2XM_1Y,
DeviceTapGeometry_Geometry_2XM_1Y2,
DeviceTapGeometry_Geometry_1X_1Y2,
DeviceTapGeometry_Geometry_1X_2YE,
DeviceTapGeometry_Geometry_1X3_1Y,
DeviceTapGeometry_Geometry_3X_1Y,
DeviceTapGeometry_Geometry_1X,
DeviceTapGeometry_Geometry_1X2,
DeviceTapGeometry_Geometry_2X,
DeviceTapGeometry_Geometry_2XE,
DeviceTapGeometry_Geometry_2XM,
DeviceTapGeometry_Geometry_1X3,
DeviceTapGeometry_Geometry_3X,
DeviceTapGeometry_Geometry_1X4_1Y,
DeviceTapGeometry_Geometry_4X_1Y,
DeviceTapGeometry_Geometry_2X2_1Y,
DeviceTapGeometry_Geometry_2X2E_1YGeometry_2X2M_1Y,
DeviceTapGeometry_Geometry_1X2_2YE,
DeviceTapGeometry_Geometry_2X_2YE,
DeviceTapGeometry_Geometry_2XE_2YE,
DeviceTapGeometry_Geometry_2XM_2YE,
DeviceTapGeometry_Geometry_1X4,
DeviceTapGeometry_Geometry_4X,
DeviceTapGeometry_Geometry_2X2,
DeviceTapGeometry_Geometry_2X2E,
DeviceTapGeometry_Geometry_2X2M,
DeviceTapGeometry_Geometry_1X8_1Y,
DeviceTapGeometry_Geometry_8X_1Y,
DeviceTapGeometry_Geometry_4X2_1Y,
DeviceTapGeometry_Geometry_2X2E_2YE,
DeviceTapGeometry_Geometry_1X8,
DeviceTapGeometry_Geometry_8X,
DeviceTapGeometry_Geometry_4X2,
DeviceTapGeometry_Geometry_4X2E,
DeviceTapGeometry_Geometry_4X2E_1Y,
DeviceTapGeometry_Geometry_1X10_1Y,
DeviceTapGeometry_Geometry_10X_1Y,
DeviceTapGeometry_Geometry_1X10,
DeviceTapGeometry_Geometry_10X,
NUM_DEVICETAPGEOMETRY }

• enum spinGevPhysicalLinkConfigurationEnums {
    GevPhysicalLinkConfiguration_SingleLink,
    GevPhysicalLinkConfiguration_MultiLink,
    GevPhysicalLinkConfiguration_StaticLAG,
    GevPhysicalLinkConfiguration_DynamicLAG,
    NUM_GEVPHYSICALLINKCONFIGURATION }

• enum spinGevCurrentPhysicalLinkConfigurationEnums {
    GevCurrentPhysicalLinkConfiguration_SingleLink,
    GevCurrentPhysicalLinkConfiguration_MultiLink,
    GevCurrentPhysicalLinkConfiguration_StaticLAG,
    GevCurrentPhysicalLinkConfiguration_DynamicLAG,
    NUM_GEVCURRENTPHYSICALLINKCONFIGURATION }

• enum spinGevIPConfigurationStatusEnums {
    GevIPConfigurationStatus_None,
    GevIPConfigurationStatus_PersistentIP,
    GevIPConfigurationStatus_DHCP,
    GevIPConfigurationStatus_LLA,
    GevIPConfigurationStatus_ForceIP,

```

```

NUM_GEVIPCONFIGURATIONSTATUS }

• enum spinGevGVCPExtendedStatusCodesSelectorEnums {
    GevGVCPExtendedStatusCodesSelector_Version1_1,
    GevGVCPExtendedStatusCodesSelector_Version2_0,
    NUM_GEVGVCPEXTENDEDSTATUSCODESSELECTOR }

• enum spinGevGVSPExtendedIDModeEnums {
    GevGVSPExtendedIDMode_Off,
    GevGVSPExtendedIDMode_On,
    NUM_GEVGVSPEXTENDEDIDMODE }

• enum spinCIConfigurationEnums {
    CIConfiguration_Base,
    CIConfiguration_Medium,
    CIConfiguration_Full,
    CIConfiguration_DualBase,
    CIConfiguration_EightyBit,
    NUM_CLCONFIGURATION }

• enum spinCITimeSlotsCountEnums {
    CITimeSlotsCount_One,
    CITimeSlotsCount_Two,
    CITimeSlotsCount_Three,
    NUM_CLTIMESLOTSCOUNT }

• enum spinCxpLinkConfigurationStatusEnums {
    CxpLinkConfigurationStatus_None,
    CxpLinkConfigurationStatus_Pending,
    CxpLinkConfigurationStatus_CXP1_X1,
    CxpLinkConfigurationStatus_CXP2_X1,
    CxpLinkConfigurationStatus_CXP3_X1,
    CxpLinkConfigurationStatus_CXP5_X1,
    CxpLinkConfigurationStatus_CXP6_X1,
    CxpLinkConfigurationStatus_CXP1_X2,
    CxpLinkConfigurationStatus_CXP2_X2,
    CxpLinkConfigurationStatus_CXP3_X2,
    CxpLinkConfigurationStatus_CXP5_X2,
    CxpLinkConfigurationStatus_CXP6_X2,
    CxpLinkConfigurationStatus_CXP1_X3,
    CxpLinkConfigurationStatus_CXP2_X3,
    CxpLinkConfigurationStatus_CXP3_X3,
    CxpLinkConfigurationStatus_CXP5_X3,
    CxpLinkConfigurationStatus_CXP6_X3,
    CxpLinkConfigurationStatus_CXP1_X4,
    CxpLinkConfigurationStatus_CXP2_X4,
    CxpLinkConfigurationStatus_CXP3_X4,
    CxpLinkConfigurationStatus_CXP5_X4,
    CxpLinkConfigurationStatus_CXP6_X4,
    CxpLinkConfigurationStatus_CXP1_X5,
    CxpLinkConfigurationStatus_CXP2_X5,
    CxpLinkConfigurationStatus_CXP3_X5,
    CxpLinkConfigurationStatus_CXP5_X5,
    CxpLinkConfigurationStatus_CXP6_X5,
    CxpLinkConfigurationStatus_CXP1_X6,
    CxpLinkConfigurationStatus_CXP2_X6,
    CxpLinkConfigurationStatus_CXP3_X6,
    CxpLinkConfigurationStatus_CXP5_X6,
    CxpLinkConfigurationStatus_CXP6_X6,
    NUM_CXPLINKCONFIGURATIONSTATUS }

• enum spinCxpLinkConfigurationPreferredEnums {
    CxpLinkConfigurationPreferred_CXP1_X1,
    CxpLinkConfigurationPreferred_CXP2_X1,

```

```

CxpLinkConfigurationPreferred_CXP3_X1,
CxpLinkConfigurationPreferred_CXP5_X1,
CxpLinkConfigurationPreferred_CXP6_X1,
CxpLinkConfigurationPreferred_CXP1_X2,
CxpLinkConfigurationPreferred_CXP2_X2,
CxpLinkConfigurationPreferred_CXP3_X2,
CxpLinkConfigurationPreferred_CXP5_X2,
CxpLinkConfigurationPreferred_CXP6_X2,
CxpLinkConfigurationPreferred_CXP1_X3,
CxpLinkConfigurationPreferred_CXP2_X3,
CxpLinkConfigurationPreferred_CXP3_X3,
CxpLinkConfigurationPreferred_CXP5_X3,
CxpLinkConfigurationPreferred_CXP6_X3,
CxpLinkConfigurationPreferred_CXP1_X4,
CxpLinkConfigurationPreferred_CXP2_X4,
CxpLinkConfigurationPreferred_CXP3_X4,
CxpLinkConfigurationPreferred_CXP5_X4,
CxpLinkConfigurationPreferred_CXP6_X4,
CxpLinkConfigurationPreferred_CXP1_X5,
CxpLinkConfigurationPreferred_CXP2_X5,
CxpLinkConfigurationPreferred_CXP3_X5,
CxpLinkConfigurationPreferred_CXP5_X5,
CxpLinkConfigurationPreferred_CXP6_X5,
CxpLinkConfigurationPreferred_CXP1_X6,
CxpLinkConfigurationPreferred_CXP2_X6,
CxpLinkConfigurationPreferred_CXP3_X6,
CxpLinkConfigurationPreferred_CXP5_X6,
CxpLinkConfigurationPreferred_CXP6_X6,
NUM_CXPLINKCONFIGURATIONPREFERRED }

```

- `enum spinCxpLinkConfigurationEnums {`

```

CxpLinkConfiguration_Auto,
CxpLinkConfiguration_CXP1_X1,
CxpLinkConfiguration_CXP2_X1,
CxpLinkConfiguration_CXP3_X1,
CxpLinkConfiguration_CXP5_X1,
CxpLinkConfiguration_CXP6_X1,
CxpLinkConfiguration_CXP1_X2,
CxpLinkConfiguration_CXP2_X2,
CxpLinkConfiguration_CXP3_X2,
CxpLinkConfiguration_CXP5_X2,
CxpLinkConfiguration_CXP6_X2,
CxpLinkConfiguration_CXP1_X3,
CxpLinkConfiguration_CXP2_X3,
CxpLinkConfiguration_CXP3_X3,
CxpLinkConfiguration_CXP5_X3,
CxpLinkConfiguration_CXP6_X3,
CxpLinkConfiguration_CXP1_X4,
CxpLinkConfiguration_CXP2_X4,
CxpLinkConfiguration_CXP3_X4,
CxpLinkConfiguration_CXP5_X4,
CxpLinkConfiguration_CXP6_X4,
CxpLinkConfiguration_CXP1_X5,
CxpLinkConfiguration_CXP2_X5,
CxpLinkConfiguration_CXP3_X5,
CxpLinkConfiguration_CXP5_X5,
CxpLinkConfiguration_CXP6_X5,
CxpLinkConfiguration_CXP1_X6,
CxpLinkConfiguration_CXP2_X6,

```



```

CxpLinkConfiguration_CXP3_X6,
CxpLinkConfiguration_CXP5_X6,
CxpLinkConfiguration_CXP6_X6,
NUM_CXPLINKCONFIGURATION }
• enum spinCxpConnectionTestModeEnums {
  CxpConnectionTestMode_Off,
  CxpConnectionTestMode_Mode1,
  NUM_CXPCONNECTIONTESTMODE }
• enum spinCxpPoCxpStatusEnums {
  CxpPoCxpStatus_Auto,
  CxpPoCxpStatus_Off,
  CxpPoCxpStatus_Tripped,
  NUM_CXPPOCXPSTATUS }

```

4.2.1 Detailed Description

4.2.2 Enumeration Type Documentation

4.2.2.1 spinAcquisitionModeEnums

```
enum spinAcquisitionModeEnums
```

< Sets the acquisition mode of the device. Continuous: acquires images continuously. Multi Frame: acquires a specified number of images before stopping acquisition. Single Frame: acquires 1 image before stopping acquisition.

Enumerator

AcquisitionMode_Continuous	
AcquisitionMode_SingleFrame	
AcquisitionMode_MultiFrame	
NUM_ACQUISITIONMODE	

4.2.2.2 spinAcquisitionStatusSelectorEnums

```
enum spinAcquisitionStatusSelectorEnums
```

< Selects the internal acquisition signal to read using AcquisitionStatus.

Enumerator

AcquisitionStatusSelector_AcquisitionTriggerWait	Device is currently waiting for a trigger for the capture of one or many frames.
AcquisitionStatusSelector_AcquisitionActive	Device is currently doing an acquisition of one or many frames.

Enumerator

AcquisitionStatusSelector_AcquisitionTransfer	Device is currently transferring an acquisition of one or many frames.
AcquisitionStatusSelector_FrameTriggerWait	Device is currently waiting for a frame start trigger.
AcquisitionStatusSelector_FrameActive	Device is currently doing the capture of a frame.
AcquisitionStatusSelector_ExposureActive	Device is doing the exposure of a frame.
NUM_ACQUISITIONSTATUSSELECTOR	

4.2.2.3 spinActionUnconditionalModeEnums

enum `spinActionUnconditionalModeEnums`

< Enables the unconditional action command mode where action commands are processed even when the primary control channel is closed.

Enumerator

ActionUnconditionalMode_Off	Unconditional mode is disabled.
ActionUnconditionalMode_On	Unconditional mode is enabled.
NUM_ACTIONUNCONDITIONALMODE	

4.2.2.4 spinAdcBitDepthEnums

enum `spinAdcBitDepthEnums`

< Selects which ADC bit depth to use. A higher ADC bit depth results in better image quality but slower maximum frame rate.

Enumerator

AdcBitDepth_Bit8	
AdcBitDepth_Bit10	
AdcBitDepth_Bit12	
AdcBitDepth_Bit14	
NUM_ADCBITDEPTH	

4.2.2.5 spinAutoAlgorithmSelectorEnums

enum `spinAutoAlgorithmSelectorEnums`

< Selects which Auto Algorithm is controlled by the RoiEnable, OffsetX, OffsetY, Width, Height features.

Enumerator

AutoAlgorithmSelector_Awb	Selects the Auto White Balance algorithm.
AutoAlgorithmSelector_Ae	Selects the Auto Exposure algorithm.
NUM_AUTOALGORITHMSELECTOR	

4.2.2.6 spinAutoExposureControlPriorityEnums

```
enum spinAutoExposureControlPriorityEnums
```

< Selects whether to adjust gain or exposure first. When gain priority is selected, the camera fixes the gain to 0 dB, and the exposure is adjusted according to the target grey level. If the maximum exposure is reached before the target grey level is hit, the gain starts to change to meet the target. This mode is used to have the minimum noise. When exposure priority is selected, the camera sets the exposure to a small value (default is 5 ms). The gain is adjusted according to the target grey level. If maximum gain is reached before the target grey level is hit, the exposure starts to change to meet the target. This mode is used to capture fast motion.

Enumerator

AutoExposureControlPriority_Gain	
AutoExposureControlPriority_ExposureTime	
NUM_AUTOEXPOSURECONTROLPRIORITY	

4.2.2.7 spinAutoExposureLightingModeEnums

```
enum spinAutoExposureLightingModeEnums
```

< Selects a lighting mode: Backlight, Frontlight or Normal (default). a. Backlight compensation: used when a strong light is coming from the back of the object. b. Frontlight compensation: used when a strong light is shining in the front of the object while the background is dark. c. Normal lighting: used when the object is not under backlight or frontlight conditions. When normal lighting is selected, metering modes are available.

Enumerator

AutoExposureLightingMode_AutoDetect	
AutoExposureLightingMode_Backlight	
AutoExposureLightingMode_Frontlight	
AutoExposureLightingMode_Normal	
NUM_AUTOEXPOSURELIGHTINGMODE	

4.2.2.8 spinAutoExposureMeteringModeEnums

```
enum spinAutoExposureMeteringModeEnums
```

< Selects a metering mode: average, spot, or partial metering. a. Average: Measures the light from the entire scene uniformly to determine the final exposure value. Every portion of the exposed area has the same contribution. b. Spot: Measures a small area (about 3%) in the center of the scene while the rest of the scene is ignored. This mode is used when the scene has a high contrast and the object of interest is relatively small. c. Partial: Measures the light from a larger area (about 11%) in the center of the scene. This mode is used when very dark or bright regions appear at the edge of the frame. Note: Metering mode is available only when Lighting Mode Selector is Normal.

Enumerator

AutoExposureMeteringMode_Average	
AutoExposureMeteringMode_Spot	
AutoExposureMeteringMode_Partial	
AutoExposureMeteringMode_CenterWeighted	
AutoExposureMeteringMode_HistogramPeak	
NUM_AUTOEXPOSUREMETERINGMODE	

4.2.2.9 spinAutoExposureTargetGreyValueAutoEnums

enum `spinAutoExposureTargetGreyValueAutoEnums`

< This indicates whether the target image grey level is automatically set by the camera or manually set by the user. Note that the target grey level is in the linear domain before gamma correction is applied.

Enumerator

AutoExposureTargetGreyValueAuto_Off	Target grey value is manually controlled
AutoExposureTargetGreyValueAuto_Continuous	Target grey value is constantly adapted by the device to maximize the dynamic range.
NUM_AUTOEXPOSURETARGETGREYVALUEAUTO	

4.2.2.10 spinBalanceRatioSelectorEnums

enum `spinBalanceRatioSelectorEnums`

< Selects a balance ratio to configure once a balance ratio control has been selected.

Enumerator

BalanceRatioSelector_Red	Selects the red balance ratio control for adjustment. The red balance ratio is relative to the green channel.
BalanceRatioSelector_Blue	Selects the blue balance ratio control for adjustment. The blue balance ratio is relative to the green channel.
NUM_BALANCERATIOSELECTOR	

4.2.2.11 spinBalanceWhiteAutoEnums

```
enum spinBalanceWhiteAutoEnums
```

< White Balance compensates for color shifts caused by different lighting conditions. It can be automatically or manually controlled. For manual control, set to Off. For automatic control, set to Once or Continuous.

Enumerator

BalanceWhiteAuto_Off	Sets operation mode to Off, which is manual control.
BalanceWhiteAuto_Once	Sets operation mode to once. Once runs for a number of iterations and then sets White Balance Auto to Off.
BalanceWhiteAuto_Continuous	Sets operation mode to continuous. Continuous automatically adjusts values if the colors are imbalanced.
NUM_BALANCEWHITEAUTO	

4.2.2.12 spinBalanceWhiteAutoProfileEnums

```
enum spinBalanceWhiteAutoProfileEnums
```

< Selects the profile used by BalanceWhiteAuto.

Enumerator

BalanceWhiteAutoProfile_Indoor	Indoor auto white balance Profile. Can be used to compensate for artificial lighting.
BalanceWhiteAutoProfile_Outdoor	Outdoor auto white balance profile. Designed for scenes with natural lighting.
NUM_BALANCEWHITEAUTOPROFILE	

4.2.2.13 spinBinningHorizontalModeEnums

```
enum spinBinningHorizontalModeEnums
```

<

Enumerator

BinningHorizontalMode_Sum	The response from the combined horizontal cells is added, resulting in increased sensitivity (a brighter image).
BinningHorizontalMode_Average	The response from the combined horizontal cells is averaged, resulting in increased signal/noise ratio. Not all sensors support average binning.
NUM_BINNINGHORIZONTALMODE	

4.2.2.14 spinBinningSelectorEnums

enum `spinBinningSelectorEnums`

< Selects which binning engine is controlled by the BinningHorizontal and BinningVertical features.

Enumerator

BinningSelector_All	The total amount of binning to be performed on the captured sensor data.
BinningSelector_Sensor	The portion of binning to be performed on the sensor directly.
BinningSelector_ISP	The portion of binning to be performed by the image signal processing engine (ISP) outside of the sensor. Note: the ISP can be disabled.
NUM_BINNINGSELECTOR	

4.2.2.15 spinBinningVerticalModeEnums

enum `spinBinningVerticalModeEnums`

<

Enumerator

BinningVerticalMode_Sum	The response from the combined vertical cells is added, resulting in increased sensitivity (a brighter image).
BinningVerticalMode_Average	The response from the combined vertical cells is averaged, resulting in increased signal/noise ratio. Not all sensors support average binning.
NUM_BINNINGVERTICALMODE	

4.2.2.16 spinBlackLevelAutoBalanceEnums

enum `spinBlackLevelAutoBalanceEnums`

< Controls the mode for automatic black level balancing between the sensor color channels or taps. The black level coefficients of each channel are adjusted so they are matched.

Enumerator

BlackLevelAutoBalance_Off	Black level tap balancing is user controlled using BlackLevel.
BlackLevelAutoBalance_Once	Black level tap balancing is automatically adjusted once by the device. Once it has converged, it automatically returns to the Off state.
BlackLevelAutoBalance_Continuous	Black level tap balancing is constantly adjusted by the device.
NUM_BLACKLEVELAUTOBALANCE	

4.2.2.17 spinBlackLevelAutoEnums

enum `spinBlackLevelAutoEnums`

< Controls the mode for automatic black level adjustment. The exact algorithm used to implement this adjustment is device-specific.

Enumerator

BlackLevelAuto_Off	Analog black level is user controlled using BlackLevel.
BlackLevelAuto_Once	Analog black level is automatically adjusted once by the device. Once it has converged, it automatically returns to the Off state.
BlackLevelAuto_Continuous	Analog black level is constantly adjusted by the device.
NUM_BLACKLEVELAUTO	

4.2.2.18 spinBlackLevelSelectorEnums

enum `spinBlackLevelSelectorEnums`

< Selects which black level to control. Only All can be set by the user. Analog and Digital are read-only.

Enumerator

BlackLevelSelector_All	
BlackLevelSelector_Analog	
BlackLevelSelector_Digital	
NUM_BLACKLEVELSELECTOR	

4.2.2.19 spinChunkBlackLevelSelectorEnums

enum `spinChunkBlackLevelSelectorEnums`

< Selects which black level to retrieve

Enumerator

ChunkBlackLevelSelector_All	
NUM_CHUNKBLACKLEVELSELECTOR	

4.2.2.20 spinChunkCounterSelectorEnums

enum `spinChunkCounterSelectorEnums`

< Selects which counter to retrieve data from.

Enumerator

ChunkCounterSelector_Counter0	Selects the counter 0.
ChunkCounterSelector_Counter1	Selects the counter 1.
ChunkCounterSelector_Counter2	Selects the counter 2.
NUM_CHUNKCOUNTERSELECTOR	

4.2.2.21 spinChunkEncoderSelectorEnums

enum `spinChunkEncoderSelectorEnums`

< Selects which Encoder to retrieve data from.

Enumerator

ChunkEncoderSelector_Encoder0	Selects the first Encoder.
ChunkEncoderSelector_Encoder1	Selects the first Encoder.
ChunkEncoderSelector_Encoder2	Selects the second Encoder.
NUM_CHUNKENCODERSELECTOR	

4.2.2.22 spinChunkEncoderStatusEnums

enum `spinChunkEncoderStatusEnums`

< Returns the motion status of the selected encoder.

Enumerator

ChunkEncoderStatus_EncoderUp	The encoder counter last incremented.
ChunkEncoderStatus_EncoderDown	The encoder counter last decremented.
ChunkEncoderStatus_EncoderIdle	The encoder is not active.
ChunkEncoderStatus_EncoderStatic	No motion within the EncoderTimeout time.
NUM_CHUNKENCODERSTATUS	

4.2.2.23 spinChunkExposureTimeSelectorEnums

enum `spinChunkExposureTimeSelectorEnums`

< Selects which exposure time is read by the ChunkExposureTime feature.

Enumerator

ChunkExposureTimeSelector_Common	Selects the common ExposureTime.
ChunkExposureTimeSelector_Red	Selects the red common ExposureTime.
ChunkExposureTimeSelector_Green	Selects the green ExposureTime.
ChunkExposureTimeSelector_Blue	Selects the blue ExposureTime.
ChunkExposureTimeSelector_Cyan	Selects the cyan common ExposureTime..
ChunkExposureTimeSelector_Magenta	Selects the magenta ExposureTime..
ChunkExposureTimeSelector_Yellow	Selects the yellow ExposureTime..
ChunkExposureTimeSelector_Infrared	Selects the infrared ExposureTime.
ChunkExposureTimeSelector_Ultraviolet	Selects the ultraviolet ExposureTime.
ChunkExposureTimeSelector_Stage1	Selects the first stage ExposureTime.
ChunkExposureTimeSelector_Stage2	Selects the second stage ExposureTime.
NUM_CHUNKEXPOSURETIMESELECTOR	

4.2.2.24 spinChunkGainSelectorEnums

```
enum spinChunkGainSelectorEnums
```

< Selects which gain to retrieve

Enumerator

ChunkGainSelector_All	
ChunkGainSelector_Red	
ChunkGainSelector_Green	
ChunkGainSelector_Blue	
NUM_CHUNKGAINSELECTOR	

4.2.2.25 spinChunkImageComponentEnums

```
enum spinChunkImageComponentEnums
```

< Returns the component of the payload image. This can be used to identify the image component of a generic part in a multipart transfer.

Enumerator

ChunkImageComponent_Intensity	The image data is the intensity component.
ChunkImageComponent_Color	The image data is color component.
ChunkImageComponent_Infrared	The image data is infrared component.
ChunkImageComponent_Ultraviolet	The image data is the ultraviolet component.

Enumerator

ChunkImageComponent_Range	The image data is the range (distance) component.
ChunkImageComponent_Disparity	The image data is the disparity component.
ChunkImageComponent_Confidence	The image data is the confidence map component.
ChunkImageComponent_Scatter	The image data is the scatter component.
NUM_CHUNKIMAGECOMPONENT	

4.2.2.26 spinChunkPixelFormatEnums

enum [spinChunkPixelFormatEnums](#)

< Format of the pixel provided by the camera

Enumerator

ChunkPixelFormat_Mono8	
ChunkPixelFormat_Mono12Packed	
ChunkPixelFormat_Mono16	
ChunkPixelFormat_RGB8Packed	
ChunkPixelFormat_YUV422Packed	
ChunkPixelFormat_BayerGR8	
ChunkPixelFormat_BayerRG8	
ChunkPixelFormat_BayerGB8	
ChunkPixelFormat_BayerBG8	
ChunkPixelFormat_YCbCr601_422_8_CbYCrY	
NUM_CHUNKPIXELFORMAT	

4.2.2.27 spinChunkRegionIDEnums

enum [spinChunkRegionIDEnums](#)

< Returns the identifier of Region that the image comes from.

Enumerator

ChunkRegionID_Region0	Image comes from the Region 0.
ChunkRegionID_Region1	Image comes from the Region 1.
ChunkRegionID_Region2	Image comes from the Region 2.
NUM_CHUNKREGIONID	

4.2.2.28 spinChunkScan3dCoordinateReferenceSelectorEnums

enum `spinChunkScan3dCoordinateReferenceSelectorEnums`

< Selector to read a coordinate system reference value defining the transform of a point from one system to the other.

Enumerator

ChunkScan3dCoordinateReferenceSelector_RotationX	Rotation around X axis.
ChunkScan3dCoordinateReferenceSelector_RotationY	Rotation around Y axis.
ChunkScan3dCoordinateReferenceSelector_RotationZ	Rotation around Z axis.
ChunkScan3dCoordinateReferenceSelector_TranslationX	X axis translation.
ChunkScan3dCoordinateReferenceSelector_TranslationY	Y axis translation.
ChunkScan3dCoordinateReferenceSelector_TranslationZ	Z axis translation.
NUM_CHUNKSCAN3DCOORDINATEREFERENCESELECTOR	

4.2.2.29 spinChunkScan3dCoordinateSelectorEnums

enum `spinChunkScan3dCoordinateSelectorEnums`

< Selects which Coordinate to retrieve data from.

Enumerator

ChunkScan3dCoordinateSelector_CoordinateA	The first (X or Theta) coordinate
ChunkScan3dCoordinateSelector_CoordinateB	The second (Y or Phi) coordinate
ChunkScan3dCoordinateSelector_CoordinateC	The third (Z or Rho) coordinate.
NUM_CHUNKSCAN3DCOORDINATESELECTOR	

4.2.2.30 spinChunkScan3dCoordinateSystemEnums

enum `spinChunkScan3dCoordinateSystemEnums`

< Returns the Coordinate System of the image included in the payload.

Enumerator

ChunkScan3dCoordinateSystem_Cartesian	Default value. 3-axis orthogonal, right-hand X-Y-Z.
ChunkScan3dCoordinateSystem_Spherical	A Theta-Phi-Rho coordinate system.
ChunkScan3dCoordinateSystem_Cylindrical	A Theta-Y-Rho coordinate system.
NUM_CHUNKSCAN3DCOORDINATESYSTEM	

4.2.2.31 spinChunkScan3dCoordinateSystemReferenceEnums

enum `spinChunkScan3dCoordinateSystemReferenceEnums`

< Returns the Coordinate System Position of the image included in the payload.

Enumerator

ChunkScan3dCoordinateSystemReference_Anchor	Default value. Original fixed reference. The coordinate system fixed relative the camera reference point marker is used.
ChunkScan3dCoordinateSystemReference_↔ Transformed	Transformed reference system. The transformed coordinate system is used according to the definition in the rotation and translation matrices.
NUM_CHUNKSCAN3DCOORDINATESYSTEMRE↔ FERENCE	

4.2.2.32 spinChunkScan3dCoordinateTransformSelectorEnums

enum `spinChunkScan3dCoordinateTransformSelectorEnums`

< Selector for transform values.

Enumerator

ChunkScan3dCoordinateTransformSelector_RotationX	Rotation around X axis.
ChunkScan3dCoordinateTransformSelector_RotationY	Rotation around Y axis.
ChunkScan3dCoordinateTransformSelector_RotationZ	Rotation around Z axis.
ChunkScan3dCoordinateTransformSelector_TranslationX	Translation along X axis.
ChunkScan3dCoordinateTransformSelector_TranslationY	Translation along Y axis.
ChunkScan3dCoordinateTransformSelector_TranslationZ	Translation along Z axis.
NUM_CHUNKSCAN3DCOORDINATETRANSFORMSELECTOR	

4.2.2.33 spinChunkScan3dDistanceUnitEnums

enum `spinChunkScan3dDistanceUnitEnums`

< Returns the Distance Unit of the payload image.

Enumerator

ChunkScan3dDistanceUnit_Millimeter	Default value. Distance values are in millimeter units.
ChunkScan3dDistanceUnit_Inch	Distance values are in inch units.
NUM_CHUNKSCAN3DDISTANCEUNIT	

4.2.2.34 spinChunkScan3dOutputModeEnums

enum [spinChunkScan3dOutputModeEnums](#)

< Returns the Calibrated Mode of the payload image.

Enumerator

ChunkScan3dOutputMode_UncalibratedC	Uncalibrated 2.5D Depth map. The distance data does not represent a physical unit and may be non-linear. The data is a 2.5D range map only.
ChunkScan3dOutputMode_CalibratedABC_Grid	3 Coordinates in grid organization. The full 3 coordinate data with the grid array organization from the sensor kept.
ChunkScan3dOutputMode_CalibratedABC_Point↔ Cloud	3 Coordinates without organization. The full 3 coordinate data without any organization of data points. Typically only valid points transmitted giving varying image size.
ChunkScan3dOutputMode_CalibratedAC	2 Coordinates with fixed B sampling. The data is sent as a A and C coordinates (X,Z or Theta,Rho). The B (Y) axis uses the scale and offset parameters for the B axis.
ChunkScan3dOutputMode_CalibratedAC_Linescan	2 Coordinates with varying sampling. The data is sent as a A and C coordinates (X,Z or Theta,Rho). The B (Y) axis comes from the encoder chunk value.
ChunkScan3dOutputMode_CalibratedC	Calibrated 2.5D Depth map. The distance data is expressed in the chosen distance unit. The data is a 2.5D range map. No information on X-Y axes available.
ChunkScan3dOutputMode_CalibratedC_Linescan	Depth Map with varying B sampling. The distance data is expressed in the chosen distance unit. The data is a 2.5D range map. The B (Y) axis comes from the encoder chunk value.
ChunkScan3dOutputMode_RectifiedC	Rectified 2.5D Depth map. The distance data has been rectified to a uniform sampling pattern in the X and Y direction. The data is a 2.5D range map only. If a complete 3D point cloud is rectified but transmitted as explicit coordinates it should be transmitted as one of the "CalibratedABC" formats.
ChunkScan3dOutputMode_RectifiedC_Linescan	Rectified 2.5D Depth map with varying B sampling. The data is sent as rectified 1D profiles using Coord3D_C pixels. The B (Y) axis comes from the encoder chunk value.
ChunkScan3dOutputMode_DisparityC	Disparity 2.5D Depth map. The distance is inversely proportional to the pixel (disparity) value.
ChunkScan3dOutputMode_DisparityC_Linescan	Disparity 2.5D Depth map with varying B sampling. The distance is inversely proportional to the pixel (disparity) value. The B (Y) axis comes from the encoder chunk value.
NUM_CHUNKSCAN3DOUTPUTMODE	

4.2.2.35 spinChunkSelectorEnums

enum `spinChunkSelectorEnums`

< Selects which chunk data to enable or disable.

Enumerator

ChunkSelector_Image	
ChunkSelector_CRC	
ChunkSelector_FrameID	
ChunkSelector_OffsetX	
ChunkSelector_OffsetY	
ChunkSelector_Width	
ChunkSelector_Height	
ChunkSelector_ExposureTime	
ChunkSelector_Gain	
ChunkSelector_BlackLevel	
ChunkSelector_PixelFormat	
ChunkSelector_Timestamp	
ChunkSelector_SequencerSetActive	
ChunkSelector_SerialData	
ChunkSelector_ExposureEndLineStatusAll	
NUM_CHUNKSELECTOR	

4.2.2.36 spinChunkSourceIDEnums

enum `spinChunkSourceIDEnums`

< Returns the identifier of Source that the image comes from.

Enumerator

ChunkSourceID_Source0	Image comes from the Source 0.
ChunkSourceID_Source1	Image comes from the Source 1.
ChunkSourceID_Source2	Image comes from the Source 2.
NUM_CHUNKSOURCEID	

4.2.2.37 spinChunkTimerSelectorEnums

enum `spinChunkTimerSelectorEnums`

< Selects which Timer to retrieve data from.

Enumerator

ChunkTimerSelector_Timer0	Selects the first Timer.
ChunkTimerSelector_Timer1	Selects the first Timer.
ChunkTimerSelector_Timer2	Selects the second Timer.
NUM_CHUNKTIMERSELECTOR	

4.2.2.38 spinChunkTransferStreamIDEnums

```
enum spinChunkTransferStreamIDEnums
```

< Returns identifier of the stream that generated this block.

Enumerator

ChunkTransferStreamID_Stream0	Data comes from Stream0.
ChunkTransferStreamID_Stream1	Data comes from Stream1.
ChunkTransferStreamID_Stream2	Data comes from Stream2.
ChunkTransferStreamID_Stream3	Data comes from Stream3.
NUM_CHUNKTRANSFERSTREAMID	

4.2.2.39 spinClConfigurationEnums

```
enum spinClConfigurationEnums
```

< This Camera Link specific feature describes the configuration used by the camera. It helps especially when a camera is capable of operation in a non-standard configuration, and when the features PixelSize, SensorDigitization, Taps, and DeviceTapGeometry do not provide enough information for interpretation of the image data provided by the camera.

Enumerator

ClConfiguration_Base	Standard base configuration described by the Camera Link standard.
ClConfiguration_Medium	Standard medium configuration described by the Camera Link standard.
ClConfiguration_Full	Standard full configuration described by the Camera Link standard.
ClConfiguration_DualBase	The camera streams the data from multiple taps (that do not fit in the standard base configuration) through two Camera Link base ports. It is responsibility of the application or frame grabber to reconstruct the full image. Only one of the ports (fixed) serves as the "master" for serial communication and triggering.
ClConfiguration_EightyBit	Standard 80-bit configuration with 10 taps of 8 bits or 8 taps of 10 bits, as described by the Camera Link standard.
NUM_CLCONFIGURATION	

4.2.2.40 spinCITimeSlotsCountEnums

enum `spinClTimeSlotsCountEnums`

< This Camera Link specific feature describes the time multiplexing of the camera link connection to transfer more than the configuration allows, in one single clock.

Enumerator

CITimeSlotsCount_One	One
CITimeSlotsCount_Two	Two
CITimeSlotsCount_Three	Three
NUM_CLTIMESLOTSCOUNT	

4.2.2.41 spinColorTransformationSelectorEnums

enum `spinColorTransformationSelectorEnums`

< Selects which Color Transformation module is controlled by the various Color Transformation features

Enumerator

ColorTransformationSelector_RGBtoRGB	
ColorTransformationSelector_RGBtoYUV	
NUM_COLORTRANSFORMATIONSELECTOR	

4.2.2.42 spinColorTransformationValueSelectorEnums

enum `spinColorTransformationValueSelectorEnums`

< Selects the Gain factor or Offset of the Transformation matrix to access in the selected Color Transformation module

Enumerator

ColorTransformationValueSelector_Gain00	
ColorTransformationValueSelector_Gain01	
ColorTransformationValueSelector_Gain02	
ColorTransformationValueSelector_Gain10	
ColorTransformationValueSelector_Gain11	
ColorTransformationValueSelector_Gain12	
ColorTransformationValueSelector_Gain20	
ColorTransformationValueSelector_Gain21	
ColorTransformationValueSelector_Gain22	
ColorTransformationValueSelector_Offset0	
ColorTransformationValueSelector_Offset1	
ColorTransformationValueSelector_Offset2	
NUM_COLORTRANSFORMATIONVALUESELECTOR	

4.2.2.43 spinCounterEventActivationEnums

```
enum spinCounterEventActivationEnums
```

< Selects the activation mode of the event to increment the Counter.

Enumerator

CounterEventActivation_LevelLow	
CounterEventActivation_LevelHigh	
CounterEventActivation_FallingEdge	
CounterEventActivation_RisingEdge	
CounterEventActivation_AnyEdge	
NUM_COUNTEREVENTACTIVATION	

4.2.2.44 spinCounterEventSourceEnums

```
enum spinCounterEventSourceEnums
```

< Selects the event that will increment the counter

Enumerator

CounterEventSource_Off	Off
CounterEventSource_MHzTick	MHzTick
CounterEventSource_Line0	Line0
CounterEventSource_Line1	Line1
CounterEventSource_Line2	Line2
CounterEventSource_Line3	Line3
CounterEventSource_UserOutput0	UserOutput0
CounterEventSource_UserOutput1	UserOutput1
CounterEventSource_UserOutput2	UserOutput2
CounterEventSource_UserOutput3	UserOutput3
CounterEventSource_Counter0Start	Counter0Start
CounterEventSource_Counter1Start	Counter1Start
CounterEventSource_Counter0End	Counter0End
CounterEventSource_Counter1End	Counter1End
CounterEventSource_LogicBlock0	LogicBlock0
CounterEventSource_LogicBlock1	LogicBlock1
CounterEventSource_ExposureStart	ExposureStart
CounterEventSource_ExposureEnd	ExposureEnd
CounterEventSource_FrameTriggerWait	FrameTriggerWait
NUM_COUNTEREVENTSOURCE	

4.2.2.45 spinCounterResetActivationEnums

enum `spinCounterResetActivationEnums`

< Selects the Activation mode of the Counter Reset Source signal.

Enumerator

CounterResetActivation_LevelLow	
CounterResetActivation_LevelHigh	
CounterResetActivation_FallingEdge	
CounterResetActivation_RisingEdge	
CounterResetActivation_AnyEdge	
NUM_COUNTERRESETACTIVATION	

4.2.2.46 spinCounterResetSourceEnums

enum `spinCounterResetSourceEnums`

< Selects the signal that will be the source to reset the Counter.

Enumerator

CounterResetSource_Off	Off
CounterResetSource_Line0	Line0
CounterResetSource_Line1	Line1
CounterResetSource_Line2	Line2
CounterResetSource_Line3	Line3
CounterResetSource_UserOutput0	UserOutput0
CounterResetSource_UserOutput1	UserOutput1
CounterResetSource_UserOutput2	UserOutput2
CounterResetSource_UserOutput3	UserOutput3
CounterResetSource_Counter0Start	Counter0Start
CounterResetSource_Counter1Start	Counter1Start
CounterResetSource_Counter0End	Counter0End
CounterResetSource_Counter1End	Counter1End
CounterResetSource_LogicBlock0	LogicBlock0
CounterResetSource_LogicBlock1	LogicBlock1
CounterResetSource_ExposureStart	ExposureStart
CounterResetSource_ExposureEnd	ExposureEnd
CounterResetSource_FrameTriggerWait	FrameTriggerWait
NUM_COUNTERRESETSOURCE	

4.2.2.47 spinCounterSelectorEnums

```
enum spinCounterSelectorEnums
```

< Selects which counter to configure

Enumerator

CounterSelector_Counter0	
CounterSelector_Counter1	
NUM_COUNTERSELECTOR	

4.2.2.48 spinCounterStatusEnums

```
enum spinCounterStatusEnums
```

< Returns the current status of the Counter.

Enumerator

CounterStatus_CounterIdle	The counter is idle.
CounterStatus_CounterTriggerWait	The counter is waiting for a start trigger.
CounterStatus_CounterActive	The counter is counting for the specified duration.
CounterStatus_CounterCompleted	The counter reached the CounterDuration count.
CounterStatus_CounterOverflow	The counter reached its maximum possible count.
NUM_COUNTERSTATUS	

4.2.2.49 spinCounterTriggerActivationEnums

```
enum spinCounterTriggerActivationEnums
```

< Selects the activation mode of the trigger to start the Counter.

Enumerator

CounterTriggerActivation_LevelLow	
CounterTriggerActivation_LevelHigh	
CounterTriggerActivation_FallingEdge	
CounterTriggerActivation_RisingEdge	
CounterTriggerActivation_AnyEdge	
NUM_COUNTERTRIGGERACTIVATION	

4.2.2.50 spinCounterTriggerSourceEnums

enum [spinCounterTriggerSourceEnums](#)

< Selects the source of the trigger to start the counter

Enumerator

CounterTriggerSource_Off	Off
CounterTriggerSource_Line0	Line0
CounterTriggerSource_Line1	Line1
CounterTriggerSource_Line2	Line2
CounterTriggerSource_Line3	Line3
CounterTriggerSource_UserOutput0	UserOutput0
CounterTriggerSource_UserOutput1	UserOutput1
CounterTriggerSource_UserOutput2	UserOutput2
CounterTriggerSource_UserOutput3	UserOutput3
CounterTriggerSource_Counter0Start	Counter0Start
CounterTriggerSource_Counter1Start	Counter1Start
CounterTriggerSource_Counter0End	Counter0End
CounterTriggerSource_Counter1End	Counter1End
CounterTriggerSource_LogicBlock0	LogicBlock0
CounterTriggerSource_LogicBlock1	LogicBlock1
CounterTriggerSource_ExposureStart	ExposureStart
CounterTriggerSource_ExposureEnd	ExposureEnd
CounterTriggerSource_FrameTriggerWait	FrameTriggerWait
NUM_COUNTERTRIGGERSOURCE	

4.2.2.51 spinCxpConnectionTestModeEnums

enum [spinCxpConnectionTestModeEnums](#)

< Enables the test mode for an individual physical connection of the Device.

Enumerator

CxpConnectionTestMode_Off	Off
CxpConnectionTestMode_Mode1	Mode 1
NUM_CXPCONNECTIONTESTMODE	

4.2.2.52 spinCxpLinkConfigurationEnums

enum [spinCxpLinkConfigurationEnums](#)

< This feature allows specifying the Link configuration for the communication between the Receiver and Transmitter Device. In most cases this feature does not need to be written because automatic discovery will set configuration correctly to the value returned by `CxpLinkConfigurationPreferred`. Note that the currently active configuration of the Link can be read using `CxpLinkConfigurationStatus`.

Enumerator

<code>CxpLinkConfiguration_Auto</code>	Sets Automatic discovery for the Link Configuration.
<code>CxpLinkConfiguration_CXP1_X1</code>	Force the Link to 1 Connection operating at CXP-1 speed (1.25 Gbps).
<code>CxpLinkConfiguration_CXP2_X1</code>	Force the Link to 1 Connection operating at CXP-2 speed (2.50 Gbps).
<code>CxpLinkConfiguration_CXP3_X1</code>	Force the Link to 1 Connection operating at CXP-3 speed (3.125 Gbps).
<code>CxpLinkConfiguration_CXP5_X1</code>	Force the Link to 1 Connection operating at CXP-5 speed (5.00 Gbps).
<code>CxpLinkConfiguration_CXP6_X1</code>	Force the Link to 1 Connection operating at CXP-6 speed (6.25 Gbps).
<code>CxpLinkConfiguration_CXP1_X2</code>	Force the Link to 2 Connections operating at CXP-1 speed (1.25 Gbps).
<code>CxpLinkConfiguration_CXP2_X2</code>	Force the Link to 2 Connections operating at CXP-2 speed (2.50 Gbps).
<code>CxpLinkConfiguration_CXP3_X2</code>	Force the Link to 2 Connections operating at CXP-3 speed (3.125 Gbps).
<code>CxpLinkConfiguration_CXP5_X2</code>	Force the Link to 2 Connections operating at CXP-5 speed (5.00 Gbps).
<code>CxpLinkConfiguration_CXP6_X2</code>	Force the Link to 3 Connections operating at CXP-6 speed (6.25 Gbps).
<code>CxpLinkConfiguration_CXP1_X3</code>	Force the Link to 3 Connections operating at CXP-1 speed (1.25 Gbps).
<code>CxpLinkConfiguration_CXP2_X3</code>	Force the Link to 3 Connections operating at CXP-2 speed (2.50 Gbps).
<code>CxpLinkConfiguration_CXP3_X3</code>	Force the Link to 3 Connections operating at CXP-3 speed (3.125 Gbps).
<code>CxpLinkConfiguration_CXP5_X3</code>	Force the Link to 3 Connections operating at CXP-5 speed (5.00 Gbps).
<code>CxpLinkConfiguration_CXP6_X3</code>	Force the Link to 3 Connections operating at CXP-6 speed (6.25 Gbps).
<code>CxpLinkConfiguration_CXP1_X4</code>	Force the Link to 4 Connections operating at CXP-1 speed (1.25 Gbps).
<code>CxpLinkConfiguration_CXP2_X4</code>	Force the Link to 4 Connections operating at CXP-2 speed (2.50 Gbps).
<code>CxpLinkConfiguration_CXP3_X4</code>	Force the Link to 4 Connections operating at CXP-3 speed (3.125 Gbps).
<code>CxpLinkConfiguration_CXP5_X4</code>	Force the Link to 4 Connections operating at CXP-5 speed (5.00 Gbps).
<code>CxpLinkConfiguration_CXP6_X4</code>	Force the Link to 4 Connections operating at CXP-6 speed (6.25 Gbps).
<code>CxpLinkConfiguration_CXP1_X5</code>	Force the Link to 5 Connections operating at CXP-1 speed (1.25 Gbps).
<code>CxpLinkConfiguration_CXP2_X5</code>	Force the Link to 5 Connections operating at CXP-2 speed (2.50 Gbps).
<code>CxpLinkConfiguration_CXP3_X5</code>	Force the Link to 5 Connections operating at CXP-3 speed (3.125 Gbps).
<code>CxpLinkConfiguration_CXP5_X5</code>	Force the Link to 5 Connections operating at CXP-5 speed (5.00 Gbps).
<code>CxpLinkConfiguration_CXP6_X5</code>	Force the Link to 5 Connections operating at CXP-6 speed (6.25 Gbps).
<code>CxpLinkConfiguration_CXP1_X6</code>	Force the Link to 6 Connections operating at CXP-1 speed (1.25 Gbps).
<code>CxpLinkConfiguration_CXP2_X6</code>	Force the Link to 6 Connections operating at CXP-2 speed (2.50 Gbps).
<code>CxpLinkConfiguration_CXP3_X6</code>	Force the Link to 6 Connections operating at CXP-3 speed (3.125 Gbps).
<code>CxpLinkConfiguration_CXP5_X6</code>	Force the Link to 6 Connections operating at CXP-5 speed (5.00 Gbps).
<code>CxpLinkConfiguration_CXP6_X6</code>	Force the Link to 6 Connections operating at CXP-6 speed (6.25 Gbps).
<code>NUM_CXPLINKCONFIGURATION</code>	

4.2.2.53 spinCxpLinkConfigurationPreferredEnums

```
enum spinCxpLinkConfigurationPreferredEnums
```

< Provides the Link configuration that allows the Transmitter Device to operate in its default mode.

Enumerator

CxpLinkConfigurationPreferred_CXP1_X1	1 Connection operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationPreferred_CXP2_X1	1 Connection operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationPreferred_CXP3_X1	1 Connection operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationPreferred_CXP5_X1	1 Connection operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationPreferred_CXP6_X1	1 Connection operating at CXP-6 speed (6.25 Gbps).
CxpLinkConfigurationPreferred_CXP1_X2	2 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationPreferred_CXP2_X2	2 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationPreferred_CXP3_X2	2 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationPreferred_CXP5_X2	2 Connections operating at CXP-4 speed (5.00 Gbps).
CxpLinkConfigurationPreferred_CXP6_X2	3 Connections operating at CXP-5 speed (6.25 Gbps).
CxpLinkConfigurationPreferred_CXP1_X3	3 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationPreferred_CXP2_X3	3 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationPreferred_CXP3_X3	3 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationPreferred_CXP5_X3	3 Connections operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationPreferred_CXP6_X3	3 Connections operating at CXP-6 speed (6.25 Gbps).
CxpLinkConfigurationPreferred_CXP1_X4	4 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationPreferred_CXP2_X4	4 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationPreferred_CXP3_X4	4 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationPreferred_CXP5_X4	4 Connections operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationPreferred_CXP6_X4	4 Connections operating at CXP-6 speed (6.25 Gbps).
CxpLinkConfigurationPreferred_CXP1_X5	5 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationPreferred_CXP2_X5	5 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationPreferred_CXP3_X5	5 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationPreferred_CXP5_X5	5 Connections operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationPreferred_CXP6_X5	5 Connections operating at CXP-6 speed (6.25 Gbps).
CxpLinkConfigurationPreferred_CXP1_X6	6 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationPreferred_CXP2_X6	6 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationPreferred_CXP3_X6	6 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationPreferred_CXP5_X6	6 Connections operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationPreferred_CXP6_X6	6 Connections operating at CXP-6 speed (6.25 Gbps).
NUM_CXPLINKCONFIGURATIONPREFERRED	

4.2.2.54 spinCxpLinkConfigurationStatusEnums

enum `spinCxpLinkConfigurationStatusEnums`

< This feature indicates the current and active Link configuration used by the Device.

Enumerator

CxpLinkConfigurationStatus_None	The Link configuration of the Device is unknown. Either the configuration operation has failed or there is nothing connected.
CxpLinkConfigurationStatus_Pending	The Device is in the process of configuring the Link. The Link cannot be used yet.

Enumerator

CxpLinkConfigurationStatus_CXP1_X1	1 Connection operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationStatus_CXP2_X1	1 Connection operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationStatus_CXP3_X1	1 Connection operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationStatus_CXP5_X1	1 Connection operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationStatus_CXP6_X1	1 Connection operating at CXP-6 speed (6.25 Gbps).
CxpLinkConfigurationStatus_CXP1_X2	2 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationStatus_CXP2_X2	2 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationStatus_CXP3_X2	2 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationStatus_CXP5_X2	2 Connections operating at CXP-4 speed (5.00 Gbps).
CxpLinkConfigurationStatus_CXP6_X2	3 Connections operating at CXP-5 speed (6.25 Gbps).
CxpLinkConfigurationStatus_CXP1_X3	3 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationStatus_CXP2_X3	3 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationStatus_CXP3_X3	3 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationStatus_CXP5_X3	3 Connections operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationStatus_CXP6_X3	3 Connections operating at CXP-6 speed (6.25 Gbps).
CxpLinkConfigurationStatus_CXP1_X4	4 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationStatus_CXP2_X4	4 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationStatus_CXP3_X4	4 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationStatus_CXP5_X4	4 Connections operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationStatus_CXP6_X4	4 Connections operating at CXP-6 speed (6.25 Gbps).
CxpLinkConfigurationStatus_CXP1_X5	5 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationStatus_CXP2_X5	5 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationStatus_CXP3_X5	5 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationStatus_CXP5_X5	5 Connections operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationStatus_CXP6_X5	5 Connections operating at CXP-6 speed (6.25 Gbps).
CxpLinkConfigurationStatus_CXP1_X6	6 Connections operating at CXP-1 speed (1.25 Gbps).
CxpLinkConfigurationStatus_CXP2_X6	6 Connections operating at CXP-2 speed (2.50 Gbps).
CxpLinkConfigurationStatus_CXP3_X6	6 Connections operating at CXP-3 speed (3.125 Gbps).
CxpLinkConfigurationStatus_CXP5_X6	6 Connections operating at CXP-5 speed (5.00 Gbps).
CxpLinkConfigurationStatus_CXP6_X6	6 Connections operating at CXP-6 speed (6.25 Gbps).
NUM_CXPLINKCONFIGURATIONSTATUS	

4.2.2.55 spinCxpPoCxpStatusEnums

```
enum spinCxpPoCxpStatusEnums
```

< Returns the Power over CoaXPress (PoCXP) status of the Device.

Enumerator

CxpPoCxpStatus_Auto	Normal automatic PoCXP operation.
CxpPoCxpStatus_Off	PoCXP is forced off.
CxpPoCxpStatus_Tripped	The Link has shut down because of an over-current trip.
NUM_CXPPOCXPSTATUS	

4.2.2.56 spinDecimationHorizontalModeEnums

enum `spinDecimationHorizontalModeEnums`

< The mode used to reduce the horizontal resolution when DecimationHorizontal is used. The current implementation only supports a single decimation mode: Discard. Average should be achieved via Binning.

Enumerator

DecimationHorizontalMode_Discard	The value of every Nth pixel is kept, others are discarded.
NUM_DECIMATIONHORIZONTALMODE	

4.2.2.57 spinDecimationSelectorEnums

enum `spinDecimationSelectorEnums`

< Selects which decimation layer is controlled by the DecimationHorizontal and DecimationVertical features.

Enumerator

DecimationSelector_All	The total amount of decimation to be performed on the captured image data.
DecimationSelector_Sensor	The portion of decimation to be performed on the sensor directly. Currently this is the only decimation layer available and hence is identical to the "All" layer. All decimation modification should therefore be done via the "All" layer only.
NUM_DECIMATIONSELECTOR	

4.2.2.58 spinDecimationVerticalModeEnums

enum `spinDecimationVerticalModeEnums`

< The mode used to reduce the vertical resolution when DecimationVertical is used. The current implementation only supports a single decimation mode: Discard. Average should be achieved via Binning.

Enumerator

DecimationVerticalMode_Discard	The value of every Nth pixel is kept, others are discarded.
NUM_DECIMATIONVERTICALMODE	

4.2.2.59 spinDefectCorrectionModeEnums

enum `spinDefectCorrectionModeEnums`

< Controls the method used for replacing defective pixels.

Enumerator

DefectCorrectionMode_Average	Pixels are replaced with the average of their neighbours. This is the normal mode of operation.
DefectCorrectionMode_Highlight	Pixels are replaced with the maximum pixel value (i.e., 255 for 8-bit images). Can be used for debugging the table.
DefectCorrectionMode_Zero	Pixels are replaced by the value zero. Can be used for testing the table.
NUM_DEFECTCORRECTIONMODE	

4.2.2.60 spinDeinterlacingEnums

enum `spinDeinterlacingEnums`

< Controls how the device performs de-interlacing.

Enumerator

Deinterlacing_Off	The device doesn't perform de-interlacing.
Deinterlacing_LineDuplication	The device performs de-interlacing by outputting each line of each field twice.
Deinterlacing_Weave	The device performs de-interlacing by interleaving the lines of all fields.
NUM_DEINTERLACING	

4.2.2.61 spinDeviceCharacterSetEnums

enum `spinDeviceCharacterSetEnums`

< Character set used by the strings of the device's bootstrap registers.

Enumerator

DeviceCharacterSet_UTF8	
DeviceCharacterSet_ASCII	
NUM_DEVICECHARACTERSET	

4.2.2.62 spinDeviceClockSelectorEnums

enum `spinDeviceClockSelectorEnums`

< Selects the clock frequency to access from the device.

Enumerator

DeviceClockSelector_Sensor	Clock frequency of the image sensor of the camera.
DeviceClockSelector_SensorDigitization	Clock frequency of the camera A/D conversion stage.
DeviceClockSelector_CameraLink	Frequency of the Camera Link clock.
NUM_DEVICECLOCKSELECTOR	

4.2.2.63 spinDeviceConnectionStatusEnums

enum `spinDeviceConnectionStatusEnums`

< Indicates the status of the specified Connection.

Enumerator

DeviceConnectionStatus_Active	Connection is in use.
DeviceConnectionStatus_Inactive	Connection is not in use.
NUM_DEVICECONNECTIONSTATUS	

4.2.2.64 spinDeviceIndicatorModeEnums

enum `spinDeviceIndicatorModeEnums`

< Controls the LED behaviour: Inactive (off), Active (current status), or Error Status (off unless an error occurs).

Enumerator

DeviceIndicatorMode_Inactive	
DeviceIndicatorMode_Active	
DeviceIndicatorMode_ErrorStatus	
NUM_DEVICEINDICATORMODE	

4.2.2.65 spinDeviceLinkHeartbeatModeEnums

enum `spinDeviceLinkHeartbeatModeEnums`

< Activate or deactivate the Link's heartbeat.

Enumerator

DeviceLinkHeartbeatMode_On	Enables the Link heartbeat.
DeviceLinkHeartbeatMode_Off	Disables the Link heartbeat.
NUM_DEVICELINKHEARTBEATMODE	

4.2.2.66 spinDeviceLinkThroughputLimitModeEnums

```
enum spinDeviceLinkThroughputLimitModeEnums
```

< Controls if the DeviceLinkThroughputLimit is active. When disabled, lower level TL specific features are expected to control the throughput. When enabled, DeviceLinkThroughputLimit controls the overall throughput.

Enumerator

DeviceLinkThroughputLimitMode_On	Enables the DeviceLinkThroughputLimit feature.
DeviceLinkThroughputLimitMode_Off	Disables the DeviceLinkThroughputLimit feature.
NUM_DEVICELINKTHROUGHPUTLIMITMODE	

4.2.2.67 spinDevicePowerSupplySelectorEnums

```
enum spinDevicePowerSupplySelectorEnums
```

< Selects the power supply source to control or read.

Enumerator

DevicePowerSupplySelector_External	
NUM_DEVICEPOWERSUPPLYSELECTOR	

4.2.2.68 spinDeviceRegistersEndiannessEnums

```
enum spinDeviceRegistersEndiannessEnums
```

< Endianness of the registers of the device.

Enumerator

DeviceRegistersEndianness_Little	
DeviceRegistersEndianness_Big	
NUM_DEVICEREGISTERSENDIANNESSE	

4.2.2.69 spinDeviceScanTypeEnums

```
enum spinDeviceScanTypeEnums
```

< Scan type of the sensor of the device.

Enumerator

DeviceScanType_Areascan	
NUM_DEVICESCANTYPE	

4.2.2.70 spinDeviceSerialPortBaudRateEnums

```
enum spinDeviceSerialPortBaudRateEnums
```

< This feature controls the baud rate used by the selected serial port.

Enumerator

DeviceSerialPortBaudRate_Baud9600	Serial port speed of 9600 baud.
DeviceSerialPortBaudRate_Baud19200	Serial port speed of 19200 baud.
DeviceSerialPortBaudRate_Baud38400	Serial port speed of 38400 baud.
DeviceSerialPortBaudRate_Baud57600	Serial port speed of 57600 baud.
DeviceSerialPortBaudRate_Baud115200	Serial port speed of 115200 baud.
DeviceSerialPortBaudRate_Baud230400	Serial port speed of 230400 baud.
DeviceSerialPortBaudRate_Baud460800	Serial port speed of 460800 baud.
DeviceSerialPortBaudRate_Baud921600	Serial port speed of 921600 baud.
NUM_DEVICESSERIALPORTBAUDRATE	

4.2.2.71 spinDeviceSerialPortSelectorEnums

```
enum spinDeviceSerialPortSelectorEnums
```

< Selects which serial port of the device to control.

Enumerator

DeviceSerialPortSelector_CameraLink	Serial port associated to the Camera link connection.
NUM_DEVICESSERIALPORTSELECTOR	

4.2.2.72 spinDeviceStreamChannelEndiannessEnums

enum `spinDeviceStreamChannelEndiannessEnums`

< Endianness of multi-byte pixel data for this stream.

Enumerator

<code>DeviceStreamChannelEndianness_Big</code>	Stream channel data is big Endian.
<code>DeviceStreamChannelEndianness_Little</code>	Stream channel data is little Endian.
<code>NUM_DEVICESTREAMCHANNELENDIANNESS</code>	

4.2.2.73 spinDeviceStreamChannelTypeEnums

enum `spinDeviceStreamChannelTypeEnums`

< Reports the type of the stream channel.

Enumerator

<code>DeviceStreamChannelType_Transmitter</code>	Data stream transmitter channel.
<code>DeviceStreamChannelType_Receiver</code>	Data stream receiver channel.
<code>NUM_DEVICESTREAMCHANNELTYPE</code>	

4.2.2.74 spinDeviceTapGeometryEnums

enum `spinDeviceTapGeometryEnums`

< This device tap geometry feature describes the geometrical properties characterizing the taps of a camera as presented at the output of the device.

Enumerator

<code>DeviceTapGeometry_Geometry_1X_1Y</code>	Geometry_1X_1Y
<code>DeviceTapGeometry_Geometry_1X2_1Y</code>	Geometry_1X2_1Y
<code>DeviceTapGeometry_Geometry_1X2_1Y2</code>	Geometry_1X2_1Y2
<code>DeviceTapGeometry_Geometry_2X_1Y</code>	Geometry_2X_1Y
<code>DeviceTapGeometry_Geometry_2X_1Y2Geometry_2XE_1Y</code>	Geometry_2X_1Y2Geometry_2XE_1Y
<code>DeviceTapGeometry_Geometry_2XE_1Y2</code>	Geometry_2XE_1Y2
<code>DeviceTapGeometry_Geometry_2XM_1Y</code>	Geometry_2XM_1Y
<code>DeviceTapGeometry_Geometry_2XM_1Y2</code>	Geometry_2XM_1Y2
<code>DeviceTapGeometry_Geometry_1X_1Y2</code>	Geometry_1X_1Y2
<code>DeviceTapGeometry_Geometry_1X_2YE</code>	Geometry_1X_2YE
<code>DeviceTapGeometry_Geometry_1X3_1Y</code>	Geometry_1X3_1Y

Enumerator

DeviceTapGeometry_Geometry_3X_1Y	Geometry_3X_1Y
DeviceTapGeometry_Geometry_1X	Geometry_1X
DeviceTapGeometry_Geometry_1X2	Geometry_1X2
DeviceTapGeometry_Geometry_2X	Geometry_2X
DeviceTapGeometry_Geometry_2XE	Geometry_2XE
DeviceTapGeometry_Geometry_2XM	Geometry_2XM
DeviceTapGeometry_Geometry_1X3	Geometry_1X3
DeviceTapGeometry_Geometry_3X	Geometry_3X
DeviceTapGeometry_Geometry_1X4_1Y	Geometry_1X4_1Y
DeviceTapGeometry_Geometry_4X_1Y	Geometry_4X_1Y
DeviceTapGeometry_Geometry_2X2_1Y	Geometry_2X2_1Y
DeviceTapGeometry_Geometry_2X2E_1YGeometry_2X2M_1Y	Geometry_2X2E_1YGeometry_2X2M_1Y
DeviceTapGeometry_Geometry_1X2_2YE	Geometry_1X2_2YE
DeviceTapGeometry_Geometry_2X_2YE	Geometry_2X_2YE
DeviceTapGeometry_Geometry_2XE_2YE	Geometry_2XE_2YE
DeviceTapGeometry_Geometry_2XM_2YE	Geometry_2XM_2YE
DeviceTapGeometry_Geometry_1X4	Geometry_1X4
DeviceTapGeometry_Geometry_4X	Geometry_4X
DeviceTapGeometry_Geometry_2X2	Geometry_2X2
DeviceTapGeometry_Geometry_2X2E	Geometry_2X2E
DeviceTapGeometry_Geometry_2X2M	Geometry_2X2M
DeviceTapGeometry_Geometry_1X8_1Y	Geometry_1X8_1Y
DeviceTapGeometry_Geometry_8X_1Y	Geometry_8X_1Y
DeviceTapGeometry_Geometry_4X2_1Y	Geometry_4X2_1Y
DeviceTapGeometry_Geometry_2X2E_2YE	Geometry_2X2E_2YE
DeviceTapGeometry_Geometry_1X8	Geometry_1X8
DeviceTapGeometry_Geometry_8X	Geometry_8X
DeviceTapGeometry_Geometry_4X2	Geometry_4X2
DeviceTapGeometry_Geometry_4X2E	Geometry_4X2E
DeviceTapGeometry_Geometry_4X2E_1Y	Geometry_4X2E_1Y
DeviceTapGeometry_Geometry_1X10_1Y	Geometry_1X10_1Y
DeviceTapGeometry_Geometry_10X_1Y	Geometry_10X_1Y
DeviceTapGeometry_Geometry_1X10	Geometry_1X10
DeviceTapGeometry_Geometry_10X	Geometry_10X
NUM_DEVICE_TAPGEOMETRY	

4.2.2.75 spinDeviceTemperatureSelectorEnums

```
enum spinDeviceTemperatureSelectorEnums
```

< Selects the location within the device, where the temperature will be measured.

Enumerator

DeviceTemperatureSelector_Sensor	
NUM_DEVICETEMPERATURESELECTOR	

4.2.2.76 spinDeviceTLTypeEnums

enum [spinDeviceTLTypeEnums](#)

< Transport Layer type of the device.

Enumerator

DeviceTLType_GigEVision	
DeviceTLType_CameraLink	
DeviceTLType_CameraLinkHS	
DeviceTLType_CoaXPress	
DeviceTLType_USB3Vision	
DeviceTLType_Custom	
NUM_DEVICETLTYPE	

4.2.2.77 spinDeviceTypeEnums

enum [spinDeviceTypeEnums](#)

< Returns the device type.

Enumerator

DeviceType_Transmitter	Data stream transmitter device.
DeviceType_Receiver	Data stream receiver device.
DeviceType_Transceiver	Data stream receiver and transmitter device.
DeviceType_Peripheral	Controllable device (with no data stream handling).
NUM_DEVICEYPE	

4.2.2.78 spinEncoderModeEnums

enum [spinEncoderModeEnums](#)

< Selects if the count of encoder uses FourPhase mode with jitter filtering or the HighResolution mode without jitter filtering.

Enumerator

EncoderMode_FourPhase	The counter increments or decrements 1 for every full quadrature cycle with jitter filtering.
EncoderMode_HighResolution	The counter increments or decrements every quadrature phase for high resolution counting, but without jitter filtering.
NUM_ENCODERMODE	

4.2.2.79 spinEncoderOutputModeEnums

```
enum spinEncoderOutputModeEnums
```

< Selects the conditions for the Encoder interface to generate a valid Encoder output signal.

Enumerator

EncoderOutputMode_Off	No output pulse are generated.
EncoderOutputMode_PositionUp	Output pulses are generated at all new positions in the positive direction. If the encoder reverses no output pulse are generated until it has again passed the position where the reversal started.
EncoderOutputMode_PositionDown	Output pulses are generated at all new positions in the negative direction. If the encoder reverses no output pulse are generated until it has again passed the position where the reversal started.
EncoderOutputMode_DirectionUp	Output pulses are generated at all position increments in the positive direction while ignoring negative direction motion.
EncoderOutputMode_DirectionDown	Output pulses are generated at all position increments in the negative direction while ignoring positive direction motion.
EncoderOutputMode_Motion	Output pulses are generated at all motion increments in both directions.
NUM_ENCODEROUTPUTMODE	

4.2.2.80 spinEncoderResetActivationEnums

```
enum spinEncoderResetActivationEnums
```

< Selects the Activation mode of the Encoder Reset Source signal.

Enumerator

EncoderResetActivation_RisingEdge	Resets the Encoder on the Rising Edge of the signal.
EncoderResetActivation_FallingEdge	Resets the Encoder on the Falling Edge of the signal.
EncoderResetActivation_AnyEdge	Resets the Encoder on the Falling or rising Edge of the selected signal.
EncoderResetActivation_LevelHigh	Resets the Encoder as long as the selected signal level is High.
EncoderResetActivation_LevelLow	Resets the Encoder as long as the selected signal level is Low.
NUM_ENCODERRESETACTIVATION	

4.2.2.81 spinEncoderResetSourceEnums

```
enum spinEncoderResetSourceEnums
```

< Selects the signals that will be the source to reset the Encoder.

Enumerator

EncoderResetSource_Off	Disable the Encoder Reset trigger.
EncoderResetSource_AcquisitionTrigger	Resets with the reception of the Acquisition Trigger.
EncoderResetSource_AcquisitionStart	Resets with the reception of the Acquisition Start.
EncoderResetSource_AcquisitionEnd	Resets with the reception of the Acquisition End.
EncoderResetSource_FrameTrigger	Resets with the reception of the Frame Start Trigger.
EncoderResetSource_FrameStart	Resets with the reception of the Frame Start.
EncoderResetSource_FrameEnd	Resets with the reception of the Frame End.
EncoderResetSource_ExposureStart	Resets with the reception of the Exposure Start.
EncoderResetSource_ExposureEnd	Resets with the reception of the Exposure End.
EncoderResetSource_Line0	Resets by the chosen I/O Line.
EncoderResetSource_Line1	Resets by the chosen I/O Line.
EncoderResetSource_Line2	Resets by the chosen I/O Line.
EncoderResetSource_Counter0Start	Resets with the reception of the Counter Start.
EncoderResetSource_Counter1Start	Resets with the reception of the Counter Start.
EncoderResetSource_Counter2Start	Resets with the reception of the Counter Start.
EncoderResetSource_Counter0End	Resets with the reception of the Counter End.
EncoderResetSource_Counter1End	Resets with the reception of the Counter End.
EncoderResetSource_Counter2End	Resets with the reception of the Counter End.
EncoderResetSource_Timer0Start	Resets with the reception of the Timer Start.
EncoderResetSource_Timer1Start	Resets with the reception of the Timer Start.
EncoderResetSource_Timer2Start	Resets with the reception of the Timer Start.
EncoderResetSource_Timer0End	Resets with the reception of the Timer End.
EncoderResetSource_Timer1End	Resets with the reception of the Timer End.
EncoderResetSource_Timer2End	Resets with the reception of the Timer End.
EncoderResetSource_UserOutput0	Resets by the chosen User Output bit.
EncoderResetSource_UserOutput1	Resets by the chosen User Output bit.
EncoderResetSource_UserOutput2	Resets by the chosen User Output bit.
EncoderResetSource_SoftwareSignal0	Resets on the reception of the Software Signal.
EncoderResetSource_SoftwareSignal1	Resets on the reception of the Software Signal.
EncoderResetSource_SoftwareSignal2	Resets on the reception of the Software Signal.
EncoderResetSource_Action0	Resets on assertions of the chosen action signal (Broadcasted signal on the transport layer).
EncoderResetSource_Action1	Resets on assertions of the chosen action signal (Broadcasted signal on the transport layer).
EncoderResetSource_Action2	Resets on assertions of the chosen action signal (Broadcasted signal on the transport layer).
EncoderResetSource_LinkTrigger0	Resets on the reception of the chosen Link Trigger (received from the transport layer).
EncoderResetSource_LinkTrigger1	Resets on the reception of the chosen Link Trigger (received from the transport layer).

Enumerator

EncoderResetSource_LinkTrigger2	Resets on the reception of the chosen Link Trigger (received from the transport layer).
NUM_ENCODERRESETSOURCE	

4.2.2.82 spinEncoderSelectorEnums

```
enum spinEncoderSelectorEnums
```

< Selects which Encoder to configure.

Enumerator

EncoderSelector_Encoder0	Selects Encoder 0.
EncoderSelector_Encoder1	Selects Encoder 1.
EncoderSelector_Encoder2	Selects Encoder 2.
NUM_ENCODERSELECTOR	

4.2.2.83 spinEncoderSourceAEnums

```
enum spinEncoderSourceAEnums
```

< Selects the signal which will be the source of the A input of the Encoder.

Enumerator

EncoderSourceA_Off	Counter is stopped.
EncoderSourceA_Line0	Encoder Forward input is taken from the chosen I/O Line.
EncoderSourceA_Line1	Encoder Forward input is taken from the chosen I/O Line.
EncoderSourceA_Line2	Encoder Forward input is taken from the chosen I/O Line.
NUM_ENCODERSOURCEA	

4.2.2.84 spinEncoderSourceBEnums

```
enum spinEncoderSourceBEnums
```

< Selects the signal which will be the source of the B input of the Encoder.

Enumerator

EncoderSourceB_Off	Counter is stopped.
EncoderSourceB_Line0	Encoder Reverse input is taken from the chosen I/O Line..
EncoderSourceB_Line1	Encoder Reverse input is taken from the chosen I/O Line..
EncoderSourceB_Line2	Encoder Reverse input is taken from the chosen I/O Line..
NUM_ENCODERSOURCEB	

4.2.2.85 spinEncoderStatusEnums

enum `spinEncoderStatusEnums`

< Returns the motion status of the encoder.

Enumerator

EncoderStatus_EncoderUp	The encoder counter last incremented.
EncoderStatus_EncoderDown	The encoder counter last decremented.
EncoderStatus_EncoderIdle	The encoder is not active.
EncoderStatus_EncoderStatic	No motion within the EncoderTimeout time.
NUM_ENCODERSTATUS	

4.2.2.86 spinEventNotificationEnums

enum `spinEventNotificationEnums`

< Enables/Disables the selected event.

Enumerator

EventNotification_On	
EventNotification_Off	
NUM_EVENTNOTIFICATION	

4.2.2.87 spinEventSelectorEnums

enum `spinEventSelectorEnums`

< Selects which Event to enable or disable.

Enumerator

EventSelector_Error	
EventSelector_ExposureEnd	
EventSelector_SerialPortReceive	
NUM_EVENTSELECTOR	

4.2.2.88 spinExposureActiveModeEnums

enum `spinExposureActiveModeEnums`

< Control sensor active exposure mode.

Enumerator

ExposureActiveMode_Line1	
ExposureActiveMode_AnyPixels	
ExposureActiveMode_AllPixels	
NUM_EXPOSUREACTIVEMODE	

4.2.2.89 spinExposureAutoEnums

enum `spinExposureAutoEnums`

< Sets the automatic exposure mode

Enumerator

ExposureAuto_Off	Exposure time is manually controlled using ExposureTime
ExposureAuto_Once	Exposure time is adapted once by the device. Once it has converged, it returns to the Off state.
ExposureAuto_Continuous	Exposure time is constantly adapted by the device to maximize the dynamic range.
NUM_EXPOSUREAUTO	

4.2.2.90 spinExposureModeEnums

enum `spinExposureModeEnums`

< Sets the operation mode of the Exposure.

Enumerator

ExposureMode_Timed	Timed exposure. The exposure time is set using the ExposureTime or ExposureAuto features and the exposure starts with the FrameStart or LineStart.
ExposureMode_TriggerWidth	Uses the width of the current Frame trigger signal pulse to control the exposure time.
NUM_EXPOSUREMODE	

4.2.2.91 spinExposureTimeModeEnums

```
enum spinExposureTimeModeEnums
```

< Sets the configuration mode of the ExposureTime feature.

Enumerator

ExposureTimeMode_Common	The exposure time is common to all the color components. The common ExposureTime value to use can be set selecting it with ExposureTimeSelector[Common].
ExposureTimeMode_Individual	The exposure time is individual for each color component. Each individual ExposureTime values to use can be set by selecting them with ExposureTimeSelector.
NUM_EXPOSURETIMEMODE	

4.2.2.92 spinExposureTimeSelectorEnums

```
enum spinExposureTimeSelectorEnums
```

< Selects which exposure time is controlled by the ExposureTime feature. This allows for independent control over the exposure components.

Enumerator

ExposureTimeSelector_Common	Selects the common ExposureTime.
ExposureTimeSelector_Red	Selects the red common ExposureTime.
ExposureTimeSelector_Green	Selects the green ExposureTime.
ExposureTimeSelector_Blue	Selects the blue ExposureTime.
ExposureTimeSelector_Cyan	Selects the cyan common ExposureTime.
ExposureTimeSelector_Magenta	Selects the magenta ExposureTime.
ExposureTimeSelector_Yellow	Selects the yellow ExposureTime.
ExposureTimeSelector_Infrared	Selects the infrared ExposureTime.
ExposureTimeSelector_Ultraviolet	Selects the ultraviolet ExposureTime.
ExposureTimeSelector_Stage1	Selects the first stage ExposureTime.
ExposureTimeSelector_Stage2	Selects the second stage ExposureTime.
NUM_EXPOSURETIMESELECTOR	

4.2.2.93 spinFileOpenModeEnums

```
enum spinFileOpenModeEnums
```

< The mode of the file when it is opened. The file can be opened for reading, writing or both. This must be set before opening the file.

Enumerator

FileOpenMode_Read	
FileOpenMode_Write	
FileOpenMode_ReadWrite	
NUM_FILEOPENMODE	

4.2.2.94 spinFileOperationSelectorEnums

```
enum spinFileOperationSelectorEnums
```

< Sets operation to execute on the selected file when the execute command is given.

Enumerator

FileOperationSelector_Open	
FileOperationSelector_Close	
FileOperationSelector_Read	
FileOperationSelector_Write	
FileOperationSelector_Delete	
NUM_FILEOPERATIONSELECTOR	

4.2.2.95 spinFileOperationStatusEnums

```
enum spinFileOperationStatusEnums
```

< Represents the file operation execution status.

Enumerator

FileOperationStatus_Success	File Operation was successful.
FileOperationStatus_Failure	File Operation failed.
FileOperationStatus_Overflow	An overflow occurred while executing the File Operation.
NUM_FILEOPERATIONSTATUS	

4.2.2.96 spinFileSelectorEnums

enum `spinFileSelectorEnums`

< Selects which file is being operated on. This must be set before performing any file operations.

Enumerator

FileSelector_UserSetDefault	
FileSelector_UserSet0	
FileSelector_UserSet1	
FileSelector_UserFile1	
FileSelector_SerialPort0	
NUM_FILESELECTOR	

4.2.2.97 spinGainAutoBalanceEnums

enum `spinGainAutoBalanceEnums`

< Sets the mode for automatic gain balancing between the sensor color channels or taps. The gain coefficients of each channel or tap are adjusted so they are matched.

Enumerator

GainAutoBalance_Off	Gain tap balancing is user controlled using Gain .
GainAutoBalance_Once	Gain tap balancing is automatically adjusted once by the device. Once it has converged, it automatically returns to the Off state.
GainAutoBalance_Continuous	Gain tap balancing is constantly adjusted by the device.
NUM_GAINAUTOBALANCE	

4.2.2.98 spinGainAutoEnums

enum `spinGainAutoEnums`

< Sets the automatic gain mode. Set to Off for manual control. Set to Once for a single automatic adjustment then return to Off. Set to Continuous for constant adjustment. In automatic modes, the camera adjusts the gain to maximize the dynamic range.

Enumerator

GainAuto_Off	Gain is manually controlled
GainAuto_Once	Gain is adapted once by the device. Once it has converged, it returns to the Off state.
GainAuto_Continuous	Gain is constantly adapted by the device to maximize the dynamic range.
NUM_GAINAUTO	

4.2.2.99 spinGainSelectorEnums

```
enum spinGainSelectorEnums
```

< Selects which gain to control. The All selection is a total amplification across all channels (or taps).

Enumerator

GainSelector_All	
NUM_GAINSELECTOR	

4.2.2.100 spinGevCCPEnums

```
enum spinGevCCPEnums
```

< Controls the device access privilege of an application.

Enumerator

GevCCP_OpenAccess	
GevCCP_ExclusiveAccess	
GevCCP_ControlAccess	
NUM_GEVCCP	

4.2.2.101 spinGevCurrentPhysicalLinkConfigurationEnums

```
enum spinGevCurrentPhysicalLinkConfigurationEnums
```

< Indicates the current physical link configuration of the device.

Enumerator

GevCurrentPhysicalLinkConfiguration_SingleLink	Single Link
GevCurrentPhysicalLinkConfiguration_MultiLink	Multi Link
GevCurrentPhysicalLinkConfiguration_StaticLAG	Static LAG
GevCurrentPhysicalLinkConfiguration_DynamicLAG	Dynamic LAG
NUM_GEVCURRENTPHYSICALLINKCONFIGURATION	

4.2.2.102 spinGevGVCPExtendedStatusCodesSelectorEnums

enum [spinGevGVCPExtendedStatusCodesSelectorEnums](#)

< Selects the GigE Vision version to control extended status codes for.

Enumerator

GevGVCPExtendedStatusCodesSelector_Version1_1	Version 1 1
GevGVCPExtendedStatusCodesSelector_Version2_0	Version 2 0
NUM_GEVGVCPEXTENDEDSTATUSCODESSELECTOR	

4.2.2.103 spinGevGVSPExtendedIDModeEnums

enum [spinGevGVSPExtendedIDModeEnums](#)

< Enables the extended IDs mode.

Enumerator

GevGVSPExtendedIDMode_Off	Off
GevGVSPExtendedIDMode_On	On
NUM_GEVGVSPEXTENDEDIDMODE	

4.2.2.104 spinGevIEEE1588ClockAccuracyEnums

enum [spinGevIEEE1588ClockAccuracyEnums](#)

< Indicates the expected accuracy of the device clock when it is the grandmaster, or in the event it becomes the grandmaster.

Enumerator

GevIEEE1588ClockAccuracy_Unknown	Unknown Accuracy
NUM_GEVIEEE1588CLOCKACCURACY	

4.2.2.105 spinGevIEEE1588ModeEnums

enum [spinGevIEEE1588ModeEnums](#)

< Provides the mode of the IEEE 1588 clock.

Enumerator

GevIEEE1588Mode_Auto	Automatic
GevIEEE1588Mode_SlaveOnly	Slave Only
NUM_GEVIEEE1588MODE	

4.2.2.106 spinGevIEEE1588StatusEnums

```
enum spinGevIEEE1588StatusEnums
```

< Provides the status of the IEEE 1588 clock.

Enumerator

GevIEEE1588Status_Initializing	Initializing
GevIEEE1588Status_Faulty	Faulty
GevIEEE1588Status_Disabled	Disabled
GevIEEE1588Status_Listening	Listening
GevIEEE1588Status_PreMaster	Pre Master
GevIEEE1588Status_Master	Master
GevIEEE1588Status_Passive	Passive
GevIEEE1588Status_Uncalibrated	Uncalibrated
GevIEEE1588Status_Slave	Slave
NUM_GEVIEEE1588STATUS	

4.2.2.107 spinGevIPConfigurationStatusEnums

```
enum spinGevIPConfigurationStatusEnums
```

< Reports the current IP configuration status.

Enumerator

GevIPConfigurationStatus_None	None
GevIPConfigurationStatus_PersistentIP	Persistent IP
GevIPConfigurationStatus_DHCP	DHCP
GevIPConfigurationStatus_LLA	LLA
GevIPConfigurationStatus_ForceIP	Force IP
NUM_GEVIPCONFIGURATIONSTATUS	

4.2.2.108 spinGevPhysicalLinkConfigurationEnums

enum `spinGevPhysicalLinkConfigurationEnums`

< Controls the principal physical link configuration to use on next restart/power-up of the device.

Enumerator

<code>GevPhysicalLinkConfiguration_SingleLink</code>	Single Link
<code>GevPhysicalLinkConfiguration_MultiLink</code>	Multi Link
<code>GevPhysicalLinkConfiguration_StaticLAG</code>	Static LAG
<code>GevPhysicalLinkConfiguration_DynamicLAG</code>	Dynamic LAG
<code>NUM_GEVPHYSICALLINKCONFIGURATION</code>	

4.2.2.109 spinGevSupportedOptionSelectorEnums

enum `spinGevSupportedOptionSelectorEnums`

< Selects the GEV option to interrogate for existing support.

Enumerator

<code>GevSupportedOptionSelector_UserDefinedName</code>	
<code>GevSupportedOptionSelector_SerialNumber</code>	
<code>GevSupportedOptionSelector_HeartbeatDisable</code>	
<code>GevSupportedOptionSelector_LinkSpeed</code>	
<code>GevSupportedOptionSelector_CCPApplicationSocket</code>	
<code>GevSupportedOptionSelector_ManifestTable</code>	
<code>GevSupportedOptionSelector_TestData</code>	
<code>GevSupportedOptionSelector_DiscoveryAckDelay</code>	
<code>GevSupportedOptionSelector_DiscoveryAckDelayWritable</code>	
<code>GevSupportedOptionSelector_ExtendedStatusCodes</code>	
<code>GevSupportedOptionSelector_Action</code>	
<code>GevSupportedOptionSelector_PendingAck</code>	
<code>GevSupportedOptionSelector_EventData</code>	
<code>GevSupportedOptionSelector_Event</code>	
<code>GevSupportedOptionSelector_PacketResend</code>	
<code>GevSupportedOptionSelector_WriteMem</code>	
<code>GevSupportedOptionSelector_CommandsConcatenation</code>	
<code>GevSupportedOptionSelector_IPConfigurationLLA</code>	
<code>GevSupportedOptionSelector_IPConfigurationDHCP</code>	
<code>GevSupportedOptionSelector_IPConfigurationPersistentIP</code>	
<code>GevSupportedOptionSelector_StreamChannelSourceSocket</code>	
<code>GevSupportedOptionSelector_MessageChannelSourceSocket</code>	
<code>NUM_GEVSUPPORTEDOPTIONSELECTOR</code>	

4.2.2.110 spinImageComponentSelectorEnums

enum `spinImageComponentSelectorEnums`

< Selects a component to activate data streaming from.

Enumerator

<code>ImageComponentSelector_Intensity</code>	The acquisition of intensity of the reflected light is controlled.
<code>ImageComponentSelector_Color</code>	The acquisition of color of the reflected light is controlled
<code>ImageComponentSelector_Infrared</code>	The acquisition of non-visible infrared light is controlled.
<code>ImageComponentSelector_Ultraviolet</code>	The acquisition of non-visible ultraviolet light is controlled.
<code>ImageComponentSelector_Range</code>	The acquisition of range (distance) data is controlled. The data produced may be only range (2.5D) or a point cloud 3D coordinates depending on the Scan3dControl.
<code>ImageComponentSelector_Disparity</code>	The acquisition of stereo camera disparity data is controlled. Disparity is a more specific range format approximately inversely proportional to distance. Disparity is typically given in pixel units.
<code>ImageComponentSelector_Confidence</code>	The acquisition of confidence map of the acquired image is controlled. Confidence data may be binary (0 - invalid) or an integer where 0 is invalid and increasing value is increased confidence in the data in the corresponding pixel. If floating point representation is used the confidence image is normalized to the range [0,1], for integer representation the maximum possible integer represents maximum confidence.
<code>ImageComponentSelector_Scatter</code>	The acquisition of data measuring how much light is scattered around the reflected light. In processing this is used as an additional intensity image, often together with the standard intensity.
<code>NUM_IMAGECOMPONENTSELECTOR</code>	

4.2.2.111 spinImageCompressionJPEGFormatOptionEnums

enum `spinImageCompressionJPEGFormatOptionEnums`

< When JPEG is selected as the compression format, a device might optionally offer better control over JPEG-specific options through this feature.

Enumerator

<code>ImageCompressionJPEGFormatOption_Lossless</code>	Selects lossless JPEG compression based on a predictive coding model.
<code>ImageCompressionJPEGFormatOption_Baseline↔ Standard</code>	Indicates this is a baseline sequential (single-scan) DCT-based JPEG.
<code>ImageCompressionJPEGFormatOption_Baseline↔ Optimized</code>	Provides optimized color and slightly better compression than baseline standard by using custom Huffman tables optimized after statistical analysis of the image content.

Enumerator

ImageCompressionJPEGFormatOption_Progressive	Indicates this is a progressive (multi-scan) DCT-based JPEG.
NUM_IMAGECOMPRESSIONJPEGFORMATOPTION	

4.2.2.112 spinImageCompressionModeEnums

enum `spinImageCompressionModeEnums`

<

Enumerator

ImageCompressionMode_Off	
ImageCompressionMode_Lossless	
NUM_IMAGECOMPRESSIONMODE	

4.2.2.113 spinImageCompressionRateOptionEnums

enum `spinImageCompressionRateOptionEnums`

< Two rate controlling options are offered: fixed bit rate or fixed quality. The exact implementation to achieve one or the other is vendor-specific.

Enumerator

ImageCompressionRateOption_FixBitrate	Output stream follows a constant bit rate. Allows easy bandwidth management on the link.
ImageCompressionRateOption_FixQuality	Output stream has a constant image quality. Can be used when image processing algorithms are sensitive to image degradation caused by excessive data compression.
NUM_IMAGECOMPRESSIONRATEOPTION	

4.2.2.114 spinLineFormatEnums

enum `spinLineFormatEnums`

< Displays the current electrical format of the selected physical input or output Line.

Enumerator

LineFormat_NoConnect	
LineFormat_TriState	
LineFormat_TTL	
LineFormat_LVDS	
LineFormat_RS422	
LineFormat_OptoCoupled	
LineFormat_OpenDrain	
NUM_LINEFORMAT	

4.2.2.115 spinLineInputFilterSelectorEnums

```
enum spinLineInputFilterSelectorEnums
```

< Selects the kind of input filter to configure: Deglitch or Debounce.

Enumerator

LineInputFilterSelector_Deglitch	
LineInputFilterSelector_Debounce	
NUM_LINEINPUTFILTERSELECTOR	

4.2.2.116 spinLineModeEnums

```
enum spinLineModeEnums
```

< Controls if the physical Line is used to Input or Output a signal.

Enumerator

LineMode_Input	
LineMode_Output	
NUM_LINEMODE	

4.2.2.117 spinLineSelectorEnums

```
enum spinLineSelectorEnums
```

< Selects the physical line (or pin) of the external device connector to configure

Enumerator

LineSelector_Line0	
LineSelector_Line1	
LineSelector_Line2	
LineSelector_Line3	
NUM_LINESELECTOR	

4.2.2.118 spinLineSourceEnums

enum `spinLineSourceEnums`

< Selects which internal acquisition or I/O source signal to output on the selected line. LineMode must be Output.

Enumerator

LineSource_Off	
LineSource_Line0	
LineSource_Line1	
LineSource_Line2	
LineSource_Line3	
LineSource_UserOutput0	
LineSource_UserOutput1	
LineSource_UserOutput2	
LineSource_UserOutput3	
LineSource_Counter0Active	
LineSource_Counter1Active	
LineSource_LogicBlock0	
LineSource_LogicBlock1	
LineSource_ExposureActive	
LineSource_FrameTriggerWait	
LineSource_SerialPort0	
LineSource_PPSSignal	
LineSource_AllPixel	
LineSource_AnyPixel	
NUM_LINESOURCE	

4.2.2.119 spinLogicBlockLUTInputActivationEnums

enum `spinLogicBlockLUTInputActivationEnums`

< Selects the activation mode of the Logic Input Source signal.

Enumerator

LogicBlockLUTInputActivation_LevelLow	
LogicBlockLUTInputActivation_LevelHigh	
LogicBlockLUTInputActivation_FallingEdge	
LogicBlockLUTInputActivation_RisingEdge	
LogicBlockLUTInputActivation_AnyEdge	
NUM_LOGICBLOCKLUTINPUTACTIVATION	

4.2.2.120 spinLogicBlockLUTInputSelectorEnums

```
enum spinLogicBlockLUTInputSelectorEnums
```

< Controls which LogicBlockLUT Input Source & Activation to access.

Enumerator

LogicBlockLUTInputSelector_Input0	
LogicBlockLUTInputSelector_Input1	
LogicBlockLUTInputSelector_Input2	
LogicBlockLUTInputSelector_Input3	
NUM_LOGICBLOCKLUTINPUTSELECTOR	

4.2.2.121 spinLogicBlockLUTInputSourceEnums

```
enum spinLogicBlockLUTInputSourceEnums
```

< Selects the source for the input into the Logic LUT.

Enumerator

LogicBlockLUTInputSource_Zero	Zero
LogicBlockLUTInputSource_Line0	Line0
LogicBlockLUTInputSource_Line1	Line1
LogicBlockLUTInputSource_Line2	Line2
LogicBlockLUTInputSource_Line3	Line3
LogicBlockLUTInputSource_UserOutput0	UserOutput0
LogicBlockLUTInputSource_UserOutput1	UserOutput1
LogicBlockLUTInputSource_UserOutput2	UserOutput2
LogicBlockLUTInputSource_UserOutput3	UserOutput3
LogicBlockLUTInputSource_Counter0Start	Counter0Start
LogicBlockLUTInputSource_Counter1Start	Counter1Start
LogicBlockLUTInputSource_Counter0End	Counter0End

Enumerator

LogicBlockLUTInputSource_Counter1End	Counter1End
LogicBlockLUTInputSource_LogicBlock0	LogicBlock0
LogicBlockLUTInputSource_LogicBlock1	LogicBlock1
LogicBlockLUTInputSource_ExposureStart	ExposureStart
LogicBlockLUTInputSource_ExposureEnd	ExposureEnd
LogicBlockLUTInputSource_FrameTriggerWait	FrameTriggerWait
LogicBlockLUTInputSource_AcquisitionActive	AcquisitionActive
NUM_LOGICBLOCKLUTINPUTSOURCE	

4.2.2.122 spinLogicBlockLUTSelectorEnums

```
enum spinLogicBlockLUTSelectorEnums
```

< Selects which LogicBlock LUT to configure

Enumerator

LogicBlockLUTSelector_Value	
LogicBlockLUTSelector_Enable	
NUM_LOGICBLOCKLUTSELECTOR	

4.2.2.123 spinLogicBlockSelectorEnums

```
enum spinLogicBlockSelectorEnums
```

< Selects which LogicBlock to configure

Enumerator

LogicBlockSelector_LogicBlock0	
LogicBlockSelector_LogicBlock1	
NUM_LOGICBLOCKSELECTOR	

4.2.2.124 spinLUTSelectorEnums

```
enum spinLUTSelectorEnums
```

The enum definitions for camera nodes.

< Selects which LUT to control.

Enumerator

LUTSelector_LUT1	This LUT is for re-mapping pixels of all formats (mono, Bayer, red, green and blue).
NUM_LUTSELECTOR	

4.2.2.125 spinPixelColorFilterEnums

```
enum spinPixelColorFilterEnums
```

< Type of color filter that is applied to the image. Only applies to Bayer pixel formats. All others have no color filter.

Enumerator

PixelColorFilter_None	No color filter.
PixelColorFilter_BayerRG	Bayer Red Green filter.
PixelColorFilter_BayerGB	Bayer Green Blue filter.
PixelColorFilter_BayerGR	Bayer Green Red filter.
PixelColorFilter_BayerBG	Bayer Blue Green filter.
NUM_PIXELCOLORFILTER	

4.2.2.126 spinPixelFormatEnums

```
enum spinPixelFormatEnums
```

< Format of the pixel provided by the camera.

Enumerator

PixelFormat_Mono8	
PixelFormat_Mono16	
PixelFormat_RGB8Packed	
PixelFormat_BayerGR8	
PixelFormat_BayerRG8	
PixelFormat_BayerGB8	
PixelFormat_BayerBG8	
PixelFormat_BayerGR16	
PixelFormat_BayerRG16	
PixelFormat_BayerGB16	
PixelFormat_BayerBG16	
PixelFormat_Mono12Packed	
PixelFormat_BayerGR12Packed	
PixelFormat_BayerRG12Packed	
PixelFormat_BayerGB12Packed	
PixelFormat_BayerBG12Packed	

Enumerator

PixelFormat_YUV411Packed	
PixelFormat_YUV422Packed	
PixelFormat_YUV444Packed	
PixelFormat_Mono12p	
PixelFormat_BayerGR12p	
PixelFormat_BayerRG12p	
PixelFormat_BayerGB12p	
PixelFormat_BayerBG12p	
PixelFormat_YCbCr8	
PixelFormat_YCbCr422_8	
PixelFormat_YCbCr411_8	
PixelFormat_BGR8	
PixelFormat_BGRa8	
PixelFormat_Mono10Packed	
PixelFormat_BayerGR10Packed	
PixelFormat_BayerRG10Packed	
PixelFormat_BayerGB10Packed	
PixelFormat_BayerBG10Packed	
PixelFormat_Mono10p	
PixelFormat_BayerGR10p	
PixelFormat_BayerRG10p	
PixelFormat_BayerGB10p	
PixelFormat_BayerBG10p	
PixelFormat_Mono1p	Monochrome 1-bit packed
PixelFormat_Mono2p	Monochrome 2-bit packed
PixelFormat_Mono4p	Monochrome 4-bit packed
PixelFormat_Mono8s	Monochrome 8-bit signed
PixelFormat_Mono10	Monochrome 10-bit unpacked
PixelFormat_Mono12	Monochrome 12-bit unpacked
PixelFormat_Mono14	Monochrome 14-bit unpacked
PixelFormat_Mono16s	Monochrome 16-bit signed
PixelFormat_Mono32f	Monochrome 32-bit float
PixelFormat_BayerBG10	Bayer Blue-Green 10-bit unpacked
PixelFormat_BayerBG12	Bayer Blue-Green 12-bit unpacked
PixelFormat_BayerGB10	Bayer Green-Blue 10-bit unpacked
PixelFormat_BayerGB12	Bayer Green-Blue 12-bit unpacked
PixelFormat_BayerGR10	Bayer Green-Red 10-bit unpacked
PixelFormat_BayerGR12	Bayer Green-Red 12-bit unpacked
PixelFormat_BayerRG10	Bayer Red-Green 10-bit unpacked
PixelFormat_BayerRG12	Bayer Red-Green 12-bit unpacked
PixelFormat_RGBa8	Red-Green-Blue-alpha 8-bit
PixelFormat_RGBa10	Red-Green-Blue-alpha 10-bit unpacked
PixelFormat_RGBa10p	Red-Green-Blue-alpha 10-bit packed
PixelFormat_RGBa12	Red-Green-Blue-alpha 12-bit unpacked
PixelFormat_RGBa12p	Red-Green-Blue-alpha 12-bit packed
PixelFormat_RGBa14	Red-Green-Blue-alpha 14-bit unpacked
PixelFormat_RGBa16	Red-Green-Blue-alpha 16-bit

Enumerator

PixelFormat_RGB8	Red-Green-Blue 8-bit
PixelFormat_RGB8_Planar	Red-Green-Blue 8-bit planar
PixelFormat_RGB10	Red-Green-Blue 10-bit unpacked
PixelFormat_RGB10_Planar	Red-Green-Blue 10-bit unpacked planar
PixelFormat_RGB10p	Red-Green-Blue 10-bit packed
PixelFormat_RGB10p32	Red-Green-Blue 10-bit packed into 32-bit
PixelFormat_RGB12	Red-Green-Blue 12-bit unpacked
PixelFormat_RGB12_Planar	Red-Green-Blue 12-bit unpacked planar
PixelFormat_RGB12p	Red-Green-Blue 12-bit packed
PixelFormat_RGB14	Red-Green-Blue 14-bit unpacked
PixelFormat_RGB16	Red-Green-Blue 16-bit
PixelFormat_RGB16s	Red-Green-Blue 16-bit signed
PixelFormat_RGB32f	Red-Green-Blue 32-bit float
PixelFormat_RGB16_Planar	Red-Green-Blue 16-bit planar
PixelFormat_RGB565p	Red-Green-Blue 5/6/5-bit packed
PixelFormat_BGRa10	Blue-Green-Red-alpha 10-bit unpacked
PixelFormat_BGRa10p	Blue-Green-Red-alpha 10-bit packed
PixelFormat_BGRa12	Blue-Green-Red-alpha 12-bit unpacked
PixelFormat_BGRa12p	Blue-Green-Red-alpha 12-bit packed
PixelFormat_BGRa14	Blue-Green-Red-alpha 14-bit unpacked
PixelFormat_BGRa16	Blue-Green-Red-alpha 16-bit
PixelFormat_RGBa32f	Red-Green-Blue-alpha 32-bit float
PixelFormat_BGR10	Blue-Green-Red 10-bit unpacked
PixelFormat_BGR10p	Blue-Green-Red 10-bit packed
PixelFormat_BGR12	Blue-Green-Red 12-bit unpacked
PixelFormat_BGR12p	Blue-Green-Red 12-bit packed
PixelFormat_BGR14	Blue-Green-Red 14-bit unpacked
PixelFormat_BGR16	Blue-Green-Red 16-bit
PixelFormat_BGR565p	Blue-Green-Red 5/6/5-bit packed
PixelFormat_R8	Red 8-bit
PixelFormat_R10	Red 10-bit
PixelFormat_R12	Red 12-bit
PixelFormat_R16	Red 16-bit
PixelFormat_G8	Green 8-bit
PixelFormat_G10	Green 10-bit
PixelFormat_G12	Green 12-bit
PixelFormat_G16	Green 16-bit
PixelFormat_B8	Blue 8-bit
PixelFormat_B10	Blue 10-bit
PixelFormat_B12	Blue 12-bit
PixelFormat_B16	Blue 16-bit
PixelFormat_Coord3D_ABC8	3D coordinate A-B-C 8-bit
PixelFormat_Coord3D_ABC8_Planar	3D coordinate A-B-C 8-bit planar
PixelFormat_Coord3D_ABC10p	3D coordinate A-B-C 10-bit packed
PixelFormat_Coord3D_ABC10p_Planar	3D coordinate A-B-C 10-bit packed planar
PixelFormat_Coord3D_ABC12p	3D coordinate A-B-C 12-bit packed
PixelFormat_Coord3D_ABC12p_Planar	3D coordinate A-B-C 12-bit packed planar
PixelFormat_Coord3D_ABC16	3D coordinate A-B-C 16-bit

Enumerator

PixelFormat_Coord3D_ABC16_Planar	3D coordinate A-B-C 16-bit planar
PixelFormat_Coord3D_ABC32f	3D coordinate A-B-C 32-bit floating point
PixelFormat_Coord3D_ABC32f_Planar	3D coordinate A-B-C 32-bit floating point planar
PixelFormat_Coord3D_AC8	3D coordinate A-C 8-bit
PixelFormat_Coord3D_AC8_Planar	3D coordinate A-C 8-bit planar
PixelFormat_Coord3D_AC10p	3D coordinate A-C 10-bit packed
PixelFormat_Coord3D_AC10p_Planar	3D coordinate A-C 10-bit packed planar
PixelFormat_Coord3D_AC12p	3D coordinate A-C 12-bit packed
PixelFormat_Coord3D_AC12p_Planar	3D coordinate A-C 12-bit packed planar
PixelFormat_Coord3D_AC16	3D coordinate A-C 16-bit
PixelFormat_Coord3D_AC16_Planar	3D coordinate A-C 16-bit planar
PixelFormat_Coord3D_AC32f	3D coordinate A-C 32-bit floating point
PixelFormat_Coord3D_AC32f_Planar	3D coordinate A-C 32-bit floating point planar
PixelFormat_Coord3D_A8	3D coordinate A 8-bit
PixelFormat_Coord3D_A10p	3D coordinate A 10-bit packed
PixelFormat_Coord3D_A12p	3D coordinate A 12-bit packed
PixelFormat_Coord3D_A16	3D coordinate A 16-bit
PixelFormat_Coord3D_A32f	3D coordinate A 32-bit floating point
PixelFormat_Coord3D_B8	3D coordinate B 8-bit
PixelFormat_Coord3D_B10p	3D coordinate B 10-bit packed
PixelFormat_Coord3D_B12p	3D coordinate B 12-bit packed
PixelFormat_Coord3D_B16	3D coordinate B 16-bit
PixelFormat_Coord3D_B32f	3D coordinate B 32-bit floating point
PixelFormat_Coord3D_C8	3D coordinate C 8-bit
PixelFormat_Coord3D_C10p	3D coordinate C 10-bit packed
PixelFormat_Coord3D_C12p	3D coordinate C 12-bit packed
PixelFormat_Coord3D_C16	3D coordinate C 16-bit
PixelFormat_Coord3D_C32f	3D coordinate C 32-bit floating point
PixelFormat_Confidence1	Confidence 1-bit unpacked
PixelFormat_Confidence1p	Confidence 1-bit packed
PixelFormat_Confidence8	Confidence 8-bit
PixelFormat_Confidence16	Confidence 16-bit
PixelFormat_Confidence32f	Confidence 32-bit floating point
PixelFormat_BiColorBGRG8	Bi-color Blue/Green - Red/Green 8-bit
PixelFormat_BiColorBGRG10	Bi-color Blue/Green - Red/Green 10-bit unpacked
PixelFormat_BiColorBGRG10p	Bi-color Blue/Green - Red/Green 10-bit packed
PixelFormat_BiColorBGRG12	Bi-color Blue/Green - Red/Green 12-bit unpacked
PixelFormat_BiColorBGRG12p	Bi-color Blue/Green - Red/Green 12-bit packed
PixelFormat_BiColorRGBG8	Bi-color Red/Green - Blue/Green 8-bit
PixelFormat_BiColorRGBG10	Bi-color Red/Green - Blue/Green 10-bit unpacked
PixelFormat_BiColorRGBG10p	Bi-color Red/Green - Blue/Green 10-bit packed
PixelFormat_BiColorRGBG12	Bi-color Red/Green - Blue/Green 12-bit unpacked
PixelFormat_BiColorRGBG12p	Bi-color Red/Green - Blue/Green 12-bit packed
PixelFormat_SCF1WBWG8	Sparse Color Filter #1 White-Blue-White-Green 8-bit
PixelFormat_SCF1WBWG10	Sparse Color Filter #1 White-Blue-White-Green 10-bit unpacked
PixelFormat_SCF1WBWG10p	Sparse Color Filter #1 White-Blue-White-Green 10-bit packed
PixelFormat_SCF1WBWG12	Sparse Color Filter #1 White-Blue-White-Green 12-bit unpacked

Enumerator

PixelFormat_SCF1WBWG12p	Sparse Color Filter #1 White-Blue-White-Green 12-bit packed
PixelFormat_SCF1WBWG14	Sparse Color Filter #1 White-Blue-White-Green 14-bit unpacked
PixelFormat_SCF1WBWG16	Sparse Color Filter #1 White-Blue-White-Green 16-bit unpacked
PixelFormat_SCF1WGWB8	Sparse Color Filter #1 White-Green-White-Blue 8-bit
PixelFormat_SCF1WGWB10	Sparse Color Filter #1 White-Green-White-Blue 10-bit unpacked
PixelFormat_SCF1WGWB10p	Sparse Color Filter #1 White-Green-White-Blue 10-bit packed
PixelFormat_SCF1WGWB12	Sparse Color Filter #1 White-Green-White-Blue 12-bit unpacked
PixelFormat_SCF1WGWB12p	Sparse Color Filter #1 White-Green-White-Blue 12-bit packed
PixelFormat_SCF1WGWB14	Sparse Color Filter #1 White-Green-White-Blue 14-bit unpacked
PixelFormat_SCF1WGWB16	Sparse Color Filter #1 White-Green-White-Blue 16-bit
PixelFormat_SCF1WGWR8	Sparse Color Filter #1 White-Green-White-Red 8-bit
PixelFormat_SCF1WGWR10	Sparse Color Filter #1 White-Green-White-Red 10-bit unpacked
PixelFormat_SCF1WGWR10p	Sparse Color Filter #1 White-Green-White-Red 10-bit packed
PixelFormat_SCF1WGWR12	Sparse Color Filter #1 White-Green-White-Red 12-bit unpacked
PixelFormat_SCF1WGWR12p	Sparse Color Filter #1 White-Green-White-Red 12-bit packed
PixelFormat_SCF1WGWR14	Sparse Color Filter #1 White-Green-White-Red 14-bit unpacked
PixelFormat_SCF1WGWR16	Sparse Color Filter #1 White-Green-White-Red 16-bit
PixelFormat_SCF1WRWG8	Sparse Color Filter #1 White-Red-White-Green 8-bit
PixelFormat_SCF1WRWG10	Sparse Color Filter #1 White-Red-White-Green 10-bit unpacked
PixelFormat_SCF1WRWG10p	Sparse Color Filter #1 White-Red-White-Green 10-bit packed
PixelFormat_SCF1WRWG12	Sparse Color Filter #1 White-Red-White-Green 12-bit unpacked
PixelFormat_SCF1WRWG12p	Sparse Color Filter #1 White-Red-White-Green 12-bit packed
PixelFormat_SCF1WRWG14	Sparse Color Filter #1 White-Red-White-Green 14-bit unpacked
PixelFormat_SCF1WRWG16	Sparse Color Filter #1 White-Red-White-Green 16-bit
PixelFormat_YCbCr8_CbYCr	YCbCr 4:4:4 8-bit
PixelFormat_YCbCr10_CbYCr	YCbCr 4:4:4 10-bit unpacked
PixelFormat_YCbCr10p_CbYCr	YCbCr 4:4:4 10-bit packed
PixelFormat_YCbCr12_CbYCr	YCbCr 4:4:4 12-bit unpacked
PixelFormat_YCbCr12p_CbYCr	YCbCr 4:4:4 12-bit packed
PixelFormat_YCbCr411_8_CbYYCrYY	YCbCr 4:1:1 8-bit
PixelFormat_YCbCr422_8_CbYCrY	YCbCr 4:2:2 8-bit
PixelFormat_YCbCr422_10	YCbCr 4:2:2 10-bit unpacked
PixelFormat_YCbCr422_10_CbYCrY	YCbCr 4:2:2 10-bit unpacked
PixelFormat_YCbCr422_10p	YCbCr 4:2:2 10-bit packed
PixelFormat_YCbCr422_10p_CbYCrY	YCbCr 4:2:2 10-bit packed
PixelFormat_YCbCr422_12	YCbCr 4:2:2 12-bit unpacked
PixelFormat_YCbCr422_12_CbYCrY	YCbCr 4:2:2 12-bit unpacked
PixelFormat_YCbCr422_12p	YCbCr 4:2:2 12-bit packed
PixelFormat_YCbCr422_12p_CbYCrY	YCbCr 4:2:2 12-bit packed
PixelFormat_YCbCr601_8_CbYCr	YCbCr 4:4:4 8-bit BT.601
PixelFormat_YCbCr601_10_CbYCr	YCbCr 4:4:4 10-bit unpacked BT.601
PixelFormat_YCbCr601_10p_CbYCr	YCbCr 4:4:4 10-bit packed BT.601
PixelFormat_YCbCr601_12_CbYCr	YCbCr 4:4:4 12-bit unpacked BT.601
PixelFormat_YCbCr601_12p_CbYCr	YCbCr 4:4:4 12-bit packed BT.601
PixelFormat_YCbCr601_411_8_CbYYCrYY	YCbCr 4:1:1 8-bit BT.601
PixelFormat_YCbCr601_422_8	YCbCr 4:2:2 8-bit BT.601
PixelFormat_YCbCr601_422_8_CbYCrY	YCbCr 4:2:2 8-bit BT.601

Enumerator

PixelFormat_YCbCr601_422_10	YCbCr 4:2:2 10-bit unpacked BT.601
PixelFormat_YCbCr601_422_10_CbYCrY	YCbCr 4:2:2 10-bit unpacked BT.601
PixelFormat_YCbCr601_422_10p	YCbCr 4:2:2 10-bit packed BT.601
PixelFormat_YCbCr601_422_10p_CbYCrY	YCbCr 4:2:2 10-bit packed BT.601
PixelFormat_YCbCr601_422_12	YCbCr 4:2:2 12-bit unpacked BT.601
PixelFormat_YCbCr601_422_12_CbYCrY	YCbCr 4:2:2 12-bit unpacked BT.601
PixelFormat_YCbCr601_422_12p	YCbCr 4:2:2 12-bit packed BT.601
PixelFormat_YCbCr601_422_12p_CbYCrY	YCbCr 4:2:2 12-bit packed BT.601
PixelFormat_YCbCr709_8_CbYCr	YCbCr 4:4:4 8-bit BT.709
PixelFormat_YCbCr709_10_CbYCr	YCbCr 4:4:4 10-bit unpacked BT.709
PixelFormat_YCbCr709_10p_CbYCr	YCbCr 4:4:4 10-bit packed BT.709
PixelFormat_YCbCr709_12_CbYCr	YCbCr 4:4:4 12-bit unpacked BT.709
PixelFormat_YCbCr709_12p_CbYCr	YCbCr 4:4:4 12-bit packed BT.709
PixelFormat_YCbCr709_411_8_CbYYCrYY	YCbCr 4:1:1 8-bit BT.709
PixelFormat_YCbCr709_422_8	YCbCr 4:2:2 8-bit BT.709
PixelFormat_YCbCr709_422_8_CbYCrY	YCbCr 4:2:2 8-bit BT.709
PixelFormat_YCbCr709_422_10	YCbCr 4:2:2 10-bit unpacked BT.709
PixelFormat_YCbCr709_422_10_CbYCrY	YCbCr 4:2:2 10-bit unpacked BT.709
PixelFormat_YCbCr709_422_10p	YCbCr 4:2:2 10-bit packed BT.709
PixelFormat_YCbCr709_422_10p_CbYCrY	YCbCr 4:2:2 10-bit packed BT.709
PixelFormat_YCbCr709_422_12	YCbCr 4:2:2 12-bit unpacked BT.709
PixelFormat_YCbCr709_422_12_CbYCrY	YCbCr 4:2:2 12-bit unpacked BT.709
PixelFormat_YCbCr709_422_12p	YCbCr 4:2:2 12-bit packed BT.709
PixelFormat_YCbCr709_422_12p_CbYCrY	YCbCr 4:2:2 12-bit packed BT.709
PixelFormat_YUV8_UYV	YUV 4:4:4 8-bit
PixelFormat_YUV411_8_UYYVYY	YUV 4:1:1 8-bit
PixelFormat_YUV422_8	YUV 4:2:2 8-bit
PixelFormat_YUV422_8_UYVY	YUV 4:2:2 8-bit
PixelFormat_Polarized8	Monochrome Polarized 8-bit
PixelFormat_Polarized10p	Monochrome Polarized 10-bit packed
PixelFormat_Polarized12p	Monochrome Polarized 12-bit packed
PixelFormat_Polarized16	Monochrome Polarized 16-bit
PixelFormat_BayerRGPolarized8	Polarized Bayer Red Green filter 8-bit
PixelFormat_BayerRGPolarized10p	Polarized Bayer Red Green filter 10-bit packed
PixelFormat_BayerRGPolarized12p	Polarized Bayer Red Green filter 12-bit packed
PixelFormat_BayerRGPolarized16	Polarized Bayer Red Green filter 16-bit
PixelFormat_LLCMono8	Lossless Compression Monochrome 8-bit
PixelFormat_LLCBayerRG8	Lossless Compression Bayer Red Green filter 8-bit
PixelFormat_JPEGMono8	JPEG Monochrome 8-bit
PixelFormat_JPEGColor8	JPEG Color 8-bit
PixelFormat_Raw16	Raw 16 bit.
PixelFormat_Raw8	Raw bit.
PixelFormat_R12_Jpeg	Red 12-bit JPEG.
PixelFormat_GR12_Jpeg	Green Red 12-bit JPEG.
PixelFormat_GB12_Jpeg	Green Blue 12-bit JPEG.
PixelFormat_B12_Jpeg	Blue 12-bit packed JPEG.
UNKNOWN_PIXELFORMAT	

Enumerator

NUM_PIXELFORMAT	
-----------------	--

4.2.2.127 spinPixelFormatInfoSelectorEnums

```
enum spinPixelFormatInfoSelectorEnums
```

< Select the pixel format for which the information will be returned.

Enumerator

PixelFormatInfoSelector_Mono1p	Monochrome 1-bit packed
PixelFormatInfoSelector_Mono2p	Monochrome 2-bit packed
PixelFormatInfoSelector_Mono4p	Monochrome 4-bit packed
PixelFormatInfoSelector_Mono8	Monochrome 8-bit
PixelFormatInfoSelector_Mono8s	Monochrome 8-bit signed
PixelFormatInfoSelector_Mono10	Monochrome 10-bit unpacked
PixelFormatInfoSelector_Mono10p	Monochrome 10-bit packed
PixelFormatInfoSelector_Mono12	Monochrome 12-bit unpacked
PixelFormatInfoSelector_Mono12p	Monochrome 12-bit packed
PixelFormatInfoSelector_Mono14	Monochrome 14-bit unpacked
PixelFormatInfoSelector_Mono16	Monochrome 16-bit
PixelFormatInfoSelector_Mono16s	Monochrome 16-bit signed
PixelFormatInfoSelector_Mono32f	Monochrome 32-bit float
PixelFormatInfoSelector_BayerBG8	Bayer Blue-Green 8-bit
PixelFormatInfoSelector_BayerBG10	Bayer Blue-Green 10-bit unpacked
PixelFormatInfoSelector_BayerBG10p	Bayer Blue-Green 10-bit packed
PixelFormatInfoSelector_BayerBG12	Bayer Blue-Green 12-bit unpacked
PixelFormatInfoSelector_BayerBG12p	Bayer Blue-Green 12-bit packed
PixelFormatInfoSelector_BayerBG16	Bayer Blue-Green 16-bit
PixelFormatInfoSelector_BayerGB8	Bayer Green-Blue 8-bit
PixelFormatInfoSelector_BayerGB10	Bayer Green-Blue 10-bit unpacked
PixelFormatInfoSelector_BayerGB10p	Bayer Green-Blue 10-bit packed
PixelFormatInfoSelector_BayerGB12	Bayer Green-Blue 12-bit unpacked
PixelFormatInfoSelector_BayerGB12p	Bayer Green-Blue 12-bit packed
PixelFormatInfoSelector_BayerGB16	Bayer Green-Blue 16-bit
PixelFormatInfoSelector_BayerGR8	Bayer Green-Red 8-bit
PixelFormatInfoSelector_BayerGR10	Bayer Green-Red 10-bit unpacked
PixelFormatInfoSelector_BayerGR10p	Bayer Green-Red 10-bit packed
PixelFormatInfoSelector_BayerGR12	Bayer Green-Red 12-bit unpacked
PixelFormatInfoSelector_BayerGR12p	Bayer Green-Red 12-bit packed
PixelFormatInfoSelector_BayerGR16	Bayer Green-Red 16-bit
PixelFormatInfoSelector_BayerRG8	Bayer Red-Green 8-bit
PixelFormatInfoSelector_BayerRG10	Bayer Red-Green 10-bit unpacked
PixelFormatInfoSelector_BayerRG10p	Bayer Red-Green 10-bit packed

Enumerator

PixelFormatInfoSelector_BayerRG12	Bayer Red-Green 12-bit unpacked
PixelFormatInfoSelector_BayerRG12p	Bayer Red-Green 12-bit packed
PixelFormatInfoSelector_BayerRG16	Bayer Red-Green 16-bit
PixelFormatInfoSelector_RGBa8	Red-Green-Blue-alpha 8-bit
PixelFormatInfoSelector_RGBa10	Red-Green-Blue-alpha 10-bit unpacked
PixelFormatInfoSelector_RGBa10p	Red-Green-Blue-alpha 10-bit packed
PixelFormatInfoSelector_RGBa12	Red-Green-Blue-alpha 12-bit unpacked
PixelFormatInfoSelector_RGBa12p	Red-Green-Blue-alpha 12-bit packed
PixelFormatInfoSelector_RGBa14	Red-Green-Blue-alpha 14-bit unpacked
PixelFormatInfoSelector_RGBa16	Red-Green-Blue-alpha 16-bit
PixelFormatInfoSelector_RGB8	Red-Green-Blue 8-bit
PixelFormatInfoSelector_RGB8_Planar	Red-Green-Blue 8-bit planar
PixelFormatInfoSelector_RGB10	Red-Green-Blue 10-bit unpacked
PixelFormatInfoSelector_RGB10_Planar	Red-Green-Blue 10-bit unpacked planar
PixelFormatInfoSelector_RGB10p	Red-Green-Blue 10-bit packed
PixelFormatInfoSelector_RGB10p32	Red-Green-Blue 10-bit packed into 32-bit
PixelFormatInfoSelector_RGB12	Red-Green-Blue 12-bit unpacked
PixelFormatInfoSelector_RGB12_Planar	Red-Green-Blue 12-bit unpacked planar
PixelFormatInfoSelector_RGB12p	Red-Green-Blue 12-bit packed
PixelFormatInfoSelector_RGB14	Red-Green-Blue 14-bit unpacked
PixelFormatInfoSelector_RGB16	Red-Green-Blue 16-bit
PixelFormatInfoSelector_RGB16s	Red-Green-Blue 16-bit signed
PixelFormatInfoSelector_RGB32f	Red-Green-Blue 32-bit float
PixelFormatInfoSelector_RGB16_Planar	Red-Green-Blue 16-bit planar
PixelFormatInfoSelector_RGB565p	Red-Green-Blue 5/6/5-bit packed
PixelFormatInfoSelector_BGRa8	Blue-Green-Red-alpha 8-bit
PixelFormatInfoSelector_BGRa10	Blue-Green-Red-alpha 10-bit unpacked
PixelFormatInfoSelector_BGRa10p	Blue-Green-Red-alpha 10-bit packed
PixelFormatInfoSelector_BGRa12	Blue-Green-Red-alpha 12-bit unpacked
PixelFormatInfoSelector_BGRa12p	Blue-Green-Red-alpha 12-bit packed
PixelFormatInfoSelector_BGRa14	Blue-Green-Red-alpha 14-bit unpacked
PixelFormatInfoSelector_BGRa16	Blue-Green-Red-alpha 16-bit
PixelFormatInfoSelector_RGBa32f	Red-Green-Blue-alpha 32-bit float
PixelFormatInfoSelector_BGR8	Blue-Green-Red 8-bit
PixelFormatInfoSelector_BGR10	Blue-Green-Red 10-bit unpacked
PixelFormatInfoSelector_BGR10p	Blue-Green-Red 10-bit packed
PixelFormatInfoSelector_BGR12	Blue-Green-Red 12-bit unpacked
PixelFormatInfoSelector_BGR12p	Blue-Green-Red 12-bit packed
PixelFormatInfoSelector_BGR14	Blue-Green-Red 14-bit unpacked
PixelFormatInfoSelector_BGR16	Blue-Green-Red 16-bit
PixelFormatInfoSelector_BGR565p	Blue-Green-Red 5/6/5-bit packed
PixelFormatInfoSelector_R8	Red 8-bit
PixelFormatInfoSelector_R10	Red 10-bit
PixelFormatInfoSelector_R12	Red 12-bit
PixelFormatInfoSelector_R16	Red 16-bit
PixelFormatInfoSelector_G8	Green 8-bit
PixelFormatInfoSelector_G10	Green 10-bit

Enumerator

PixelFormatInfoSelector_G12	Green 12-bit
PixelFormatInfoSelector_G16	Green 16-bit
PixelFormatInfoSelector_B8	Blue 8-bit
PixelFormatInfoSelector_B10	Blue 10-bit
PixelFormatInfoSelector_B12	Blue 12-bit
PixelFormatInfoSelector_B16	Blue 16-bit
PixelFormatInfoSelector_Coord3D_ABC8	3D coordinate A-B-C 8-bit
PixelFormatInfoSelector_Coord3D_ABC8_Planar	3D coordinate A-B-C 8-bit planar
PixelFormatInfoSelector_Coord3D_ABC10p	3D coordinate A-B-C 10-bit packed
PixelFormatInfoSelector_Coord3D_ABC10p_Planar	3D coordinate A-B-C 10-bit packed planar
PixelFormatInfoSelector_Coord3D_ABC12p	3D coordinate A-B-C 12-bit packed
PixelFormatInfoSelector_Coord3D_ABC12p_Planar	3D coordinate A-B-C 12-bit packed planar
PixelFormatInfoSelector_Coord3D_ABC16	3D coordinate A-B-C 16-bit
PixelFormatInfoSelector_Coord3D_ABC16_Planar	3D coordinate A-B-C 16-bit planar
PixelFormatInfoSelector_Coord3D_ABC32f	3D coordinate A-B-C 32-bit floating point
PixelFormatInfoSelector_Coord3D_ABC32f_Planar	3D coordinate A-B-C 32-bit floating point planar
PixelFormatInfoSelector_Coord3D_AC8	3D coordinate A-C 8-bit
PixelFormatInfoSelector_Coord3D_AC8_Planar	3D coordinate A-C 8-bit planar
PixelFormatInfoSelector_Coord3D_AC10p	3D coordinate A-C 10-bit packed
PixelFormatInfoSelector_Coord3D_AC10p_Planar	3D coordinate A-C 10-bit packed planar
PixelFormatInfoSelector_Coord3D_AC12p	3D coordinate A-C 12-bit packed
PixelFormatInfoSelector_Coord3D_AC12p_Planar	3D coordinate A-C 12-bit packed planar
PixelFormatInfoSelector_Coord3D_AC16	3D coordinate A-C 16-bit
PixelFormatInfoSelector_Coord3D_AC16_Planar	3D coordinate A-C 16-bit planar
PixelFormatInfoSelector_Coord3D_AC32f	3D coordinate A-C 32-bit floating point
PixelFormatInfoSelector_Coord3D_AC32f_Planar	3D coordinate A-C 32-bit floating point planar
PixelFormatInfoSelector_Coord3D_A8	3D coordinate A 8-bit
PixelFormatInfoSelector_Coord3D_A10p	3D coordinate A 10-bit packed
PixelFormatInfoSelector_Coord3D_A12p	3D coordinate A 12-bit packed
PixelFormatInfoSelector_Coord3D_A16	3D coordinate A 16-bit
PixelFormatInfoSelector_Coord3D_A32f	3D coordinate A 32-bit floating point
PixelFormatInfoSelector_Coord3D_B8	3D coordinate B 8-bit
PixelFormatInfoSelector_Coord3D_B10p	3D coordinate B 10-bit packed
PixelFormatInfoSelector_Coord3D_B12p	3D coordinate B 12-bit packed
PixelFormatInfoSelector_Coord3D_B16	3D coordinate B 16-bit
PixelFormatInfoSelector_Coord3D_B32f	3D coordinate B 32-bit floating point
PixelFormatInfoSelector_Coord3D_C8	3D coordinate C 8-bit
PixelFormatInfoSelector_Coord3D_C10p	3D coordinate C 10-bit packed
PixelFormatInfoSelector_Coord3D_C12p	3D coordinate C 12-bit packed
PixelFormatInfoSelector_Coord3D_C16	3D coordinate C 16-bit
PixelFormatInfoSelector_Coord3D_C32f	3D coordinate C 32-bit floating point
PixelFormatInfoSelector_Confidence1	Confidence 1-bit unpacked
PixelFormatInfoSelector_Confidence1p	Confidence 1-bit packed
PixelFormatInfoSelector_Confidence8	Confidence 8-bit
PixelFormatInfoSelector_Confidence16	Confidence 16-bit
PixelFormatInfoSelector_Confidence32f	Confidence 32-bit floating point
PixelFormatInfoSelector_BiColorBGRG8	Bi-color Blue/Green - Red/Green 8-bit

Enumerator

PixelFormatInfoSelector_BiColorBGRG10	Bi-color Blue/Green - Red/Green 10-bit unpacked
PixelFormatInfoSelector_BiColorBGRG10p	Bi-color Blue/Green - Red/Green 10-bit packed
PixelFormatInfoSelector_BiColorBGRG12	Bi-color Blue/Green - Red/Green 12-bit unpacked
PixelFormatInfoSelector_BiColorBGRG12p	Bi-color Blue/Green - Red/Green 12-bit packed
PixelFormatInfoSelector_BiColorRGBG8	Bi-color Red/Green - Blue/Green 8-bit
PixelFormatInfoSelector_BiColorRGBG10	Bi-color Red/Green - Blue/Green 10-bit unpacked
PixelFormatInfoSelector_BiColorRGBG10p	Bi-color Red/Green - Blue/Green 10-bit packed
PixelFormatInfoSelector_BiColorRGBG12	Bi-color Red/Green - Blue/Green 12-bit unpacked
PixelFormatInfoSelector_BiColorRGBG12p	Bi-color Red/Green - Blue/Green 12-bit packed
PixelFormatInfoSelector_SCF1WBWG8	Sparse Color Filter #1 White-Blue-White-Green 8-bit
PixelFormatInfoSelector_SCF1WBWG10	Sparse Color Filter #1 White-Blue-White-Green 10-bit unpacked
PixelFormatInfoSelector_SCF1WBWG10p	Sparse Color Filter #1 White-Blue-White-Green 10-bit packed
PixelFormatInfoSelector_SCF1WBWG12	Sparse Color Filter #1 White-Blue-White-Green 12-bit unpacked
PixelFormatInfoSelector_SCF1WBWG12p	Sparse Color Filter #1 White-Blue-White-Green 12-bit packed
PixelFormatInfoSelector_SCF1WBWG14	Sparse Color Filter #1 White-Blue-White-Green 14-bit unpacked
PixelFormatInfoSelector_SCF1WBWG16	Sparse Color Filter #1 White-Blue-White-Green 16-bit unpacked
PixelFormatInfoSelector_SCF1WGWB8	Sparse Color Filter #1 White-Green-White-Blue 8-bit
PixelFormatInfoSelector_SCF1WGWB10	Sparse Color Filter #1 White-Green-White-Blue 10-bit unpacked
PixelFormatInfoSelector_SCF1WGWB10p	Sparse Color Filter #1 White-Green-White-Blue 10-bit packed
PixelFormatInfoSelector_SCF1WGWB12	Sparse Color Filter #1 White-Green-White-Blue 12-bit unpacked
PixelFormatInfoSelector_SCF1WGWB12p	Sparse Color Filter #1 White-Green-White-Blue 12-bit packed
PixelFormatInfoSelector_SCF1WGWB14	Sparse Color Filter #1 White-Green-White-Blue 14-bit unpacked
PixelFormatInfoSelector_SCF1WGWB16	Sparse Color Filter #1 White-Green-White-Blue 16-bit
PixelFormatInfoSelector_SCF1WGWR8	Sparse Color Filter #1 White-Green-White-Red 8-bit
PixelFormatInfoSelector_SCF1WGWR10	Sparse Color Filter #1 White-Green-White-Red 10-bit unpacked
PixelFormatInfoSelector_SCF1WGWR10p	Sparse Color Filter #1 White-Green-White-Red 10-bit packed
PixelFormatInfoSelector_SCF1WGWR12	Sparse Color Filter #1 White-Green-White-Red 12-bit unpacked
PixelFormatInfoSelector_SCF1WGWR12p	Sparse Color Filter #1 White-Green-White-Red 12-bit packed
PixelFormatInfoSelector_SCF1WGWR14	Sparse Color Filter #1 White-Green-White-Red 14-bit unpacked
PixelFormatInfoSelector_SCF1WGWR16	Sparse Color Filter #1 White-Green-White-Red 16-bit
PixelFormatInfoSelector_SCF1WRWG8	Sparse Color Filter #1 White-Red-White-Green 8-bit
PixelFormatInfoSelector_SCF1WRWG10	Sparse Color Filter #1 White-Red-White-Green 10-bit unpacked

Enumerator

PixelFormatInfoSelector_SCF1WRWG10p	Sparse Color Filter #1 White-Red-White-Green 10-bit packed
PixelFormatInfoSelector_SCF1WRWG12	Sparse Color Filter #1 White-Red-White-Green 12-bit unpacked
PixelFormatInfoSelector_SCF1WRWG12p	Sparse Color Filter #1 White-Red-White-Green 12-bit packed
PixelFormatInfoSelector_SCF1WRWG14	Sparse Color Filter #1 White-Red-White-Green 14-bit unpacked
PixelFormatInfoSelector_SCF1WRWG16	Sparse Color Filter #1 White-Red-White-Green 16-bit
PixelFormatInfoSelector_YCbCr8	YCbCr 4:4:4 8-bit
PixelFormatInfoSelector_YCbCr8_CbYCr	YCbCr 4:4:4 8-bit
PixelFormatInfoSelector_YCbCr10_CbYCr	YCbCr 4:4:4 10-bit unpacked
PixelFormatInfoSelector_YCbCr10p_CbYCr	YCbCr 4:4:4 10-bit packed
PixelFormatInfoSelector_YCbCr12_CbYCr	YCbCr 4:4:4 12-bit unpacked
PixelFormatInfoSelector_YCbCr12p_CbYCr	YCbCr 4:4:4 12-bit packed
PixelFormatInfoSelector_YCbCr411_8	YCbCr 4:1:1 8-bit
PixelFormatInfoSelector_YCbCr411_8_CbYYCrYY	YCbCr 4:1:1 8-bit
PixelFormatInfoSelector_YCbCr422_8	YCbCr 4:2:2 8-bit
PixelFormatInfoSelector_YCbCr422_8_CbYCrY	YCbCr 4:2:2 8-bit
PixelFormatInfoSelector_YCbCr422_10	YCbCr 4:2:2 10-bit unpacked
PixelFormatInfoSelector_YCbCr422_10_CbYCrY	YCbCr 4:2:2 10-bit unpacked
PixelFormatInfoSelector_YCbCr422_10p	YCbCr 4:2:2 10-bit packed
PixelFormatInfoSelector_YCbCr422_10p_CbYCrY	YCbCr 4:2:2 10-bit packed
PixelFormatInfoSelector_YCbCr422_12	YCbCr 4:2:2 12-bit unpacked
PixelFormatInfoSelector_YCbCr422_12_CbYCrY	YCbCr 4:2:2 12-bit unpacked
PixelFormatInfoSelector_YCbCr422_12p	YCbCr 4:2:2 12-bit packed
PixelFormatInfoSelector_YCbCr422_12p_CbYCrY	YCbCr 4:2:2 12-bit packed
PixelFormatInfoSelector_YCbCr601_8_CbYCr	YCbCr 4:4:4 8-bit BT.601
PixelFormatInfoSelector_YCbCr601_10_CbYCr	YCbCr 4:4:4 10-bit unpacked BT.601
PixelFormatInfoSelector_YCbCr601_10p_CbYCr	YCbCr 4:4:4 10-bit packed BT.601
PixelFormatInfoSelector_YCbCr601_12_CbYCr	YCbCr 4:4:4 12-bit unpacked BT.601
PixelFormatInfoSelector_YCbCr601_12p_CbYCr	YCbCr 4:4:4 12-bit packed BT.601
PixelFormatInfoSelector_YCbCr601_411_8_CbYYCrYY	YCbCr 4:1:1 8-bit BT.601
PixelFormatInfoSelector_YCbCr601_422_8	YCbCr 4:2:2 8-bit BT.601
PixelFormatInfoSelector_YCbCr601_422_8_CbYCrY	YCbCr 4:2:2 8-bit BT.601
PixelFormatInfoSelector_YCbCr601_422_10	YCbCr 4:2:2 10-bit unpacked BT.601
PixelFormatInfoSelector_YCbCr601_422_10_CbYYCrY	YCbCr 4:2:2 10-bit unpacked BT.601
PixelFormatInfoSelector_YCbCr601_422_10p	YCbCr 4:2:2 10-bit packed BT.601
PixelFormatInfoSelector_YCbCr601_422_10p_CbYYCrY	YCbCr 4:2:2 10-bit packed BT.601
PixelFormatInfoSelector_YCbCr601_422_12	YCbCr 4:2:2 12-bit unpacked BT.601
PixelFormatInfoSelector_YCbCr601_422_12_CbYYCrY	YCbCr 4:2:2 12-bit unpacked BT.601
PixelFormatInfoSelector_YCbCr601_422_12p	YCbCr 4:2:2 12-bit packed BT.601
PixelFormatInfoSelector_YCbCr601_422_12p_CbYYCrY	YCbCr 4:2:2 12-bit packed BT.601
PixelFormatInfoSelector_YCbCr709_8_CbYCr	YCbCr 4:4:4 8-bit BT.709

Enumerator

PixelFormatInfoSelector_YCbCr709_10_CbYCr	YCbCr 4:4:4 10-bit unpacked BT.709
PixelFormatInfoSelector_YCbCr709_10p_CbYCr	YCbCr 4:4:4 10-bit packed BT.709
PixelFormatInfoSelector_YCbCr709_12_CbYCr	YCbCr 4:4:4 12-bit unpacked BT.709
PixelFormatInfoSelector_YCbCr709_12p_CbYCr	YCbCr 4:4:4 12-bit packed BT.709
PixelFormatInfoSelector_YCbCr709_411_8_CbYY↔ CrYY	YCbCr 4:1:1 8-bit BT.709
PixelFormatInfoSelector_YCbCr709_422_8	YCbCr 4:2:2 8-bit BT.709
PixelFormatInfoSelector_YCbCr709_422_8_CbYCrY	YCbCr 4:2:2 8-bit BT.709
PixelFormatInfoSelector_YCbCr709_422_10	YCbCr 4:2:2 10-bit unpacked BT.709
PixelFormatInfoSelector_YCbCr709_422_10_CbY↔ CrY	YCbCr 4:2:2 10-bit unpacked BT.709
PixelFormatInfoSelector_YCbCr709_422_10p	YCbCr 4:2:2 10-bit packed BT.709
PixelFormatInfoSelector_YCbCr709_422_10p_Cb↔ YCrY	YCbCr 4:2:2 10-bit packed BT.709
PixelFormatInfoSelector_YCbCr709_422_12	YCbCr 4:2:2 12-bit unpacked BT.709
PixelFormatInfoSelector_YCbCr709_422_12_CbY↔ CrY	YCbCr 4:2:2 12-bit unpacked BT.709
PixelFormatInfoSelector_YCbCr709_422_12p	YCbCr 4:2:2 12-bit packed BT.709
PixelFormatInfoSelector_YCbCr709_422_12p_Cb↔ YCrY	YCbCr 4:2:2 12-bit packed BT.709
PixelFormatInfoSelector_YUV8_UYV	YUV 4:4:4 8-bit
PixelFormatInfoSelector_YUV411_8_UYVYY	YUV 4:1:1 8-bit
PixelFormatInfoSelector_YUV422_8	YUV 4:2:2 8-bit
PixelFormatInfoSelector_YUV422_8_UYVY	YUV 4:2:2 8-bit
PixelFormatInfoSelector_Polarized8	Monochrome Polarized 8-bit
PixelFormatInfoSelector_Polarized10p	Monochrome Polarized 10-bit packed
PixelFormatInfoSelector_Polarized12p	Monochrome Polarized 12-bit packed
PixelFormatInfoSelector_Polarized16	Monochrome Polarized 16-bit
PixelFormatInfoSelector_BayerRGPolarized8	Polarized Bayer Red Green filter 8-bit
PixelFormatInfoSelector_BayerRGPolarized10p	Polarized Bayer Red Green filter 10-bit packed
PixelFormatInfoSelector_BayerRGPolarized12p	Polarized Bayer Red Green filter 12-bit packed
PixelFormatInfoSelector_BayerRGPolarized16	Polarized Bayer Red Green filter 16-bit
PixelFormatInfoSelector_LLCMono8	Lossless Compression Monochrome 8-bit
PixelFormatInfoSelector_LLCBayerRG8	Lossless Compression Bayer Red Green filter 8-bit
PixelFormatInfoSelector_JPEGMono8	JPEG Monochrome 8-bit
PixelFormatInfoSelector_JPEGColor8	JPEG Color 8-bit
NUM_PIXELFORMATINFOSELECTOR	

4.2.2.128 spinPixelSizeEnums

```
enum spinPixelSizeEnums
```

< Total size in bits of a pixel of the image.

Enumerator

PixelSize_Bpp1	1 bit per pixel.
PixelSize_Bpp2	2 bits per pixel.
PixelSize_Bpp4	4 bits per pixel.
PixelSize_Bpp8	8 bits per pixel.
PixelSize_Bpp10	10 bits per pixel.
PixelSize_Bpp12	12 bits per pixel.
PixelSize_Bpp14	14 bits per pixel.
PixelSize_Bpp16	16 bits per pixel.
PixelSize_Bpp20	20 bits per pixel.
PixelSize_Bpp24	24 bits per pixel.
PixelSize_Bpp30	30 bits per pixel.
PixelSize_Bpp32	32 bits per pixel.
PixelSize_Bpp36	36 bits per pixel.
PixelSize_Bpp48	48 bits per pixel.
PixelSize_Bpp64	64 bits per pixel.
PixelSize_Bpp96	96 bits per pixel.
NUM_PIXELSIZE	

4.2.2.129 spinRegionDestinationEnums

```
enum spinRegionDestinationEnums
```

< Control the destination of the selected region.

Enumerator

RegionDestination_Stream0	The destination of the region is the data stream 0.
RegionDestination_Stream1	The destination of the region is the data stream 1.
RegionDestination_Stream2	The destination of the region is the data stream 2.
NUM_REGIONDESTINATION	

4.2.2.130 spinRegionModeEnums

```
enum spinRegionModeEnums
```

< Controls if the selected Region of interest is active and streaming.

Enumerator

RegionMode_Off	Disable the usage of the Region.
RegionMode_On	Enable the usage of the Region.
NUM_REGIONMODE	

4.2.2.131 spinRegionSelectorEnums

enum `spinRegionSelectorEnums`

< Selects the Region of interest to control. The RegionSelector feature allows devices that are able to extract multiple regions out of an image, to configure the features of those individual regions independently.

Enumerator

RegionSelector_Region0	Selected feature will control the region 0.
RegionSelector_Region1	Selected feature will control the region 1.
RegionSelector_Region2	Selected feature will control the region 2.
RegionSelector_All	Selected features will control all the regions at the same time.
NUM_REGIONSELECTOR	

4.2.2.132 spinRgbTransformLightSourceEnums

enum `spinRgbTransformLightSourceEnums`

< Used to select from a set of RGBtoRGB transform matrices calibrated for different light sources. Selecting a value also sets the white balance ratios (BalanceRatioRed and BalanceRatioBlue), but those can be overwritten through manual or auto white balance.

Enumerator

RgbTransformLightSource_General	Uses a matrix calibrated for a wide range of light sources.
RgbTransformLightSource_Tungsten2800K	Uses a matrix optimized for tungsten/incandescent light with color temperature 2800K.
RgbTransformLightSource_WarmFluorescent3000K	Uses a matrix optimized for a typical warm fluorescent light with color temperature 3000K.
RgbTransformLightSource_CoolFluorescent4000K	Uses a matrix optimized for a typical cool fluorescent light with color temperature 4000K.
RgbTransformLightSource_Daylight5000K	Uses a matrix optimized for noon Daylight with color temperature 5000K.
RgbTransformLightSource_Cloudy6500K	Uses a matrix optimized for a cloudy sky with color temperature 6500K.
RgbTransformLightSource_Shade8000K	Uses a matrix optimized for shade with color temperature 8000K.
RgbTransformLightSource_Custom	Uses a custom matrix set by the user through the ColorTransformationValueSelector and ColorTransformationValue controls.
NUM_RGBTRANSFORMLIGHTSOURCE	

4.2.2.133 spinScan3dCoordinateReferenceSelectorEnums

enum `spinScan3dCoordinateReferenceSelectorEnums`

< Sets the index to read a coordinate system reference value defining the transform of a point from the current (Anchor or Transformed) system to the reference system.

Enumerator

<code>Scan3dCoordinateReferenceSelector_RotationX</code>	Rotation around X axis.
<code>Scan3dCoordinateReferenceSelector_RotationY</code>	Rotation around Y axis.
<code>Scan3dCoordinateReferenceSelector_RotationZ</code>	Rotation around Z axis.
<code>Scan3dCoordinateReferenceSelector_TranslationX</code>	X axis translation.
<code>Scan3dCoordinateReferenceSelector_TranslationY</code>	Y axis translation.
<code>Scan3dCoordinateReferenceSelector_TranslationZ</code>	Z axis translation.
<code>NUM_SCAN3DCOORDINATEREFERENCESELECTOR</code>	

4.2.2.134 spinScan3dCoordinateSelectorEnums

enum `spinScan3dCoordinateSelectorEnums`

< Selects the individual coordinates in the vectors for 3D information/transformation.

Enumerator

<code>Scan3dCoordinateSelector_CoordinateA</code>	The first (X or Theta) coordinate
<code>Scan3dCoordinateSelector_CoordinateB</code>	The second (Y or Phi) coordinate
<code>Scan3dCoordinateSelector_CoordinateC</code>	The third (Z or Rho) coordinate.
<code>NUM_SCAN3DCOORDINATESELECTOR</code>	

4.2.2.135 spinScan3dCoordinateSystemEnums

enum `spinScan3dCoordinateSystemEnums`

< Specifies the Coordinate system to use for the device.

Enumerator

<code>Scan3dCoordinateSystem_Cartesian</code>	Default value. 3-axis orthogonal, right-hand X-Y-Z.
<code>Scan3dCoordinateSystem_Spherical</code>	A Theta-Phi-Rho coordinate system.
<code>Scan3dCoordinateSystem_Cylindrical</code>	A Theta-Y-Rho coordinate system.
<code>NUM_SCAN3DCOORDINATESYSTEM</code>	

4.2.2.136 spinScan3dCoordinateSystemReferenceEnums

enum `spinScan3dCoordinateSystemReferenceEnums`

< Defines coordinate system reference location.

Enumerator

<code>Scan3dCoordinateSystemReference_Anchor</code>	Default value. Original fixed reference. The coordinate system fixed relative the camera reference point marker is used.
<code>Scan3dCoordinateSystemReference_Transformed</code>	Transformed reference system. The transformed coordinate system is used according to the definition in the rotation and translation matrices.
<code>NUM_SCAN3DCOORDINATESYSTEMREFERENCE</code>	

4.2.2.137 spinScan3dCoordinateTransformSelectorEnums

enum `spinScan3dCoordinateTransformSelectorEnums`

< Sets the index to read/write a coordinate transform value.

Enumerator

<code>Scan3dCoordinateTransformSelector_RotationX</code>	Rotation around X axis.
<code>Scan3dCoordinateTransformSelector_RotationY</code>	Rotation around Y axis.
<code>Scan3dCoordinateTransformSelector_RotationZ</code>	Rotation around Z axis.
<code>Scan3dCoordinateTransformSelector_TranslationX</code>	Translation along X axis.
<code>Scan3dCoordinateTransformSelector_TranslationY</code>	Translation along Y axis.
<code>Scan3dCoordinateTransformSelector_TranslationZ</code>	Translation along Z axis.
<code>NUM_SCAN3DCOORDINATETRANSFORMSELECTOR</code>	

4.2.2.138 spinScan3dDistanceUnitEnums

enum `spinScan3dDistanceUnitEnums`

< Specifies the unit used when delivering calibrated distance data.

Enumerator

<code>Scan3dDistanceUnit_Millimeter</code>	Distance values are in millimeter units (default).
<code>Scan3dDistanceUnit_Inch</code>	Distance values are in inch units.
<code>NUM_SCAN3DDISTANCEUNIT</code>	

4.2.2.139 spinScan3dOutputModeEnums

enum `spinScan3dOutputModeEnums`

< Controls the Calibration and data organization of the device, naming the coordinates transmitted.

Enumerator

<code>Scan3dOutputMode_UncalibratedC</code>	Uncalibrated 2.5D Depth map. The distance data does not represent a physical unit and may be non-linear. The data is a 2.5D range map only.
<code>Scan3dOutputMode_CalibratedABC_Grid</code>	3 Coordinates in grid organization. The full 3 coordinate data with the grid array organization from the sensor kept.
<code>Scan3dOutputMode_CalibratedABC_PointCloud</code>	3 Coordinates without organization. The full 3 coordinate data without any organization of data points. Typically only valid points transmitted giving varying image size.
<code>Scan3dOutputMode_CalibratedAC</code>	2 Coordinates with fixed B sampling. The data is sent as a A and C coordinates (X,Z or Theta,Rho). The B (Y) axis uses the scale and offset parameters for the B axis.
<code>Scan3dOutputMode_CalibratedAC_Linescan</code>	2 Coordinates with varying sampling. The data is sent as a A and C coordinates (X,Z or Theta,Rho). The B (Y) axis comes from the encoder chunk value.
<code>Scan3dOutputMode_CalibratedC</code>	Calibrated 2.5D Depth map. The distance data is expressed in the chosen distance unit. The data is a 2.5D range map. No information on X-Y axes available.
<code>Scan3dOutputMode_CalibratedC_Linescan</code>	Depth Map with varying B sampling. The distance data is expressed in the chosen distance unit. The data is a 2.5D range map. The B (Y) axis comes from the encoder chunk value.
<code>Scan3dOutputMode_RectifiedC</code>	Rectified 2.5D Depth map. The distance data has been rectified to a uniform sampling pattern in the X and Y direction. The data is a 2.5D range map only. If a complete 3D point cloud is rectified but transmitted as explicit coordinates it should be transmitted as one of the "CalibratedABC" formats.
<code>Scan3dOutputMode_RectifiedC_Linescan</code>	Rectified 2.5D Depth map with varying B sampling. The data is sent as rectified 1D profiles using <code>Coord3D_C</code> pixels. The B (Y) axis comes from the encoder chunk value.
<code>Scan3dOutputMode_DisparityC</code>	Disparity 2.5D Depth map. The distance is inversely proportional to the pixel (disparity) value.
<code>Scan3dOutputMode_DisparityC_Linescan</code>	Disparity 2.5D Depth map with varying B sampling. The distance is inversely proportional to the pixel (disparity) value. The B (Y) axis comes from the encoder chunk value.
<code>NUM_SCAN3DOUTPUTMODE</code>	

4.2.2.140 spinSensorDigitizationTapsEnums

enum `spinSensorDigitizationTapsEnums`

< Number of digitized samples outputted simultaneously by the camera A/D conversion stage.

Enumerator

SensorDigitizationTaps_One	1 tap.
SensorDigitizationTaps_Two	2 taps.
SensorDigitizationTaps_Three	3 taps.
SensorDigitizationTaps_Four	4 taps.
SensorDigitizationTaps_Eight	8 taps.
SensorDigitizationTaps_Ten	10 taps.
NUM_SENSORDIGITIZATIONTAPS	

4.2.2.141 spinSensorShutterModeEnums

enum `spinSensorShutterModeEnums`

< Sets the shutter mode of the device.

Enumerator

SensorShutterMode_Global	The shutter opens and closes at the same time for all pixels. All the pixels are exposed for the same length of time at the same time.
SensorShutterMode_Rolling	The shutter opens and closes sequentially for groups (typically lines) of pixels. All the pixels are exposed for the same length of time but not at the same time.
SensorShutterMode_GlobalReset	The shutter opens at the same time for all pixels but ends in a sequential manner. The pixels are exposed for different lengths of time.
NUM_SENSORSHUTTERMODE	

4.2.2.142 spinSensorTapsEnums

enum `spinSensorTapsEnums`

< Number of taps of the camera sensor.

Enumerator

SensorTaps_One	1 tap.
SensorTaps_Two	2 taps.
SensorTaps_Three	3 taps.
SensorTaps_Four	4 taps.
SensorTaps_Eight	8 taps.
SensorTaps_Ten	10 taps.
NUM_SENSORTAPS	

4.2.2.143 spinSequencerConfigurationModeEnums

enum `spinSequencerConfigurationModeEnums`

< Controls whether or not a sequencer is in configuration mode.

Enumerator

SequencerConfigurationMode_Off	
SequencerConfigurationMode_On	
NUM_SEQUENCERCONFIGURATIONMODE	

4.2.2.144 spinSequencerConfigurationValidEnums

enum `spinSequencerConfigurationValidEnums`

< Display whether the current sequencer configuration is valid to run.

Enumerator

SequencerConfigurationValid_No	
SequencerConfigurationValid_Yes	
NUM_SEQUENCERCONFIGURATIONVALID	

4.2.2.145 spinSequencerModeEnums

enum `spinSequencerModeEnums`

< Controls whether or not a sequencer is active.

Enumerator

SequencerMode_Off	
SequencerMode_On	
NUM_SEQUENCERMODE	

4.2.2.146 spinSequencerSetValidEnums

enum `spinSequencerSetValidEnums`

< Displays whether the currently selected sequencer set's register contents are valid to use.

Enumerator

SequencerSetValid_No	
SequencerSetValid_Yes	
NUM_SEQUENCERSETVALID	

4.2.2.147 spinSequencerTriggerActivationEnums

enum `spinSequencerTriggerActivationEnums`

< Specifies the activation mode of the sequencer trigger.

Enumerator

SequencerTriggerActivation_RisingEdge	
SequencerTriggerActivation_FallingEdge	
SequencerTriggerActivation_AnyEdge	
SequencerTriggerActivation_LevelHigh	
SequencerTriggerActivation_LevelLow	
NUM_SEQUENCERTRIGGERACTIVATION	

4.2.2.148 spinSequencerTriggerSourceEnums

enum `spinSequencerTriggerSourceEnums`

< Specifies the internal signal or physical input line to use as the sequencer trigger source.

Enumerator

SequencerTriggerSource_Off	
SequencerTriggerSource_FrameStart	
NUM_SEQUENCERTRIGGERSOURCE	

4.2.2.149 spinSerialPortBaudRateEnums

enum `spinSerialPortBaudRateEnums`

< This feature controls the baud rate used by the selected serial port.

Enumerator

SerialPortBaudRate_Baud300	
SerialPortBaudRate_Baud600	
SerialPortBaudRate_Baud1200	
SerialPortBaudRate_Baud2400	
SerialPortBaudRate_Baud4800	
SerialPortBaudRate_Baud9600	
SerialPortBaudRate_Baud14400	
SerialPortBaudRate_Baud19200	
SerialPortBaudRate_Baud38400	
SerialPortBaudRate_Baud57600	
SerialPortBaudRate_Baud115200	
SerialPortBaudRate_Baud230400	
SerialPortBaudRate_Baud460800	
SerialPortBaudRate_Baud921600	
NUM_SERIALPORTBAUDRATE	

4.2.2.150 spinSerialPortParityEnums

enum `spinSerialPortParityEnums`

< This feature controls the parity used by the selected serial port.

Enumerator

SerialPortParity_None	
SerialPortParity_Odd	
SerialPortParity_Even	
SerialPortParity_Mark	
SerialPortParity_Space	
NUM_SERIALPORTPARITY	

4.2.2.151 spinSerialPortSelectorEnums

enum `spinSerialPortSelectorEnums`

< Selects which serial port of the device to control.

Enumerator

SerialPortSelector_SerialPort0	
NUM_SERIALPORTSELECTOR	

4.2.2.152 spinSerialPortSourceEnums

enum `spinSerialPortSourceEnums`

< Specifies the physical input Line on which to receive serial data.

Enumerator

SerialPortSource_Line0	
SerialPortSource_Line1	
SerialPortSource_Line2	
SerialPortSource_Line3	
SerialPortSource_Off	
NUM_SERIALPORTSOURCE	

4.2.2.153 spinSerialPortStopBitsEnums

enum `spinSerialPortStopBitsEnums`

< This feature controls the number of stop bits used by the selected serial port.

Enumerator

SerialPortStopBits_Bits1	
SerialPortStopBits_Bits1AndAHalf	
SerialPortStopBits_Bits2	
NUM_SERIALPORTSTOPBITS	

4.2.2.154 spinSoftwareSignalSelectorEnums

enum `spinSoftwareSignalSelectorEnums`

< Selects which Software Signal features to control.

Enumerator

SoftwareSignalSelector_SoftwareSignal0	Selects the software generated signal to control.
SoftwareSignalSelector_SoftwareSignal1	Selects the software generated signal to control.
SoftwareSignalSelector_SoftwareSignal2	Selects the software generated signal to control.
NUM_SOFTWARESIGNALSELECTOR	

4.2.2.155 spinSourceSelectorEnums

```
enum spinSourceSelectorEnums
```

< Selects the source to control.

Enumerator

SourceSelector_Source0	Selects the data source 0.
SourceSelector_Source1	Selects the data source 1.
SourceSelector_Source2	Selects the data source 2.
SourceSelector_All	Selects all the data sources.
NUM_SOURCESELECTOR	

4.2.2.156 spinTestPatternEnums

```
enum spinTestPatternEnums
```

< Selects the type of test pattern that is generated by the device as image source.

Enumerator

TestPattern_Off	Test pattern is disabled.
TestPattern_Increment	Pixel value increments by 1 for each pixel.
TestPattern_SensorTestPattern	A test pattern generated by the image sensor. The pattern varies for different sensor models.
NUM_TESTPATTERN	

4.2.2.157 spinTestPatternGeneratorSelectorEnums

```
enum spinTestPatternGeneratorSelectorEnums
```

< Selects which test pattern generator is controlled by the TestPattern feature.

Enumerator

TestPatternGeneratorSelector_Sensor	TestPattern feature controls the sensor's test pattern generator.
TestPatternGeneratorSelector_PipelineStart	TestPattern feature controls the test pattern inserted at the start of the image pipeline.
NUM_TESTPATTERNGENERATORSELECTOR	

4.2.2.158 spinTimerSelectorEnums

```
enum spinTimerSelectorEnums
```

< Selects which Timer to configure.

Enumerator

TimerSelector_Timer0	Selects the Timer 0.
TimerSelector_Timer1	Selects the Timer 1.
TimerSelector_Timer2	Selects the Timer 2.
NUM_TIMERSELECTOR	

4.2.2.159 spinTimerStatusEnums

```
enum spinTimerStatusEnums
```

< Returns the current status of the Timer.

Enumerator

TimerStatus_TimerIdle	The Timer is idle.
TimerStatus_TimerTriggerWait	The Timer is waiting for a start trigger.
TimerStatus_TimerActive	The Timer is counting for the specified duration.
TimerStatus_TimerCompleted	The Timer reached the TimerDuration count.
NUM_TIMERSTATUS	

4.2.2.160 spinTimerTriggerActivationEnums

```
enum spinTimerTriggerActivationEnums
```

< Selects the activation mode of the trigger to start the Timer.

Enumerator

TimerTriggerActivation_RisingEdge	Starts counting on the Rising Edge of the selected trigger signal.
TimerTriggerActivation_FallingEdge	Starts counting on the Falling Edge of the selected trigger signal.
TimerTriggerActivation_AnyEdge	Starts counting on the Falling or Rising Edge of the selected trigger signal.
TimerTriggerActivation_LevelHigh	Counts as long as the selected trigger signal level is High.
TimerTriggerActivation_LevelLow	Counts as long as the selected trigger signal level is Low.
NUM_TIMERTRIGGERACTIVATION	

4.2.2.161 spinTimerTriggerSourceEnums

```
enum spinTimerTriggerSourceEnums
```

< Selects the source of the trigger to start the Timer.

Enumerator

TimerTriggerSource_Off	Disables the Timer trigger.
TimerTriggerSource_AcquisitionTrigger	Starts with the reception of the Acquisition Trigger.
TimerTriggerSource_AcquisitionStart	Starts with the reception of the Acquisition Start.
TimerTriggerSource_AcquisitionEnd	Starts with the reception of the Acquisition End.
TimerTriggerSource_FrameTrigger	Starts with the reception of the Frame Start Trigger.
TimerTriggerSource_FrameStart	Starts with the reception of the Frame Start.
TimerTriggerSource_FrameEnd	Starts with the reception of the Frame End.
TimerTriggerSource_FrameBurstStart	Starts with the reception of the Frame Burst Start.
TimerTriggerSource_FrameBurstEnd	Starts with the reception of the Frame Burst End.
TimerTriggerSource_LineTrigger	Starts with the reception of the Line Start Trigger.
TimerTriggerSource_LineStart	Starts with the reception of the Line Start.
TimerTriggerSource_LineEnd	Starts with the reception of the Line End.
TimerTriggerSource_ExposureStart	Starts with the reception of the Exposure Start.
TimerTriggerSource_ExposureEnd	Starts with the reception of the Exposure End.
TimerTriggerSource_Line0	Starts when the specified TimerTriggerActivation condition is met on the chosen I/O Line.
TimerTriggerSource_Line1	Starts when the specified TimerTriggerActivation condition is met on the chosen I/O Line.
TimerTriggerSource_Line2	Starts when the specified TimerTriggerActivation condition is met on the chosen I/O Line.
TimerTriggerSource_UserOutput0	Specifies which User Output bit signal to use as internal source for the trigger.
TimerTriggerSource_UserOutput1	Specifies which User Output bit signal to use as internal source for the trigger.
TimerTriggerSource_UserOutput2	Specifies which User Output bit signal to use as internal source for the trigger.
TimerTriggerSource_Counter0Start	Starts with the reception of the Counter Start.
TimerTriggerSource_Counter1Start	Starts with the reception of the Counter Start.
TimerTriggerSource_Counter2Start	Starts with the reception of the Counter Start.
TimerTriggerSource_Counter0End	Starts with the reception of the Counter End.
TimerTriggerSource_Counter1End	Starts with the reception of the Counter End.
TimerTriggerSource_Counter2End	Starts with the reception of the Counter End.
TimerTriggerSource_Timer0Start	Starts with the reception of the Timer Start.
TimerTriggerSource_Timer1Start	Starts with the reception of the Timer Start.
TimerTriggerSource_Timer2Start	Starts with the reception of the Timer Start.
TimerTriggerSource_Timer0End	Starts with the reception of the Timer End. Note that a timer can retrigger itself to achieve a free running Timer.
TimerTriggerSource_Timer1End	Starts with the reception of the Timer End. Note that a timer can retrigger itself to achieve a free running Timer.
TimerTriggerSource_Timer2End	Starts with the reception of the Timer End. Note that a timer can retrigger itself to achieve a free running Timer.

Enumerator

TimerTriggerSource_Encoder0	Starts with the reception of the Encoder output signal.
TimerTriggerSource_Encoder1	Starts with the reception of the Encoder output signal.
TimerTriggerSource_Encoder2	Starts with the reception of the Encoder output signal.
TimerTriggerSource_SoftwareSignal0	Starts on the reception of the Software Signal.
TimerTriggerSource_SoftwareSignal1	Starts on the reception of the Software Signal.
TimerTriggerSource_SoftwareSignal2	Starts on the reception of the Software Signal.
TimerTriggerSource_Action0	Starts with the assertion of the chosen action signal.
TimerTriggerSource_Action1	Starts with the assertion of the chosen action signal.
TimerTriggerSource_Action2	Starts with the assertion of the chosen action signal.
TimerTriggerSource_LinkTrigger0	Starts with the reception of the chosen Link Trigger.
TimerTriggerSource_LinkTrigger1	Starts with the reception of the chosen Link Trigger.
TimerTriggerSource_LinkTrigger2	Starts with the reception of the chosen Link Trigger.
NUM_TIMERTRIGGERSOURCE	

4.2.2.162 spinTransferComponentSelectorEnums

enum `spinTransferComponentSelectorEnums`

< Selects the color component for the control of the TransferStreamChannel feature.

Enumerator

TransferComponentSelector_Red	The TransferStreamChannel feature controls the index of the stream channel for the streaming of the red plane of the planar pixel formats.
TransferComponentSelector_Green	The TransferStreamChannel feature controls the index of the stream channel for the streaming of the green plane of the planar pixel formats.
TransferComponentSelector_Blue	The TransferStreamChannel feature controls the index of the stream channel for the streaming of blue plane of the planar pixel formats.
TransferComponentSelector_All	The TransferStreamChannel feature controls the index of the stream channel for the streaming of all the planes of the planar pixel formats simultaneously or non planar pixel formats.
NUM_TRANSFERCOMPONENTSELECTOR	

4.2.2.163 spinTransferControlModeEnums

enum `spinTransferControlModeEnums`

< Selects the control method for the transfers. Basic and Automatic start transmitting data as soon as there is enough data to fill a link layer packet. User Controlled allows you to directly control the transfer of blocks.

Enumerator

TransferControlMode_Basic	Basic
TransferControlMode_Automatic	Automatic
TransferControlMode_UserControlled	User Controlled
NUM_TRANSFERCONTROLMODE	

4.2.2.164 spinTransferOperationModeEnums

```
enum spinTransferOperationModeEnums
```

< Selects the operation mode of the transfer. Continuous is similar to Basic/Automatic but you can start/stop the transfer while acquisition runs independently. Multi Block transmits a specified number of blocks and then stops.

Enumerator

TransferOperationMode_Continuous	Continuous
TransferOperationMode_MultiBlock	Multi Block
NUM_TRANSFEROPERATIONMODE	

4.2.2.165 spinTransferQueueModeEnums

```
enum spinTransferQueueModeEnums
```

< Specifies the operation mode of the transfer queue.

Enumerator

TransferQueueMode_FirstInFirstOut	Blocks first In are transferred Out first.
NUM_TRANSFERQUEUEMODE	

4.2.2.166 spinTransferSelectorEnums

```
enum spinTransferSelectorEnums
```

< Selects which stream transfers are currently controlled by the selected Transfer features.

Enumerator

TransferSelector_Stream0	The transfer features control the data stream 0.
TransferSelector_Stream1	The transfer features control the data stream 1.
TransferSelector_Stream2	The transfer features control the data stream 2.
TransferSelector_All	The transfer features control all the data streams simulateneously.
NUM_TRANSFERSELECTOR	

4.2.2.167 spinTransferStatusSelectorEnums

```
enum spinTransferStatusSelectorEnums
```

< Selects which status of the transfer module to read.

Enumerator

TransferStatusSelector_Streaming	Data blocks are transmitted when enough data is available.
TransferStatusSelector_Paused	Data blocks transmission is suspended immediately.
TransferStatusSelector_Stopping	Data blocks transmission is stopping. The current block transmission will be completed and the transfer state will stop.
TransferStatusSelector_Stopped	Data blocks transmission is stopped.
TransferStatusSelector_QueueOverflow	Data blocks queue is in overflow state.
NUM_TRANSFERSTATUSSELECTOR	

4.2.2.168 spinTransferTriggerActivationEnums

```
enum spinTransferTriggerActivationEnums
```

< Specifies the activation mode of the transfer control trigger.

Enumerator

TransferTriggerActivation_RisingEdge	Specifies that the trigger is considered valid on the rising edge of the source signal.
TransferTriggerActivation_FallingEdge	Specifies that the trigger is considered valid on the falling edge of the source signal.
TransferTriggerActivation_AnyEdge	Specifies that the trigger is considered valid on the falling or rising edge of the source signal.
TransferTriggerActivation_LevelHigh	Specifies that the trigger is considered valid as long as the level of the source signal is high. This can apply to TransferActive and TransferPause trigger.
TransferTriggerActivation_LevelLow	Specifies that the trigger is considered valid as long as the level of the source signal is low. This can apply to TransferActive and TransferPause trigger.
NUM_TRANSFERTRIGGERACTIVATION	

4.2.2.169 spinTransferTriggerModeEnums

```
enum spinTransferTriggerModeEnums
```

< Controls if the selected trigger is active.

Enumerator

TransferTriggerMode_Off	Disables the selected trigger.
TransferTriggerMode_On	Enable the selected trigger.
NUM_TRANSFERTRIGGERMODE	

4.2.2.170 spinTransferTriggerSelectorEnums

```
enum spinTransferTriggerSelectorEnums
```

< Selects the type of transfer trigger to configure.

Enumerator

TransferTriggerSelector_TransferStart	Selects a trigger to start the transfers.
TransferTriggerSelector_TransferStop	Selects a trigger to stop the transfers.
TransferTriggerSelector_TransferAbort	Selects a trigger to abort the transfers.
TransferTriggerSelector_TransferPause	Selects a trigger to pause the transfers.
TransferTriggerSelector_TransferResume	Selects a trigger to Resume the transfers.
TransferTriggerSelector_TransferActive	Selects a trigger to Activate the transfers. This trigger type is used when TriggerActivation is set LevelHigh or levelLow.
TransferTriggerSelector_TransferBurstStart	Selects a trigger to start the transfer of a burst of frames specified by TransferBurstCount.
TransferTriggerSelector_TransferBurstStop	Selects a trigger to end the transfer of a burst of frames.
NUM_TRANSFERTRIGGERSELECTOR	

4.2.2.171 spinTransferTriggerSourceEnums

```
enum spinTransferTriggerSourceEnums
```

< Specifies the signal to use as the trigger source for transfers.

Enumerator

TransferTriggerSource_Line0	Specifies which physical line (or pin) and associated I/O control block to use as external source for the transfer control trigger signal.
TransferTriggerSource_Line1	Specifies which physical line (or pin) and associated I/O control block to use as external source for the transfer control trigger signal.
TransferTriggerSource_Line2	Specifies which physical line (or pin) and associated I/O control block to use as external source for the transfer control trigger signal.
TransferTriggerSource_Counter0Start	Specifies which of the Counter signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Counter1Start	Specifies which of the Counter signal to use as internal source for the transfer control trigger signal.

Enumerator

TransferTriggerSource_Counter2Start	Specifies which of the Counter signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Counter0End	Specifies which of the Counter signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Counter1End	Specifies which of the Counter signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Counter2End	Specifies which of the Counter signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Timer0Start	Specifies which Timer signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Timer1Start	Specifies which Timer signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Timer2Start	Specifies which Timer signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Timer0End	Specifies which Timer signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Timer1End	Specifies which Timer signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Timer2End	Specifies which Timer signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_SoftwareSignal0	Specifies which Software Signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_SoftwareSignal1	Specifies which Software Signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_SoftwareSignal2	Specifies which Software Signal to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Action0	Specifies which Action command to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Action1	Specifies which Action command to use as internal source for the transfer control trigger signal.
TransferTriggerSource_Action2	Specifies which Action command to use as internal source for the transfer control trigger signal.
NUM_TRANSFERTRIGGERSOURCE	

4.2.2.172 spinTriggerActivationEnums

```
enum spinTriggerActivationEnums
```

< Specifies the activation mode of the trigger.

Enumerator

TriggerActivation_LevelLow	
TriggerActivation_LevelHigh	
TriggerActivation_FallingEdge	
TriggerActivation_RisingEdge	
TriggerActivation_AnyEdge	
NUM_TRIGGERACTIVATION	

4.2.2.173 spinTriggerModeEnums

```
enum spinTriggerModeEnums
```

< Controls whether or not trigger is active.

Enumerator

TriggerMode_Off	
TriggerMode_On	
NUM_TRIGGERMODE	

4.2.2.174 spinTriggerOverlapEnums

```
enum spinTriggerOverlapEnums
```

< Specifies the overlap mode of the trigger.

Enumerator

TriggerOverlap_Off	
TriggerOverlap_ReadOut	
TriggerOverlap_PreviousFrame	
NUM_TRIGGEROVERLAP	

4.2.2.175 spinTriggerSelectorEnums

```
enum spinTriggerSelectorEnums
```

< Selects the type of trigger to configure.

Enumerator

TriggerSelector_AcquisitionStart	
TriggerSelector_FrameStart	
TriggerSelector_FrameBurstStart	
NUM_TRIGGERSELECTOR	

4.2.2.176 spinTriggerSourceEnums

enum `spinTriggerSourceEnums`

< Specifies the internal signal or physical input line to use as the trigger source.

Enumerator

TriggerSource_Software	
TriggerSource_Line0	
TriggerSource_Line1	
TriggerSource_Line2	
TriggerSource_Line3	
TriggerSource_UserOutput0	
TriggerSource_UserOutput1	
TriggerSource_UserOutput2	
TriggerSource_UserOutput3	
TriggerSource_Counter0Start	
TriggerSource_Counter1Start	
TriggerSource_Counter0End	
TriggerSource_Counter1End	
TriggerSource_LogicBlock0	
TriggerSource_LogicBlock1	
TriggerSource_Action0	
NUM_TRIGGERSOURCE	

4.2.2.177 spinUserOutputSelectorEnums

enum `spinUserOutputSelectorEnums`

< Selects which bit of the User Output register is set by UserOutputValue.

Enumerator

UserOutputSelector_UserOutput0	
UserOutputSelector_UserOutput1	
UserOutputSelector_UserOutput2	
UserOutputSelector_UserOutput3	
NUM_USEROUTPUTSELECTOR	

4.2.2.178 spinUserSetDefaultEnums

enum `spinUserSetDefaultEnums`

< Selects the feature User Set to load and make active by default when the device is restarted.

Enumerator

UserSetDefault_Default	Factory default set.
UserSetDefault_UserSet0	User configurable set 0.
UserSetDefault_UserSet1	User configurable set 1.
NUM_USERSETDEFAULT	

4.2.2.179 spinUserSetSelectorEnums

enum `spinUserSetSelectorEnums`

< Selects the feature User Set to load, save or configure.

Enumerator

UserSetSelector_Default	Factory default set.
UserSetSelector_UserSet0	User configurable set 0.
UserSetSelector_UserSet1	User configurable set 1.
NUM_USERSETSELECTOR	

4.2.2.180 spinWhiteClipSelectorEnums

enum `spinWhiteClipSelectorEnums`


< Selects which White Clip to control.

Enumerator

WhiteClipSelector_All	White Clip will be applied to all channels or taps.
WhiteClipSelector_Red	White Clip will be applied to the red channel.
WhiteClipSelector_Green	White Clip will be applied to the green channel.
WhiteClipSelector_Blue	White Clip will be applied to the blue channel.
WhiteClipSelector_Y	White Clip will be applied to Y channel.
WhiteClipSelector_U	White Clip will be applied to U channel.
WhiteClipSelector_V	White Clip will be applied to V channel.
WhiteClipSelector_Tap1	White Clip will be applied to Tap 1.
WhiteClipSelector_Tap2	White Clip will be applied to Tap 2.
NUM_WHITECLIPSELECTOR	

4.3 Chunk Data Structures

Collaboration diagram for Chunk Data Structures:



Data Structures


- struct [spinChunkData](#)

The type of information that can be obtained from image chunk data.

4.3.1 Detailed Description

4.4 Spinnaker C QuickSpin API

Collaboration diagram for Spinnaker C QuickSpin API:



Modules

- [QuickSpin Access](#)

The functions in this section initialize the various QuickSpin structs for the C API.

- [Transport Layer Enumerations](#)
- [TLDevice Structures](#)
- [TLInterface Structures](#)
- [TLStream Structures](#)
- [TLSystem Structures](#)

4.4.1 Detailed Description

4.5 QuickSpin Access

The functions in this section initialize the various QuickSpin structs for the C API.

Collaboration diagram for QuickSpin Access:



Functions

- [SPINNAKERC_API quickSpinInit](#) ([spinCamera](#) hCamera, [quickSpin](#) *pQuickSpin)
- [SPINNAKERC_API quickSpinInitEx](#) ([spinCamera](#) hCamera, [quickSpin](#) *pQuickSpin, [quickSpinTLDevice](#) *pQuickSpinTLDevice, [quickSpinTLStream](#) *pQuickSpinTLStream)
- [SPINNAKERC_API quickSpinTLDeviceInit](#) ([spinCamera](#) hCamera, [quickSpinTLDevice](#) *pQuickSpinTLDevice)
- [SPINNAKERC_API quickSpinTLStreamInit](#) ([spinCamera](#) hCamera, [quickSpinTLStream](#) *pQuickSpinTLStream)
- [SPINNAKERC_API quickSpinTLInterfaceInit](#) ([spinInterface](#) hInterface, [quickSpinTLInterface](#) *pQuickSpinTLInterface)
- [SPINNAKERC_API quickSpinTLSystemInit](#) ([spinSystem](#) hSystem, [quickSpinTLSystem](#) *pQuickSpinTLSystem)

4.5.1 Detailed Description

The functions in this section initialize the various QuickSpin structs for the C API.

4.5.2 Function Documentation

4.5.2.1 quickSpinInit()

```

SPINNAKERC_API quickSpinInit (
    spinCamera hCamera,
    quickSpin * pQuickSpin )
  
```

4.5.2.2 quickSpinInitEx()

```
SPINNAKERC_API quickSpinInitEx (
    spinCamera hCamera,
    quickSpin * pQuickSpin,
    quickSpinTLDevice * pQuickSpinTLDevice,
    quickSpinTLStream * pQuickSpinTLStream )
```

4.5.2.3 quickSpinTLDeviceInit()

```
SPINNAKERC_API quickSpinTLDeviceInit (
    spinCamera hCamera,
    quickSpinTLDevice * pQuickSpinTLDevice )
```

4.5.2.4 quickSpinTLInterfaceInit()

```
SPINNAKERC_API quickSpinTLInterfaceInit (
    spinInterface hInterface,
    quickSpinTLInterface * pQuickSpinTLInterface )
```

4.5.2.5 quickSpinTLStreamInit()

```
SPINNAKERC_API quickSpinTLStreamInit (
    spinCamera hCamera,
    quickSpinTLStream * pQuickSpinTLStream )
```


4.5.2.6 quickSpinTLSystemInit()

```
SPINNAKERC_API quickSpinTLSystemInit (
    spinSystem hSystem,
    quickSpinTLSystem * pQuickSpinTLSystem )
```

4.6 Spinnaker C API

SpinnakerPlatform C Include.

Collaboration diagram for Spinnaker C API:



Modules

- [Spinnaker C Definitions](#)

Definitions for Spinnaker C.

- [Error Handling](#)

The functions in this section provide access to additional information related to error returns.

- [System Access](#)

The functions in this section provide access to information, objects, and functionality of the system object.

- [InterfaceList Access](#)

The functions in this section provide access to information, objects, and functionality of interface lists.

- [CameraList Access](#)

The functions in this section provide access to information, objects, and functionality of camera lists.

- [Interface Access](#)

The functions in this section provide access to information, objects, and functionality of interfaces.

- [Camera Access](#)

The functions in this section provide access to information, objects, and functionality of cameras.

- [SpinVideo Recording Access](#)

The functions in this section provide access to video recording capabilities, which include opening, building, and closing video files.

Functions

- [SPINNAKERC_API spinCameraDiscoverMaxPacketSize](#) ([spinCamera](#) hCamera, unsigned int *pMaxPacketSize)

Returns the largest packet size that can be safely used on the interface that device is connected to.

4.6.1 Detailed Description

SpinnakerPlatform C Include.

Spinnaker C Definition Includes Spinnaker GenICam C Wrapper Includes Spinnaker QuickSpin C Includes

Spinnaker C Definition Includes

4.6.2 Function Documentation

4.6.2.1 spinCameraDiscoverMaxPacketSize()

```
SPINNAKERC_API spinCameraDiscoverMaxPacketSize (  
    spinCamera hCamera,  
    unsigned int * pMaxPacketSize )
```

Returns the largest packet size that can be safely used on the interface that device is connected to.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera to check
<i>pMaxPacketSize</i>	The maximum packet size returned


Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.7 Error Handling

The functions in this section provide access to additional information related to error returns.

Collaboration diagram for Error Handling:



Functions

- [SPINNAKERC_API spinErrorGetLast](#) ([spinError](#) *pError)
Retrieves the error code of the last error.
- [SPINNAKERC_API spinErrorGetLastMessage](#) (char *pBuf, size_t *pBufLen)
Retrieves the error message of the last error.
- [SPINNAKERC_API spinErrorGetLastBuildDate](#) (char *pBuf, size_t *pBufLen)
Retrieves the build date of the last error.
- [SPINNAKERC_API spinErrorGetLastBuildTime](#) (char *pBuf, size_t *pBufLen)
Retrieves the build time of the last error.
- [SPINNAKERC_API spinErrorGetLastFileName](#) (char *pBuf, size_t *pBufLen)
Retrieves the filename of the last error.
- [SPINNAKERC_API spinErrorGetLastFullMessage](#) (char *pBuf, size_t *pBufLen)
Retrieves the full error message of the last error.
- [SPINNAKERC_API spinErrorGetLastFunctionName](#) (char *pBuf, size_t *pBufLen)
Retrieves the function name of the last error.
- [SPINNAKERC_API spinErrorGetLastLineNumber](#) (int64_t *pLineNum)
Retrieves the line number of the last error.

4.7.1 Detailed Description

The functions in this section provide access to additional information related to error returns.

4.7.2 Function Documentation

4.7.2.1 spinErrorGetLast()

```
SPINNAKERC_API spinErrorGetLast (
    spinError * pError )
```

Retrieves the error code of the last error.

See also

[spinError](#)

Parameters

<i>pError</i>	The error enum pointer in which the error message is returned
---------------	---

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.7.2.2 spinErrorGetLastBuildDate()

```
SPINNAKERC_API spinErrorGetLastBuildDate (
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the build date of the last error.

See also

[spinError](#)

Parameters

<i>pBuf</i>	The c-string character buffer in which the build date is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.7.2.3 spinErrorGetLastBuildTime()

```
SPINNAKERC_API spinErrorGetLastBuildTime (
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the build time of the last error.

See also

[spinError](#)

Parameters

<i>pBuf</i>	The c-string character buffer in which the build time is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.7.2.4 spinErrorGetLastFileName()

```
SPINNAKERC_API spinErrorGetLastFileName (
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the filename of the last error.

See also

[spinError](#)

Parameters

<i>pBuf</i>	The c-string character buffer in which the file name is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.7.2.5 spinErrorGetLastFullMessage()

```
SPINNAKERC_API spinErrorGetLastFullMessage (
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the full error message of the last error.

See also

[spinError](#)

Parameters

<i>pBuf</i>	The c-string character buffer in which the full error message is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.7.2.6 spinErrorGetLastFunctionName()

```
SPINNAKERC_API spinErrorGetLastFunctionName (
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the function name of the last error.

See also

[spinError](#)

Parameters

<i>pBuf</i>	The c-string character buffer in which the function name is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.7.2.7 spinErrorGetLastLineNumber()

```
SPINNAKERC_API spinErrorGetLastLineNumber (
    int64_t * pLineNum )
```

Retrieves the line number of the last error.

See also

[spinError](#)

Parameters

<i>pBuf</i>	The c-string character buffer in which the line number is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.7.2.8 spinErrorGetLastMessage()

```
SPINNAKERC_API spinErrorGetLastMessage (
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the error message of the last error.

See also

[spinError](#)

Parameters

<i>pBuf</i>	The c-string character buffer in which the error message is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8 System Access

The functions in this section provide access to information, objects, and functionality of the system object.

Collaboration diagram for System Access:



Functions

- [SPINNAKERC_API spinSystemGetInstance \(spinSystem *phSystem\)](#)
Retrieves an instance of the system object; the system is a singleton, so there will only ever be one instance; system instance must be destroyed by calling spinSystemReleaseInstance.
- [SPINNAKERC_API spinSystemReleaseInstance \(spinSystem hSystem\)](#)
Releases the system; make sure handle is cleaned up properly by setting it to NULL after system is released; the handle can only be used again after calling spinSystemGetInstance.
- [SPINNAKERC_API spinSystemGetInterfaces \(spinSystem hSystem, spinInterfaceList hInterfaceList\)](#)
Retrieves a list of detected (and enumerable) interfaces on the system; interface lists must be created and destroyed.
- [SPINNAKERC_API spinSystemGetCameras \(spinSystem hSystem, spinCameraList hCameraList\)](#)
Retrieves a list of detected (and enumerable) cameras on the system; camera lists must be created and destroyed.
- [SPINNAKERC_API spinSystemGetCamerasEx \(spinSystem hSystem, bool8_t bUpdateInterfaces, bool8_t bUpdateCameras, spinCameraList hCameraList\)](#)
Retrieves a list of detected (and enumerable) cameras on the system; manually set whether to update the current interface and camera lists; camera lists must be created and destroyed.
- [SPINNAKERC_API spinSystemSetLoggingLevel \(spinSystem hSystem, spinnakerLogLevel logLevel\)](#)
Sets the logging level for all logging events on the system.
- [SPINNAKERC_API spinSystemGetLoggingLevel \(spinSystem hSystem, spinnakerLogLevel *pLogLevel\)](#)
Retrieves the logging level for all logging events on the system.
- [SPINNAKERC_API spinSystemRegisterLogEventHandler \(spinSystem hSystem, spinLogEventHandler hLogEventHandler\)](#)
Registers a logging event handler to the system (event handlers registered in this way must be unregistered)
- [SPINNAKERC_API spinSystemUnregisterLogEventHandler \(spinSystem hSystem, spinLogEventHandler hLogEventHandler\)](#)
Unregisters a selected logging event handler from the system.
- [SPINNAKERC_API spinSystemUnregisterAllLogEventHandlers \(spinSystem hSystem\)](#)
Unregisters all logging event handlers from the system.
- [SPINNAKERC_API spinSystemIsInUse \(spinSystem hSystem, bool8_t *pbIsInUse\)](#)
Checks whether a system is currently in use.
- [SPINNAKERC_API spinSystemRegisterDeviceArrivalEventHandler \(spinSystem hSystem, spinDeviceArrivalEventHandler hDeviceArrivalEventHandler\)](#)
Registers a device arrival event handler to every interface on the system (event handlers registered this way must be unregistered)
- [SPINNAKERC_API spinSystemRegisterDeviceRemovalEventHandler \(spinSystem hSystem, spinDeviceRemovalEventHandler hDeviceRemovalEventHandler\)](#)

Registers a device removal event handler to the system to every interface on the system (event handlers registered this way must be unregistered)

- [SPINNAKERC_API spinSystemUnregisterDeviceArrivalEventHandler](#) ([spinSystem](#) hSystem, [spinDeviceArrivalEventHandler](#) hDeviceArrivalEventHandler)

Unregisters a device arrival event handler from the system.

- [SPINNAKERC_API spinSystemUnregisterDeviceRemovalEventHandler](#) ([spinSystem](#) hSystem, [spinDeviceRemovalEventHandler](#) hDeviceRemovalEventHandler)

Unregisters a device removal event handler from the system.

- [SPINNAKERC_API spinSystemRegisterInterfaceEventHandler](#) ([spinSystem](#) hSystem, [spinInterfaceEventHandler](#) hInterfaceEventHandler)

Registers an interface event handler (device arrival and device removal) to every interface on the system (interface events registered this way must be unregistered) If new interfaces are detected by the system after [spinSystemRegisterInterfaceEventHandler\(\)](#) is called, those interfaces will be automatically registered with this event.

- [SPINNAKERC_API spinSystemUnregisterInterfaceEventHandler](#) ([spinSystem](#) hSystem, [spinInterfaceEventHandler](#) hInterfaceEventHandler)

Unregisters an interface event handler from the system.

- [SPINNAKERC_API spinSystemUpdateCameras](#) ([spinSystem](#) hSystem, [bool8_t](#) *pbChanged)

Updates the list of cameras on the system, informing whether there has been any changes.

- [SPINNAKERC_API spinSystemUpdateCamerasEx](#) ([spinSystem](#) hSystem, [bool8_t](#) bUpdateInterfaces, [bool8_t](#) *pbChanged)

Updates the list of cameras on the system, informing whether there has been any changes; manually set whether to update the current interface lists.

- [SPINNAKERC_API spinSystemSendActionCommand](#) ([spinSystem](#) hSystem, [size_t](#) iDeviceKey, [size_t](#) iGroupKey, [size_t](#) iGroupMask, [size_t](#) iActionTime, [size_t](#) *piResultSize, [actionCommandResult](#) results[])

Broadcast an Action Command to all devices on system.

- [SPINNAKERC_API spinSystemGetLibraryVersion](#) ([spinSystem](#) hSystem, [spinLibraryVersion](#) *hLibraryVersion)

Get current library version of Spinnaker.

- [SPINNAKERC_API spinSystemGetTLNodeMap](#) ([spinSystem](#) hSystem, [spinNodeMapHandle](#) *phNodeMap)

Retrieves the transport layer nodemap from the system.

4.8.1 Detailed Description

The functions in this section provide access to information, objects, and functionality of the system object.

This includes the system object, interface and camera lists, and interface and logging events.

4.8.2 Function Documentation

4.8.2.1 spinSystemGetCameras()

```
SPINNAKERC_API spinSystemGetCameras (
    spinSystem hSystem,
    spinCameraList hCameraList )
```

Retrieves a list of detected (and enumerable) cameras on the system; camera lists must be created and destroyed.

See also

```
spinCameraListCreateEmpty()
spinCameraListDestroy()
spinError
```


Parameters

<i>hSystem</i>	The system, from which the camera list is retrieved
<i>hCameraList</i>	The camera list to house the cameras from the system

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.8.2.2 `spinSystemGetCamerasEx()`

```
SPINNAKERC_API spinSystemGetCamerasEx (
    spinSystem hSystem,
    bool8_t bUpdateInterfaces,
    bool8_t bUpdateCameras,
    spinCameraList hCameraList )
```

Retrieves a list of detected (and enumerable) cameras on the system; manually set whether to update the current interface and camera lists; camera lists must be created and destroyed.

See also

[spinCameraListCreateEmpty\(\)](#)
[spinCameraListDestroy\(\)](#)
[spinError](#)

Parameters

<i>hSystem</i>	The system, from which the camera list is retrieved
<i>bUpdateInterfaces</i>	The boolean of whether to update the interface list
<i>bUpdateCameras</i>	The boolean of whether to update the camera list
<i>hCameraList</i>	The camera list to house the cameras from the system

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.8.2.3 `spinSystemGetInstance()`

```
SPINNAKERC_API spinSystemGetInstance (
    spinSystem * phSystem )
```

Retrieves an instance of the system object; the system is a singleton, so there will only ever be one instance; system instance must be destroyed by calling `spinSystemReleaseInstance`.

See also

[spinSystemReleaseInstance](#)

[spinError](#)

Parameters

<i>phSystem</i>	The system handle pointer in which the system instance is returned
-----------------	--

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.4 `spinSystemGetInterfaces()`

```
SPINNAKERC_API spinSystemGetInterfaces (
    spinSystem hSystem,
    spinInterfaceList hInterfaceList )
```

Retrieves a list of detected (and enumerable) interfaces on the system; interface lists must be created and destroyed.

See also

[spinInterfaceListCreateEmpty\(\)](#)
[spinInterfaceListDestroy\(\)](#)
[spinError](#)

Parameters

<i>hSystem</i>	The system, from which the interface list is retrieved
<i>hInterfaceList</i>	The interface list to house the interfaces from the system

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.5 `spinSystemGetLibraryVersion()`

```
SPINNAKERC_API spinSystemGetLibraryVersion (
    spinSystem hSystem,
    spinLibraryVersion * hLibraryVersion )
```

Get current library version of Spinnaker.

Returns

A struct containing the current version of Spinnaker(major, minor, type, build).

4.8.2.6 spinSystemGetLoggingLevel()

```
SPINNAKERC_API spinSystemGetLoggingLevel (
    spinSystem hSystem,
    spinnakerLogLevel * pLogLevel )
```

Retrieves the logging level for all logging events on the system.

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system, from which the logging level is retrieved
<i>logLevel</i>	The logging level enum pointer in which the current logging level is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.7 spinSystemGetTLNodeMap()

```
SPINNAKERC_API spinSystemGetTLNodeMap (
    spinSystem hSystem,
    spinNodeMapHandle * phNodeMap )
```

Retrieves the transport layer nodemap from the system.

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system handle.
<i>phNodeMap</i>	The nodemap handle pointer in which the transport layer system nodemap is returned.

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.8 spinSystemIsInUse()

```
SPINNAKERC_API spinSystemIsInUse (
    spinSystem hSystem,
    bool8_t * pbIsInUse )
```

Checks whether a system is currently in use.

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system to check
<i>pbIsInUse</i>	The boolean pointer to return whether the system is currently in use

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.9 spinSystemRegisterDeviceArrivalEventHandler()

```
SPINNAKERC_API spinSystemRegisterDeviceArrivalEventHandler (
    spinSystem hSystem,
    spinDeviceArrivalEventHandler hDeviceArrivalEventHandler )
```

Registers a device arrival event handler to every interface on the system (event handlers registered this way must be unregistered)

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system, on which the device arrival event handler is registered
<i>hDeviceArrivalEventHandler</i>	The device arrival event handler to register on the system

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.10 spinSystemRegisterDeviceRemovalEventHandler()

```
SPINNAKERC_API spinSystemRegisterDeviceRemovalEventHandler (
    spinSystem hSystem,
    spinDeviceRemovalEventHandler hDeviceRemovalEventHandler )
```

Registers a device removal event handler to the system to every interface on the system (event handlers registered this way must be unregistered)

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system, on which the device removal event handler is registered
<i>hDeviceRemovalEventHandler</i>	The device removal event handler to register on the system

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.11 spinSystemRegisterInterfaceEventHandler()

```
SPINNAKERC_API spinSystemRegisterInterfaceEventHandler (
    spinSystem hSystem,
    spinInterfaceEventHandler hInterfaceEventHandler )
```

Registers an interface event handler (device arrival and device removal) to every interface on the system (interface events registered this way must be unregistered) If new interfaces are detected by the system after [spinSystemRegisterInterfaceEventHandler\(\)](#) is called, those interfaces will be automatically registered with this event.

See also

[spinError](#)
[spinInterfaceEventHandler](#)

Parameters

<i>hSystem</i>	The system, on which the interface event handler is registered
<i>hInterfaceEventHandler</i>	The interface event handler (device arrival and device removal) to register on the system

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.12 spinSystemRegisterLogEventHandler()

```
SPINNAKERC_API spinSystemRegisterLogEventHandler (
    spinSystem hSystem,
    spinLogEventHandler hLogEventHandler )
```

Registers a logging event handler to the system (event handlers registered in this way must be unregistered)

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system, on which the logging event handler is registered
<i>hLogEventHandler</i>	The logging event handler to register on the system

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.13 spinSystemReleaseInstance()

```
SPINNAKERC_API spinSystemReleaseInstance (
    spinSystem hSystem )
```

Releases the system; make sure handle is cleaned up properly by setting it to NULL after system is released; the handle can only be used again after calling spinSystemGetInstance.

See also

[spinSystemGetInstance](#)
[spinError](#)

Parameters

<i>hSystem</i>	The system handle
----------------	-------------------

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.14 spinSystemSendActionCommand()

```
SPINNAKERC_API spinSystemSendActionCommand (
    spinSystem hSystem,
```

```

size_t iDeviceKey,
size_t iGroupKey,
size_t iGroupMask,
size_t iActionTime,
size_t * piResultSize,
actionCommandResult results[] )

```

Broadcast an Action Command to all devices on system.

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system on which to send the action command to all devices.
<i>iDeviceKey</i>	The Action Command's device key
<i>iGroupKey</i>	The Action Command's group key
<i>iGroupMask</i>	The Action Command's group mask
<i>iActionTime</i>	(Optional) Time when to assert a future action. Zero means immediate action.
<i>piResultSize</i>	(Optional) The number of results in the results array. The value passed should be equal to the expected number of devices that acknowledge the command. Returns the number of received results.
<i>results</i>	(Optional) An Array with *piResultSize elements to hold the action command result status. The buffer is filled starting from index 0. If received results are less than expected number of devices that acknowledge the command, remaining results are not changed. If received results are more than expected number of devices that acknowledge the command, extra results are ignored and not appended to array. This parameter is ignored if piResultSize is 0. Thus this parameter can be NULL if pResultSize is 0 or NULL.

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.15 spinSystemSetLoggingLevel()

```

SPINNAKERC_API spinSystemSetLoggingLevel (
    spinSystem hSystem,
    spinnakerLogLevel logLevel )

```

Sets the logging level for all logging events on the system.

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system, on which the logging level is set
<i>logLevel</i>	The logging level to set

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.8.2.16 `spinSystemUnregisterAllLogEventHandlers()`

```
SPINNAKERC_API spinSystemUnregisterAllLogEventHandlers (
    spinSystem hSystem )
```

Unregisters all logging event handlers from the system.

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system, from which all logging event handlers are unregistered
----------------	--

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.8.2.17 `spinSystemUnregisterDeviceArrivalEventHandler()`

```
SPINNAKERC_API spinSystemUnregisterDeviceArrivalEventHandler (
    spinSystem hSystem,
    spinDeviceArrivalEventHandler hDeviceArrivalEventHandler )
```

Unregisters a device arrival event handler from the system.

See also

[spinError](#)
[spinDeviceArrivalEventHandler](#)

Parameters

<i>hSystem</i>	The system, from which the device arrival event handler is unregistered
<i>hDeviceArrivalEventHandler</i>	The device arrival event handler to unregister from the system

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.8.2.18 spinSystemUnregisterDeviceRemovalEventHandler()

```
SPINNAKERC_API spinSystemUnregisterDeviceRemovalEventHandler (
    spinSystem hSystem,
    spinDeviceRemovalEventHandler hDeviceRemovalEventHandler )
```

Unregisters a device removal event handler from the system.

See also

[spinError](#)
[spinDeviceRemovalEventHandler](#)

Parameters

<i>hSystem</i>	The system, from which the device removal event handler is unregistered
<i>hDeviceRemovalEventHandler</i>	The device removal event handler to unregister from the system

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.19 spinSystemUnregisterInterfaceEventHandler()

```
SPINNAKERC_API spinSystemUnregisterInterfaceEventHandler (
    spinSystem hSystem,
    spinInterfaceEventHandler hInterfaceEventHandler )
```

Unregisters an interface event handler from the system.

See also

[spinError](#)
[spinInterfaceEventHandler](#)

Parameters

<i>hSystem</i>	The system, from which the interface event handler is unregistered
<i>hInterfaceEventHandler</i>	The interface event handler (device arrival and device removal) to unregister from the system

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.20 spinSystemUnregisterLogEventHandler()

```
SPINNAKERC_API spinSystemUnregisterLogEventHandler (
    spinSystem hSystem,
    spinLogEventHandler hLogEventHandler )
```

Unregisters a selected logging event handler from the system.

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system, from which the logging event handler is unregistered
<i>hLogEventHandler</i>	The logging event handler to unregister from the system

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.21 spinSystemUpdateCameras()

```
SPINNAKERC_API spinSystemUpdateCameras (
    spinSystem hSystem,
    bool8_t * pbChanged )
```

Updates the list of cameras on the system, informing whether there has been any changes.

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system, on which the list of attached cameras is updated
<i>pbChanged</i>	The boolean pointer to return whether cameras have arrived on or been removed from the system

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.8.2.22 spinSystemUpdateCamerasEx()

```
SPINNAKERC_API spinSystemUpdateCamerasEx (
    spinSystem hSystem,
```

```
bool8_t bUpdateInterfaces,  
bool8_t * pbChanged )
```

Updates the list of cameras on the system, informing whether there has been any changes; manually set whether to update the current interface lists.

See also

[spinError](#)

Parameters

<i>hSystem</i>	The system, on which the list of attached cameras is updated
<i>bUpdateInterfaces</i>	The boolean of whether to update the interface list
<i>pbChanged</i>	The boolean pointer to return whether cameras have arrived or been removed from the system


Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.9 InterfaceList Access

The functions in this section provide access to information, objects, and functionality of interface lists.

Collaboration diagram for InterfaceList Access:



Functions

- [SPINNAKERC_API spinInterfaceListCreateEmpty](#) ([spinInterfaceList](#) *phInterfaceList)
Creates an empty interface list (interface lists created this way must be destroyed)
- [SPINNAKERC_API spinInterfaceListDestroy](#) ([spinInterfaceList](#) hInterfaceList)
Destroys an interface list.
- [SPINNAKERC_API spinInterfaceListGetSize](#) ([spinInterfaceList](#) hInterfaceList, [size_t](#) *pSize)
Retrieves the number of interfaces in an interface list.
- [SPINNAKERC_API spinInterfaceListGet](#) ([spinInterfaceList](#) hInterfaceList, [size_t](#) index, [spinInterface](#) *ph↔
Interface)
Retrieves an interface from an interface list using an index (interfaces retrieved this way must be released)
- [SPINNAKERC_API spinInterfaceListClear](#) ([spinInterfaceList](#) hInterfaceList)
Clears an interface list.

4.9.1 Detailed Description

The functions in this section provide access to information, objects, and functionality of interface lists.

This includes updating, size and interface retrieval, and clearance.

4.9.2 Function Documentation

4.9.2.1 spinInterfaceListClear()

```
SPINNAKERC_API spinInterfaceListClear (
    spinInterfaceList hInterfaceList )
```

Clears an interface list.

See also

[spinError](#)

Parameters

<i>hInterfaceList</i>	The interface list to clear
-----------------------	-----------------------------

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.9.2.2 spinInterfaceListCreateEmpty()

```
SPINNAKERC_API spinInterfaceListCreateEmpty (  
    spinInterfaceList * phInterfaceList )
```

Creates an empty interface list (interface lists created this way must be destroyed)

See also

[spinError](#)

Parameters

<i>phInterfaceList</i>	The interface list handle pointer in which the empty interface list is returned
------------------------	---

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.9.2.3 spinInterfaceListDestroy()

```
SPINNAKERC_API spinInterfaceListDestroy (  
    spinInterfaceList hInterfaceList )
```

Destroys an interface list.

See also

[spinError](#)

Parameters

<i>hInterfaceList</i>	The interface list to destroy
-----------------------	-------------------------------

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.9.2.4 spinInterfaceListGet()

```
SPINNAKERC_API spinInterfaceListGet (
    spinInterfaceList hInterfaceList,
    size_t index,
    spinInterface * phInterface )
```

Retrieves an interface from an interface list using an index (interfaces retrieved this way must be released)

See also

[spinError](#)

Parameters

<i>hInterfaceList</i>	The interface list of the interface to be retrieved
<i>index</i>	The index of the interface
<i>phInterface</i>	The interface handle pointer in which the interface is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.9.2.5 spinInterfaceListGetSize()

```
SPINNAKERC_API spinInterfaceListGetSize (
    spinInterfaceList hInterfaceList,
    size_t * pSize )
```

Retrieves the number of interfaces in an interface list.

See also

[spinError](#)

Parameters

<i>hInterfaceList</i>	The interface list where the interfaces to be counted are
<i>pSize</i>	The unsigned integer pointer in which the number of interfaces is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error


See also

[spinError](#)

4.10 CameraList Access

The functions in this section provide access to information, objects, and functionality of camera lists.

Collaboration diagram for CameraList Access:



Functions

- [SPINNAKERC_API spinCameraListCreateEmpty](#) ([spinCameraList](#) *phCameraList)
Creates an empty camera list (camera lists created this way must be destroyed)
- [SPINNAKERC_API spinCameraListDestroy](#) ([spinCameraList](#) hCameraList)
Destroys a camera list.
- [SPINNAKERC_API spinCameraListGetSize](#) ([spinCameraList](#) hCameraList, [size_t](#) *pSize)
Retrieves the number of cameras on a camera list.
- [SPINNAKERC_API spinCameraListGet](#) ([spinCameraList](#) hCameraList, [size_t](#) index, [spinCamera](#) *phCamera)
Retrieves a camera from a camera list using an index.
- [SPINNAKERC_API spinCameraListClear](#) ([spinCameraList](#) hCameraList)
Clears a camera list.
- [SPINNAKERC_API spinCameraListRemove](#) ([spinCameraList](#) hCameraList, [size_t](#) index)
Removes a camera from a camera list using its index.
- [SPINNAKERC_API spinCameraListAppend](#) ([spinCameraList](#) hCameraListBase, [spinCameraList](#) hCameraListToAppend)
Appends all the cameras from one camera list to another.
- [SPINNAKERC_API spinCameraListGetBySerial](#) ([spinCameraList](#) hCameraList, [const char](#) *pSerial, [spinCamera](#) *phCamera)
Retrieves a camera from a camera list using its serial number.
- [SPINNAKERC_API spinCameraListRemoveBySerial](#) ([spinCameraList](#) hCameraList, [const char](#) *pSerial)
Removes a camera from a camera list using its serial number.

4.10.1 Detailed Description

The functions in this section provide access to information, objects, and functionality of camera lists.

This includes updating, size and camera retrieval, and clearance.

4.10.2 Function Documentation

4.10.2.1 spinCameraListAppend()

```
SPINNAKERC_API spinCameraListAppend (
    spinCameraList hCameraListBase,
    spinCameraList hCameraListToAppend )
```

Appends all the cameras from one camera list to another.

See also

[spinError](#)

Parameters

<i>hCameraListBase</i>	The camera list to receive the other
<i>hCameraListToAppend</i>	The camera list to add to the other

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.10.2.2 spinCameraListClear()

```
SPINNAKERC_API spinCameraListClear (
    spinCameraList hCameraList )
```

Clears a camera list.

See also

[spinError](#)

Parameters

<i>hCameraList</i>	The camera list to clear
--------------------	--------------------------

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.10.2.3 spinCameraListCreateEmpty()

```
SPINNAKERC_API spinCameraListCreateEmpty (
    spinCameraList * phCameraList )
```

Creates an empty camera list (camera lists created this way must be destroyed)

See also

[spinError](#)

Parameters

<i>phCameraList</i>	The camera list handle pointer in which the empty camera list is returned
---------------------	---

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.10.2.4 spinCameraListDestroy()

```
SPINNAKERC_API spinCameraListDestroy (
    spinCameraList hCameraList )
```

Destroys a camera list.

See also

[spinError](#)

Parameters

<i>hCameraList</i>	The camera list to destroy
--------------------	----------------------------

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.10.2.5 spinCameraListGet()

```
SPINNAKERC_API spinCameraListGet (
    spinCameraList hCameraList,
    size_t index,
    spinCamera * phCamera )
```

Retrieves a camera from a camera list using an index.

This function will return a SPINNAKER_ERR_INVALID_PARAMETER error if the input index is out of range.

See also

[spinError](#)

Parameters

<i>hCameraList</i>	The camera list of the camera to retrieve
<i>index</i>	The index of the camera
<i>phCamera</i>	The camera handle pointer in which the camera is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.10.2.6 spinCameraListGetBySerial()

```
SPINNAKERC_API spinCameraListGetBySerial (
    spinCameraList hCameraList,
    const char * pSerial,
    spinCamera * phCamera )
```

Retrieves a camera from a camera list using its serial number.

This function will return a NULL `spinCamera` pointer if no matching camera serial is found.

See also

[spinError](#)

Parameters

<i>hCameraList</i>	The camera list of the camera to retrieve
<i>serial</i>	The serial number of the camera to retrieve
<i>phCamera</i>	The camera handle pointer in which the camera is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.10.2.7 spinCameraListGetSize()

```
SPINNAKERC_API spinCameraListGetSize (
    spinCameraList hCameraList,
    size_t * pSize )
```

Retrieves the number of cameras on a camera list.

See also

[spinError](#)

Parameters

<i>hCameraList</i>	The camera list where the cameras to be counted are
<i>pSize</i>	The unsigned integer pointer in which the number of cameras is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.10.2.8 `spinCameraListRemove()`

```
SPINNAKERC_API spinCameraListRemove (
    spinCameraList hCameraList,
    size_t index )
```

Removes a camera from a camera list using its index.

See also

[spinError](#)

Parameters

<i>hCameraList</i>	The camera list of the camera to remove
<i>index</i>	The index of the camera to remove

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.10.2.9 `spinCameraListRemoveBySerial()`

```
SPINNAKERC_API spinCameraListRemoveBySerial (
    spinCameraList hCameraList,
    const char * pSerial )
```

Removes a camera from a camera list using its serial number.

See also

[spinError](#)

Parameters

<i>hCameraList</i>	The camera of the camera to remove
<i>pSerial</i>	The serial number of the camera to remove

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.11 Interface Access

The functions in this section provide access to information, objects, and functionality of interfaces.

Collaboration diagram for Interface Access:



Functions

- **SPINNAKERC_API spinInterfaceUpdateCameras** ([spinInterface](#) hInterface, [bool8_t](#) *pbChanged)
Checks whether any cameras have been connected or disconnected on an interface.
- **SPINNAKERC_API spinInterfaceGetCameras** ([spinInterface](#) hInterface, [spinCameraList](#) hCameraList)
Retrieves a camera list from an interface; camera lists must be created and destroy.
- **SPINNAKERC_API spinInterfaceGetCamerasEx** ([spinInterface](#) hInterface, [bool8_t](#) bUpdateCameras, [spinCameraList](#) hCameraList)
Retrieves a camera list from an interface; manually set whether to update the cameras; camera lists must be created and destroyed.
- **SPINNAKERC_API spinInterfaceGetTLNodeMap** ([spinInterface](#) hInterface, [spinNodeMapHandle](#) *phNodeMap)
Retrieves the transport layer nodemap from an interface.
- **SPINNAKERC_API spinInterfaceRegisterDeviceArrivalEventHandler** ([spinInterface](#) hInterface, [spinDeviceArrivalEventHandler](#) hDeviceArrivalEventHandler)
Registers a device arrival event handler on an interface (event handlers registered in this way must be unregistered)
- **SPINNAKERC_API spinInterfaceRegisterDeviceRemovalEventHandler** ([spinInterface](#) hInterface, [spinDeviceRemovalEventHandler](#) hDeviceRemovalEventHandler)
Registers a device removal event handler on an interface (event handlers registered in this way must be unregistered)
- **SPINNAKERC_API spinInterfaceUnregisterDeviceArrivalEventHandler** ([spinInterface](#) hInterface, [spinDeviceArrivalEventHandler](#) hDeviceArrivalEventHandler)
Unregisters a device arrival event handler from an interface.
- **SPINNAKERC_API spinInterfaceUnregisterDeviceRemovalEventHandler** ([spinInterface](#) hInterface, [spinDeviceRemovalEventHandler](#) hDeviceRemovalEventHandler)
Unregisters a device removal event handler from an interface.
- **SPINNAKERC_API spinInterfaceRegisterInterfaceEventHandler** ([spinInterface](#) hInterface, [spinInterfaceEventHandler](#) hInterfaceEventHandler)
Registers an interface event handler (both device arrival and device removal) on an interface.
- **SPINNAKERC_API spinInterfaceUnregisterInterfaceEventHandler** ([spinInterface](#) hInterface, [spinInterfaceEventHandler](#) hInterfaceEventHandler)
Unregisters an interface event handler from an interface.
- **SPINNAKERC_API spinInterfaceRelease** ([spinInterface](#) hInterface)
Releases an interface.
- **SPINNAKERC_API spinInterfaceIsInUse** ([spinInterface](#) hInterface, [bool8_t](#) *pbIsInUse)
Checks whether an interface is in use.
- **SPINNAKERC_API spinInterfaceSendActionCommand** ([spinInterface](#) hInterface, [size_t](#) iDeviceKey, [size_t](#) iGroupKey, [size_t](#) iGroupMask, [size_t](#) iActionTime, [size_t](#) *piResultSize, [actionCommandResult](#) results[])
Broadcast an Action Command to all devices on interface.

4.11.1 Detailed Description

The functions in this section provide access to information, objects, and functionality of interfaces.

This includes camera list and nodemap retrieval, event handler registration, and interface release.

4.11.2 Function Documentation

4.11.2.1 spinInterfaceGetCameras()

```
SPINNAKERC_API spinInterfaceGetCameras (
    spinInterface hInterface,
    spinCameraList hCameraList )
```

Retrieves a camera list from an interface; camera lists must be created and destroy.

See also

[spinCameraListCreateEmpty\(\)](#)
[spinCameraListDestroy\(\)](#)
[spinError](#)

Parameters

<i>hInterface</i>	The interface of the camera list to retrieve
<i>hCameraList</i>	The camera list to house the cameras from the interface

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.11.2.2 spinInterfaceGetCamerasEx()

```
SPINNAKERC_API spinInterfaceGetCamerasEx (
    spinInterface hInterface,
    bool8_t bUpdateCameras,
    spinCameraList hCameraList )
```

Retrieves a camera list from an interface; manually set whether to update the cameras; camera lists must be created and destroyed.

See also

[spinCameraListCreateEmpty\(\)](#)
[spinCameraListDestroy\(\)](#)
[spinError](#)

Parameters

<i>hInterface</i>	The interface of the camera list to retrieve
<i>bUpdateCameras</i>	The boolean of whether or not to update the cameras
<i>hCameraList</i>	The camera list to house the cameras from the interface

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.3 `spinInterfaceGetTLNodeMap()`

```
SPINNAKERC_API spinInterfaceGetTLNodeMap (
    spinInterface hInterface,
    spinNodeMapHandle * phNodeMap )
```

Retrieves the transport layer nodemap from an interface.

See also

[spinError](#)

Parameters

<i>hInterface</i>	The interface of the nodemap to retrieve
<i>phNodeMap</i>	The nodemap handle pointer in which the transport layer interface nodemap is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.4 `spinInterfaceIsInUse()`

```
SPINNAKERC_API spinInterfaceIsInUse (
    spinInterface hInterface,
    bool8_t * pbIsInUse )
```

Checks whether an interface is in use.

See also

[spinError](#)

Parameters

<i>hInterface</i>	The interface to check
<i>pblsInUse</i>	The boolean pointer to return whether or not the interface is in use

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.5 `spinInterfaceRegisterDeviceArrivalEventHandler()`

```
SPINNAKERC_API spinInterfaceRegisterDeviceArrivalEventHandler (
    spinInterface hInterface,
    spinDeviceArrivalEventHandler hDeviceArrivalEventHandler )
```

Registers a device arrival event handler on an interface (event handlers registered in this way must be unregistered)

See also

[spinError](#)

Parameters

<i>hInterface</i>	The interface on which to register the device arrival event handler
<i>hDeviceArrivalEventHandler</i>	The device arrival event handler to register

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.6 `spinInterfaceRegisterDeviceRemovalEventHandler()`

```
SPINNAKERC_API spinInterfaceRegisterDeviceRemovalEventHandler (
    spinInterface hInterface,
    spinDeviceRemovalEventHandler hDeviceRemovalEventHandler )
```

Registers a device removal event handler on an interface (event handlers registered in this way must be unregistered)

See also

[spinError](#)

Parameters

<i>hInterface</i>	the Interface on which to register the device removal event handler
<i>hDeviceRemovalEventHandler</i>	The device removal event handler to register

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.7 `spinInterfaceRegisterInterfaceEventHandler()`

```
SPINNAKERC_API spinInterfaceRegisterInterfaceEventHandler (
    spinInterface hInterface,
    spinInterfaceEventHandler hInterfaceEventHandler )
```

Registers an interface event handler (both device arrival and device removal) on an interface.

See also

[`spinError`](#)

Parameters

<i>hInterface</i>	The interface on which to register the interface event handler
<i>hInterfaceEventHandler</i>	The interface event handler to register

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.8 `spinInterfaceRelease()`

```
SPINNAKERC_API spinInterfaceRelease (
    spinInterface hInterface )
```

Releases an interface.

See also

[`spinError`](#)

Parameters

<i>hInterface</i>	The interface to release
-------------------	--------------------------

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.9 spinInterfaceSendActionCommand()

```
SPINNAKERC_API spinInterfaceSendActionCommand (
    spinInterface hInterface,
    size_t iDeviceKey,
    size_t iGroupKey,
    size_t iGroupMask,
    size_t iActionTime,
    size_t * piResultSize,
    actionCommandResult results[] )
```

Broadcast an Action Command to all devices on interface.

See also

[spinError](#)

Parameters

<i>iDeviceKey</i>	The Action Command's device key
<i>iGroupKey</i>	The Action Command's group key
<i>iGroupMask</i>	The Action Command's group mask
<i>iActionTime</i>	(Optional) Time when to assert a future action. Zero means immediate action.
<i>piResultSize</i>	(Optional) The number of results in the results array. The value passed should be equal to the expected number of devices that acknowledge the command. Returns the number of received results.
<i>results</i>	(Optional) An Array with *piResultSize elements to hold the action command result status. The buffer is filled starting from index 0. If received results are less than expected number of devices that acknowledge the command, remaining results are not changed. If received results are more than expected number of devices that acknowledge the command, extra results are ignored and not appended to array. This parameter is ignored if piResultSize is 0. Thus this parameter can be NULL if pResultSize is 0 or NULL.

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.10 spinInterfaceUnregisterDeviceArrivalEventHandler()

```
SPINNAKERC_API spinInterfaceUnregisterDeviceArrivalEventHandler (
    spinInterface hInterface,
    spinDeviceArrivalEventHandler hDeviceArrivalEventHandler )
```

Unregisters a device arrival event handler from an interface.

See also

[spinError](#)

Parameters

<i>hInterface</i>	The interface from which to unregister the device arrival event handler
<i>hDeviceArrivalEventHandler</i>	The device arrival event handler to unregister

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.11 `spinInterfaceUnregisterDeviceRemovalEventHandler()`

```
SPINNAKERC_API spinInterfaceUnregisterDeviceRemovalEventHandler (  
    spinInterface hInterface,  
    spinDeviceRemovalEventHandler hDeviceRemovalEventHandler )
```

Unregisters a device removal event handler from an interface.

See also

[spinError](#)

Parameters

<i>hInterface</i>	The interface from which to unregister the device removal event handler
<i>hDeviceRemovalEventHandler</i>	The device removal event handler to unregister

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.12 `spinInterfaceUnregisterInterfaceEventHandler()`

```
SPINNAKERC_API spinInterfaceUnregisterInterfaceEventHandler (  
    spinInterface hInterface,  
    spinInterfaceEventHandler hInterfaceEventHandler )
```

Unregisters an interface event handler from an interface.

See also

[spinError](#)

Parameters

<i>hInterface</i>	The interface from which to unregister the interface event handler
<i>hInterfaceEventHandler</i>	The interface event handler to unregister

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.11.2.13 `spinInterfaceUpdateCameras()`

```
SPINNAKERC_API spinInterfaceUpdateCameras (
    spinInterface hInterface,
    bool8_t * pbChanged )
```

Checks whether any cameras have been connected or disconnected on an interface.

See also

[`spinError`](#)

Parameters

<i>hInterface</i>	The interface of the list of attached cameras to update
<i>pbChanged</i>	The boolean pointer to return whether or not the cameras have changed


Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12 Camera Access

The functions in this section provide access to information, objects, and functionality of cameras.

Collaboration diagram for Camera Access:



Functions

- [SPINNAKERC_API spinCameraInit \(spinCamera hCamera\)](#)
Initializes a camera, allowing for much more interaction.
- [SPINNAKERC_API spinCameraDeInit \(spinCamera hCamera\)](#)
Deinitializes a camera, greatly reducing functionality.
- [SPINNAKERC_API spinCameraGetNodeMap \(spinCamera hCamera, spinNodeMapHandle *phNodeMap\)](#)
Retrieves the GenICam nodemap from a camera.
- [SPINNAKERC_API spinCameraGetTLDeviceNodeMap \(spinCamera hCamera, spinNodeMapHandle *phNodeMap\)](#)
Retrieves the transport layer device nodemap from a camera.
- [SPINNAKERC_API spinCameraGetTLStreamNodeMap \(spinCamera hCamera, spinNodeMapHandle *phNodeMap\)](#)
Retrieves the transport layer stream nodemap from a camera.
- [SPINNAKERC_API spinCameraGetAccessMode \(spinCamera hCamera, spinAccessMode *pAccessMode\)](#)
Retrieves the access mode of a camera (as an enum, spinAccessMode)
- [SPINNAKERC_API spinCameraReadPort \(spinCamera hCamera, uint64_t iAddress, void *pBuffer, size_t iSize\)](#)
- [SPINNAKERC_API spinCameraWritePort \(spinCamera hCamera, uint64_t iAddress, void *pBuffer, size_t iSize\)](#)
- [SPINNAKERC_API spinCameraBeginAcquisition \(spinCamera hCamera\)](#)
Has a camera start acquiring images.
- [SPINNAKERC_API spinCameraEndAcquisition \(spinCamera hCamera\)](#)
Has a camera stop acquiring images.
- [SPINNAKERC_API spinCameraGetNextImage \(spinCamera hCamera, spinImage *phImage\)](#)
Retrieves an image from a camera.
- [SPINNAKERC_API spinCameraGetNextImageEx \(spinCamera hCamera, uint64_t grabTimeout, spinImage *phImage\)](#)
Retrieves an image from a camera; manually set the timeout in milliseconds.
- [SPINNAKERC_API spinCameraGetUniqueID \(spinCamera hCamera, char *pBuf, size_t *pBufLen\)](#)
Retrieves a unique identifier for a camera.
- [SPINNAKERC_API spinCameraIsStreaming \(spinCamera hCamera, bool8_t *pIsStreaming\)](#)
Checks whether a camera is currently acquiring images.
- [SPINNAKERC_API spinCameraGetGuiXml \(spinCamera hCamera, char *pBuf, size_t *pBufLen\)](#)
Retrieves the GUI XML from a camera.

- [SPINNAKERC_API spinCameraRegisterDeviceEventHandler](#) ([spinCamera](#) hCamera, [spinDeviceEvent↵Handler](#) hDeviceEventHandler)
Registers a universal device event handler (every device event type) to a camera.
- [SPINNAKERC_API spinCameraRegisterDeviceEventHandlerEx](#) ([spinCamera](#) hCamera, [spinDeviceEvent↵Handler](#) hDeviceEventHandler, const char *pName)
Registers a specific device event handler (only one device event type) to a camera.
- [SPINNAKERC_API spinCameraUnregisterDeviceEventHandler](#) ([spinCamera](#) hCamera, [spinDeviceEvent↵Handler](#) hDeviceEventHandler)
Unregisters a device event handler from a camera.
- [SPINNAKERC_API spinCameraRegisterImageEventHandler](#) ([spinCamera](#) hCamera, [spinImageEvent↵Handler](#) hImageEventHandler)
Registers an image event handler to a camera.
- [SPINNAKERC_API spinCameraUnregisterImageEventHandler](#) ([spinCamera](#) hCamera, [spinImageEvent↵Handler](#) hImageEventHandler)
Unregisters an image event handler from a camera.
- [SPINNAKERC_API spinCameraRelease](#) ([spinCamera](#) hCamera)
Releases a camera.
- [SPINNAKERC_API spinCamerasValid](#) ([spinCamera](#) hCamera, [bool8_t](#) *pbValid)
Checks whether a camera is still valid for use.
- [SPINNAKERC_API spinCamerasInitialized](#) ([spinCamera](#) hCamera, [bool8_t](#) *pbInit)
Checks whether a camera is currently initialized.

4.12.1 Detailed Description

The functions in this section provide access to information, objects, and functionality of cameras.

This includes nodemap retrieval, acquisition and init commands, event handler registration, and camera property retrieval.

4.12.2 Function Documentation

4.12.2.1 spinCameraBeginAcquisition()

```
SPINNAKERC_API spinCameraBeginAcquisition (
    spinCamera hCamera )
```

Has a camera start acquiring images.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera to begin acquiring images
----------------	--------------------------------------

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.2 `spinCameraDeInit()`

```
SPINNAKERC_API spinCameraDeInit (  
    spinCamera hCamera )
```

Deinitializes a camera, greatly reducing functionality.

See also

[spinError](#)

Parameters

<code>hCamera</code>	The camera to deinitialize
----------------------	----------------------------

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.3 `spinCameraEndAcquisition()`

```
SPINNAKERC_API spinCameraEndAcquisition (  
    spinCamera hCamera )
```

Has a camera stop acquiring images.

See also

[spinError](#)

Parameters

<code>hCamera</code>	The camera to stop acquiring images
----------------------	-------------------------------------

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.4 spinCameraGetAccessMode()

```
SPINNAKERC_API spinCameraGetAccessMode (
    spinCamera hCamera,
    spinAccessMode * pAccessMode )
```

Retrieves the access mode of a camera (as an enum, spinAccessMode)

See also

[spinError](#)
[spinAccessMode](#)

Parameters

<i>hCamera</i>	The camera of the access mode to retrieve
<i>pAccessMode</i>	The access mode enum pointer in which the access mode is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.5 spinCameraGetGuiXml()

```
SPINNAKERC_API spinCameraGetGuiXml (
    spinCamera hCamera,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the GUI XML from a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera of the GUI XML to retrieve
<i>pBuf</i>	The c-string character buffer in which the GUI XML is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.6 `spinCameraGetNextImage()`

```
SPINNAKERC_API spinCameraGetNextImage (
    spinCamera hCamera,
    spinImage * phImage )
```

Retrieves an image from a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera of the image to retrieve
<i>phImage</i>	The image handle pointer in which the image is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.7 `spinCameraGetNextImageEx()`

```
SPINNAKERC_API spinCameraGetNextImageEx (
    spinCamera hCamera,
    uint64_t grabTimeout,
    spinImage * phImage )
```

Retrieves an image from a camera; manually set the timeout in milliseconds.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera of the image to retrieve
<i>grabTimeout</i>	The timeout value for returned an image
<i>phImage</i>	The image handle pointer in which the image is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.8 spinCameraGetNodeMap()

```
SPINNAKERC_API spinCameraGetNodeMap (
    spinCamera hCamera,
    spinNodeMapHandle * phNodeMap )
```

Retrieves the GenICam nodemap from a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera from which the nodemap is retrieved
<i>phNodeMap</i>	The nodemap handle pointer in which the nodemap is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.9 spinCameraGetTLDeviceNodeMap()

```
SPINNAKERC_API spinCameraGetTLDeviceNodeMap (
    spinCamera hCamera,
    spinNodeMapHandle * phNodeMap )
```

Retrieves the transport layer device nodemap from a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera from which the transport layer device nodemap is retrieved
<i>phNodeMap</i>	The nodemap handle pointer in which the nodemap is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.10 `spinCameraGetTLStreamNodeMap()`

```
SPINNAKERC_API spinCameraGetTLStreamNodeMap (
    spinCamera hCamera,
    spinNodeMapHandle * phNodeMap )
```

Retrieves the transport layer stream nodemap from a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera from which the transport layer streaming nodemap is retrieved
<i>phNodeMap</i>	The nodemap handle pointer in which the nodemap is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.11 `spinCameraGetUniqueID()`

```
SPINNAKERC_API spinCameraGetUniqueID (
    spinCamera hCamera,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves a unique identifier for a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera of the unique identifier
<i>pBuf</i>	The c-string character buffer in which the unique identifier is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.12 spinCameraInit()

```
SPINNAKERC_API spinCameraInit (
    spinCamera hCamera )
```

Initializes a camera, allowing for much more interaction.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera to initialize
----------------	--------------------------

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.13 spinCameraIsInitialized()

```
SPINNAKERC_API spinCameraIsInitialized (
    spinCamera hCamera,
    bool8_t * pbInit )
```

Checks whether a camera is currently initialized.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera to check
<i>pbInit</i>	The boolean pointer to return whether or not the camera is initialized

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.14 spinCameraIsStreaming()

```
SPINNAKERC_API spinCameraIsStreaming (
    spinCamera hCamera,
    bool8_t * pbIsStreaming )
```

Checks whether a camera is currently acquiring images.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera to check
<i>pbIsStreaming</i>	The boolean pointer to return whether or not the camera is currently streaming

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.15 `spinCamerasValid()`

```
SPINNAKERC_API spinCameraIsValid (  
    spinCamera hCamera,  
    bool8_t * pbValid )
```

Checks whether a camera is still valid for use.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera to check
<i>pbValid</i>	The boolean pointer to return whether or not the camera is valid

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.16 `spinCameraReadPort()`

```
SPINNAKERC_API spinCameraReadPort (  
    spinCamera hCamera,  
    uint64_t iAddress,  
    void * pBuffer,  
    size_t iSize )
```

4.12.2.17 spinCameraRegisterDeviceEventHandler()

```
SPINNAKERC_API spinCameraRegisterDeviceEventHandler (
    spinCamera hCamera,
    spinDeviceEventHandler hDeviceEventHandler )
```

Registers a universal device event handler (every device event type) to a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera on which to register the universal device event handler
<i>hDeviceEventHandler</i>	The device event handler to register

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.18 spinCameraRegisterDeviceEventHandlerEx()

```
SPINNAKERC_API spinCameraRegisterDeviceEventHandlerEx (
    spinCamera hCamera,
    spinDeviceEventHandler hDeviceEventHandler,
    const char * pName )
```

Registers a specific device event handler (only one device event type) to a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera on which to register the specific device event handler
<i>hDeviceEventHandler</i>	The device event handler to register
<i>pName</i>	The name of the device event handler to register

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.19 spinCameraRegisterImageEventHandler()

```
SPINNAKERC_API spinCameraRegisterImageEventHandler (
    spinCamera hCamera,
    spinImageEventHandler hImageEventHandler )
```

Registers an image event handler to a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera on which to register the image event handler
<i>hImageEventHandler</i>	The image event handler to register

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.20 spinCameraRelease()

```
SPINNAKERC_API spinCameraRelease (
    spinCamera hCamera )
```

Releases a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera to release
----------------	-----------------------

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.12.2.21 spinCameraUnregisterDeviceEventHandler()

```
SPINNAKERC_API spinCameraUnregisterDeviceEventHandler (
    spinCamera hCamera,
    spinDeviceEventHandler hDeviceEventHandler )
```

Unregisters a device event handler from a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera from which to unregister the device event handler
<i>hDeviceEventHandler</i>	The device event handler to unregister

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.22 `spinCameraUnregisterImageEventHandler()`

```
SPINNAKERC_API spinCameraUnregisterImageEventHandler (
    spinCamera hCamera,
    spinImageEventHandler hImageEventHandler )
```

Unregisters an image event handler from a camera.

See also

[spinError](#)

Parameters

<i>hCamera</i>	The camera from which to unregister the image event handler
<i>hImageEventHandler</i>	The image event handler to unregister

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.12.2.23 `spinCameraWritePort()`

```
SPINNAKERC_API spinCameraWritePort (
    spinCamera hCamera,
    uint64_t iAddress,
    void * pBuffer,
    size_t iSize )
```

4.13 Image Access

The functions in this section provide access to information and functionality of images.

Functions

- [SPINNAKERC_API spinImageCreateEmpty](#) ([spinImage](#) *phImage)
Creates an empty image; images created this way must be destroyed.
- [SPINNAKERC_API spinImageCreate](#) ([spinImage](#) hSrcImage, [spinImage](#) *phDestImage)
Creates an image from another; images created this way must be destroyed.
- [SPINNAKERC_API spinImageCreateEx](#) ([spinImage](#) *phImage, [size_t](#) width, [size_t](#) height, [size_t](#) offsetX, [size_t](#) offsetY, [spinPixelFormatEnums](#) pixelFormat, void *pData)
Creates an image with some set properties; images created this way must be destroyed.
- [SPINNAKERC_API spinImageDestroy](#) ([spinImage](#) hImage)
Destroys an image.
- [SPINNAKERC_API spinImageSetDefaultColorProcessing](#) ([spinColorProcessingAlgorithm](#) algorithm)
Sets the default color processing algorithm of all images (if not otherwise set)
- [SPINNAKERC_API spinImageGetDefaultColorProcessing](#) ([spinColorProcessingAlgorithm](#) *pAlgorithm)
Retrieves the default color processing algorithm.
- [SPINNAKERC_API spinImageGetColorProcessing](#) ([spinImage](#) hImage, [spinColorProcessingAlgorithm](#) *pAlgorithm)
Retrieves the color processing algorithm of a specific image.
- [SPINNAKERC_API spinImageConvert](#) ([spinImage](#) hSrcImage, [spinPixelFormatEnums](#) pixelFormat, [spinImage](#) hDestImage)
Converts the pixel format of one image into a new image.
- [SPINNAKERC_API spinImageConvertEx](#) ([spinImage](#) hSrcImage, [spinPixelFormatEnums](#) pixelFormat, [spinColorProcessingAlgorithm](#) algorithm, [spinImage](#) hDestImage)
Converts the pixel format and color processing algorithm of one image into a new image.
- [SPINNAKERC_API spinImageReset](#) ([spinImage](#) hImage, [size_t](#) width, [size_t](#) height, [size_t](#) offsetX, [size_t](#) offsetY, [spinPixelFormatEnums](#) pixelFormat)
Resets an image with some set properties.
- [SPINNAKERC_API spinImageResetEx](#) ([spinImage](#) hImage, [size_t](#) width, [size_t](#) height, [size_t](#) offsetX, [size_t](#) offsetY, [spinPixelFormatEnums](#) pixelFormat, void *pData)
Resets an image with some set properties and image data.
- [SPINNAKERC_API spinImageGetID](#) ([spinImage](#) hImage, [uint64_t](#) *pId)
Retrieves the ID of an image.
- [SPINNAKERC_API spinImageGetData](#) ([spinImage](#) hImage, void **ppData)
Retrieves the image data of an image.
- [SPINNAKERC_API spinImageGetPrivateData](#) ([spinImage](#) hImage, void **ppData)
Retrieves the private data of an image.
- [SPINNAKERC_API spinImageGetBufferSize](#) ([spinImage](#) hImage, [size_t](#) *pSize)
Retrieves the buffer size of an image.
- [SPINNAKERC_API spinImageDeepCopy](#) ([spinImage](#) hSrcImage, [spinImage](#) hDestImage)
Creates a deep copy of an image (the destination image must be created as an empty image prior to the deep copy)
- [SPINNAKERC_API spinImageGetWidth](#) ([spinImage](#) hImage, [size_t](#) *pWidth)
Retrieves the width of an image.
- [SPINNAKERC_API spinImageGetHeight](#) ([spinImage](#) hImage, [size_t](#) *pHeight)
Retrieves the height of an image.
- [SPINNAKERC_API spinImageGetOffsetX](#) ([spinImage](#) hImage, [size_t](#) *pOffsetX)
Retrieves the offset of an image along its X axis.

- [SPINNAKERC_API spinImageGetOffsetY](#) ([spinImage](#) hImage, [size_t](#) *pOffsetY)
Retrieves the offset of an image along its Y axis.
- [SPINNAKERC_API spinImageGetPaddingX](#) ([spinImage](#) hImage, [size_t](#) *pPaddingX)
Retrieves the padding of an image along its X axis.
- [SPINNAKERC_API spinImageGetPaddingY](#) ([spinImage](#) hImage, [size_t](#) *pPaddingY)
Retrieves the padding of an image along its Y axis.
- [SPINNAKERC_API spinImageGetFrameID](#) ([spinImage](#) hImage, [uint64_t](#) *pFrameID)
Retrieves the frame ID of an image.
- [SPINNAKERC_API spinImageGetTimeStamp](#) ([spinImage](#) hImage, [uint64_t](#) *pTimeStamp)
Retrieves the timestamp of an image.
- [SPINNAKERC_API spinImageGetPayloadType](#) ([spinImage](#) hImage, [size_t](#) *pPayloadType)
Retrieves the payload type of an image (as an enum, [spinPayloadTypeInfos](#))
- [SPINNAKERC_API spinImageGetTLPayloadType](#) ([spinImage](#) hImage, [spinPayloadTypeInfoIDs](#) *pPayloadType)
Retrieves the transport layer payload type of an image (as an enum, [spinPayloadTypeInfos](#))
- [SPINNAKERC_API spinImageGetPixelFormat](#) ([spinImage](#) hImage, [spinPixelFormatEnums](#) *pPixelFormat)
Retrieves the pixel format of an image (as an enum, [spinPixelFormatEnums](#))
- [SPINNAKERC_API spinImageGetTLPixelFormat](#) ([spinImage](#) hImage, [uint64_t](#) *pPixelFormat)
Retrieves the transport layer pixel format of an image (as an unsigned integer)
- [SPINNAKERC_API spinImageGetTLPixelFormatNamespace](#) ([spinImage](#) hImage, [spinPixelFormatNamespaces](#) *pPixelFormatNamespace)
Retrieves the transport layer pixel format namespace of an image (as an enum, [spinPixelFormatNamespaces](#))
- [SPINNAKERC_API spinImageGetPixelFormatName](#) ([spinImage](#) hImage, [char](#) *pBuf, [size_t](#) *pBufLen)
Retrieves the pixel format of an image (as a symbolic)
- [SPINNAKERC_API spinImageIsIncomplete](#) ([spinImage](#) hImage, [bool8_t](#) *pIsIncomplete)
Checks whether an image is incomplete.
- [SPINNAKERC_API spinImageGetValidPayloadSize](#) ([spinImage](#) hImage, [size_t](#) *pSize)
Retrieves the valid payload size of an image.
- [SPINNAKERC_API spinImageSave](#) ([spinImage](#) hImage, [const char](#) *pFilename, [spinImageFileFormat](#) format)
Saves an image using a specified file format (using an enum, [spinImageFileFormat](#))
- [SPINNAKERC_API spinImageSaveFromExt](#) ([spinImage](#) hImage, [const char](#) *pFilename)
Saves an image using a specified file format (using the extension of the filename)
- [SPINNAKERC_API spinImageSavePng](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinPNGOption](#) *pOption)
Saves an image as a PNG image.
- [SPINNAKERC_API spinImageSavePpm](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinPPMOption](#) *pOption)
Saves an image as a PPM image.
- [SPINNAKERC_API spinImageSavePgm](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinPGMOption](#) *pOption)
Saves an image as an PGM image.
- [SPINNAKERC_API spinImageSaveTiff](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinTIFFOption](#) *pOption)
Saves an image as a TIFF image.
- [SPINNAKERC_API spinImageSaveJpeg](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinJPEGOption](#) *pOption)
Saves an image as a JPEG image.
- [SPINNAKERC_API spinImageSaveJpg2](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinJPG2Option](#) *pOption)
Saves an image as a JPEG 2000 image.

- [SPINNAKERC_API spinImageSaveBmp](#) ([spinImage](#) hImage, const char *pFilename, const [spinBMPOption](#) *pOption)
Saves an image as a BMP image.
- [SPINNAKERC_API spinImageGetChunkLayoutID](#) ([spinImage](#) hImage, uint64_t *pId)
Retrieves the chunk layout ID of an image.
- [SPINNAKERC_API spinImageCalculateStatistics](#) ([spinImage](#) hImage, const [spinImageStatistics](#) hStatistics)
Calculates the image statistics of an image.
- [SPINNAKERC_API spinImageGetStatus](#) ([spinImage](#) hImage, [spinImageStatus](#) *pStatus)
Retrieves the image status of an image.
- [SPINNAKERC_API spinImageGetStatusDescription](#) ([spinImageStatus](#) status, char *pBuf, size_t *pBufLen)
Retrieves the description of image status.
- [SPINNAKERC_API spinImageRelease](#) ([spinImage](#) hImage)
Releases an image.
- [SPINNAKERC_API spinImageHasCRC](#) ([spinImage](#) hImage, bool8_t *pbHasCRC)
Checks whether an image has CRC.
- [SPINNAKERC_API spinImageCheckCRC](#) ([spinImage](#) hImage, bool8_t *pbCheckCRC)
Checks whether the CRC of an image is correct.
- [SPINNAKERC_API spinImageGetBitsPerPixel](#) ([spinImage](#) hImage, size_t *pBitsPerPixel)
Retrieves the number of bits per pixel of an image.
- [SPINNAKERC_API spinImageGetSize](#) ([spinImage](#) hImage, size_t *pImageSize)
Retrieves the size of an image.
- [SPINNAKERC_API spinImageGetStride](#) ([spinImage](#) hImage, size_t *pStride)
Retrieves the stride of an image.

4.13.1 Detailed Description

The functions in this section provide access to information and functionality of images.

This includes creation, destruction, and saving as well as a wealth of information including things like width, height, stride, and timestamp.

4.13.2 Function Documentation

4.13.2.1 spinImageCalculateStatistics()

```
SPINNAKERC_API spinImageCalculateStatistics (
    spinImage hImage,
    const spinImageStatistics hStatistics )
```

Calculates the image statistics of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>hStatistics</i>	The image statistics context in which the calculated statistics are returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.2 `spinImageCheckCRC()`

```
SPINNAKERC_API spinImageCheckCRC (  
    spinImage hImage,  
    bool8_t * pbCheckCRC )
```

Checks whether the CRC of an image is correct.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pbCheckCRC</i>	The boolean pointer to return whether the image CRC passes

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.3 `spinImageConvert()`

```
SPINNAKERC_API spinImageConvert (  
    spinImage hSrcImage,  
    spinPixelFormatEnums pixelFormat,  
    spinImage hDestImage )
```

Converts the pixel format of one image into a new image.

See also

[spinError](#)

Parameters

<i>hSrcImage</i>	The image to be converted
<i>pixelFormat</i>	The pixel format to be converted to
<i>hDestImage</i>	The image handle pointer in which the converted image is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.4 `spinImageConvertEx()`

```
SPINNAKERC_API spinImageConvertEx (
    spinImage hSrcImage,
    spinPixelFormatEnums pixelFormat,
    spinColorProcessingAlgorithm algorithm,
    spinImage hDestImage )
```

Converts the pixel format and color processing algorithm of one image into a new image.

See also

[spinError](#)

Parameters

<i>hSrcImage</i>	The image to be converted
<i>pixelFormat</i>	The pixel format to be converted to
<i>algorithm</i>	The color processing algorithm to use for conversion
<i>hDestImage</i>	The image handle pointer in which the converted image is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.5 `spinImageCreate()`

```
SPINNAKERC_API spinImageCreate (
    spinImage hSrcImage,
    spinImage * phDestImage )
```

Creates an image from another; images created this way must be destroyed.

See also

[spinError](#)

Parameters

<i>hSrcImage</i>	The image to be copied
<i>phDestImage</i>	The image handle pointer of the image to be created

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.6 `spinImageCreateEmpty()`

```
SPINNAKERC_API spinImageCreateEmpty (  
    spinImage * phImage )
```

Creates an empty image; images created this way must be destroyed.

See also

[spinError](#)

Parameters

<i>phImage</i>	The image handle pointer in which the empty image is returned
----------------	---

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.7 `spinImageCreateEx()`

```
SPINNAKERC_API spinImageCreateEx (  
    spinImage * phImage,  
    size_t width,  
    size_t height,  
    size_t offsetX,  
    size_t offsetY,  
    spinPixelFormatEnums pixelFormat,  
    void * pData )
```

Creates an image with some set properties; images created this way must be destroyed.

See also

[spinError](#)

Parameters

<i>phImage</i>	The image handle pointer in which the image is returned
<i>width</i>	The width to set
<i>height</i>	The height to set
<i>offsetX</i>	The offset along the X axis to set
<i>offsetY</i>	The offset along the Y axis to set
<i>pixelFormat</i>	The pixel format to set
<i>pData</i>	The image data to set; can be set to null

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.8 `spinImageDeepCopy()`

```
SPINNAKERC_API spinImageDeepCopy (
    spinImage hSrcImage,
    spinImage hDestImage )
```

Creates a deep copy of an image (the destination image must be created as an empty image prior to the deep copy)

See also

[spinError](#)

Parameters

<i>hSrcImage</i>	The image to be copied
<i>hDestImage</i>	The image handle in which the image is copied

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.9 `spinImageDestroy()`

```
SPINNAKERC_API spinImageDestroy (
    spinImage hImage )
```

Destroys an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to destroy
---------------	----------------------

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.10 `spinImageGetBitsPerPixel()`

```
SPINNAKERC_API spinImageGetBitsPerPixel (
    spinImage hImage,
    size_t * pBitsPerPixel )
```

Retrieves the number of bits per pixel of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pBitsPerPixel</i>	The unsigned integer pointer in which the number of bits per pixel is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.11 `spinImageGetBufferSize()`

```
SPINNAKERC_API spinImageGetBufferSize (
    spinImage hImage,
    size_t * pSize )
```

Retrieves the buffer size of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of image data buffer to retrieve
<i>pSize</i>	The unsigned integer pointer in which the size of the image data if returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.12 `spinImageGetChunkLayoutID()`

```
SPINNAKERC_API spinImageGetChunkLayoutID (
    spinImage hImage,
    uint64_t * pId )
```

Retrieves the chunk layout ID of an image.

See also

[`spinError`](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pId</i>	The unsigned integer pointer in which the chunk layout ID is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.13 `spinImageGetColorProcessing()`

```
SPINNAKERC_API spinImageGetColorProcessing (
    spinImage hImage,
    spinColorProcessingAlgorithm * pAlgorithm )
```

Retrieves the color processing algorithm of a specific image.

See also

[`spinError`](#)

Parameters

<i>hImage</i>	The image of the color processing algorithm to retrieve
<i>pAlgorithm</i>	The color processing algorithm pointer in which the color processing algorithm is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.14 `spinImageGetData()`

```
SPINNAKERC_API spinImageGetData (
    spinImage hImage,
    void ** ppData )
```

Retrieves the image data of an image.

See also

[`spinError`](#)

Parameters

<i>hImage</i>	The image of the image data to retrieve
<i>ppData</i>	The pointer to the void pointer in which the image data is retrieved

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.15 `spinImageGetDefaultColorProcessing()`

```
SPINNAKERC_API spinImageGetDefaultColorProcessing (
    spinColorProcessingAlgorithm * pAlgorithm )
```

Retrieves the default color processing algorithm.

See also

[`spinError`](#)

Parameters

<i>pAlgorithm</i>	The color processing algorithm enum pointer in which the color processing algorithm is returned
-------------------	---

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.16 spinImageGetFrameID()

```
SPINNAKERC_API spinImageGetFrameID (
    spinImage hImage,
    uint64_t * pFrameID )
```

Retrieves the frame ID of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the frame ID to retrieve
<i>pFrameID</i>	The unsigned integer pointer in which the frame ID is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.17 spinImageGetHeight()

```
SPINNAKERC_API spinImageGetHeight (
    spinImage hImage,
    size_t * pHeight )
```

Retrieves the height of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the height to retrieve
<i>pHeight</i>	The unsigned integer pointer in which the height is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.18 spinImageGetID()

```
SPINNAKERC_API spinImageGetID (
    spinImage hImage,
    uint64_t * pId )
```

Retrieves the ID of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the ID to retrieve
<i>pId</i>	The unsigned integer pointer in which the ID is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.19 spinImageGetOffsetX()

```
SPINNAKERC_API spinImageGetOffsetX (
    spinImage hImage,
    size_t * pOffsetX )
```

Retrieves the offset of an image along its X axis.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the offset along the X axis to retrieve
<i>pOffsetX</i>	The unsigned integer pointer in which the offset along the X axis is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.20 spinImageGetOffsetY()

```
SPINNAKERC_API spinImageGetOffsetY (
    spinImage hImage,
    size_t * pOffsetY )
```

Retrieves the offset of an image along its Y axis.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the offset along the Y axis to retrieve
<i>pOffsetY</i>	The unsigned integer pointer in which the offset along the Y axis is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.21 spinImageGetPaddingX()

```
SPINNAKERC_API spinImageGetPaddingX (
    spinImage hImage,
    size_t * pPaddingX )
```

Retrieves the padding of an image along its X axis.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the padding along the X axis to retrieve
<i>pPaddingX</i>	The unsigned integer pointer in which the padding along the X axis is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.22 spinImageGetPaddingY()

```
SPINNAKERC_API spinImageGetPaddingY (
    spinImage hImage,
    size_t * pPaddingY )
```

Retrieves the padding of an image along its Y axis.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the padding along the Y axis to retrieve
<i>pPaddingY</i>	The unsigned integer pointer in which the padding along the Y axis is returned

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.23 spinImageGetPayloadType()

```
SPINNAKERC_API spinImageGetPayloadType (
    spinImage hImage,
    size_t * pPayloadType )
```

Retrieves the payload type of an image (as an enum, [spinPayloadTypeIn folds](#))

See also

[spinError](#)

[spinPayloadTypeIn folds](#)

Parameters

<i>hImage</i>	The image of the payload type to retrieve
<i>pPayloadType</i>	The payload type enum pointer in which the payload type is returned

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.24 spinImageGetPixelFormat()

```
SPINNAKERC_API spinImageGetPixelFormat (
    spinImage hImage,
    spinPixelFormatEnums * pPixelFormat )
```

Retrieves the pixel format of an image (as an enum, spinPixelFormatEnums)

See also

[spinError](#)
[spinPixelFormatEnums](#)

Parameters

<i>hImage</i>	The image of the pixel format to retrieve
<i>pPixelFormat</i>	The pixel format enum pointer in which the pixel format is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.25 spinImageGetPixelFormatName()

```
SPINNAKERC_API spinImageGetPixelFormatName (
    spinImage hImage,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the pixel format of an image (as a symbolic)

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the pixel format to retrieve
<i>pBuf</i>	The c-string character buffer in which the pixel format symbolic is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.26 spinImageGetPrivateData()

```
SPINNAKERC_API spinImageGetPrivateData (
    spinImage hImage,
    void ** ppData )
```

Retrieves the private data of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the private image data to retrieve
<i>ppData</i>	The pointer to the void pointer in which the private image data is retrieved

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.27 spinImageGetSize()

```
SPINNAKERC_API spinImageGetSize (
    spinImage hImage,
    size_t * pImageSize )
```

Retrieves the size of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pImageSize</i>	The unsigned integer pointer in which the size of the image is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.28 spinImageGetStatus()

```
SPINNAKERC_API spinImageGetStatus (
    spinImage hImage,
    spinImageStatus * pStatus )
```

Retrieves the image status of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pStatus</i>	The status enum pointer in which the image status is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.29 spinImageGetStatusDescription()

```
SPINNAKERC_API spinImageGetStatusDescription (
    spinImageStatus status,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the description of image status.

See also

[spinError](#)

Parameters

<i>status</i>	The status enum
<i>pBuf</i>	The c-string character buffer in which the explanation of image status enum is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length; if pBuf is NULL, minimum length of string buffer is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.30 spinImageGetStride()

```
SPINNAKERC_API spinImageGetStride (
    spinImage hImage,
    size_t * pStride )
```

Retrieves the stride of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pStride</i>	The unsigned integer pointer in which the stride is returned

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.31 spinImageGetTimeStamp()

```
SPINNAKERC_API spinImageGetTimeStamp (
    spinImage hImage,
    uint64_t * pTimeStamp )
```

Retrieves the timestamp of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the timestamp to retrieve
<i>pTimeStamp</i>	The unsigned integer pointer om which the timestamp is returned

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.32 spinImageGetTLPayloadType()

```
SPINNAKERC_API spinImageGetTLPayloadType (
    spinImage hImage,
    spinPayloadTypeInfoIDs * pPayloadType )
```

Retrieves the transport layer payload type of an image (as an enum, spinPayloadTypeInfolDs)

See also

[spinError](#)
[spinPayloadTypeInfolDs](#)

Parameters

<i>hImage</i>	The image of the TL payload type to retrieve
<i>pPayloadType</i>	The payload type enum pointer in which the TL payload type is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.33 spinImageGetTLPixelFormat()

```
SPINNAKERC_API spinImageGetTLPixelFormat (
    spinImage hImage,
    uint64_t * pPixelFormat )
```

Retrieves the transport layer pixel format of an image (as an unsigned integer)

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the TL pixel format to retrieve
<i>pPixelFormat</i>	The unsigned integer pointer in which the TL pixel format is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.34 spinImageGetTLPixelFormatNamespace()

```
SPINNAKERC_API spinImageGetTLPixelFormatNamespace (
    spinImage hImage,
    spinPixelFormatNamespaceID * pPixelFormatNamespace )
```

Retrieves the transport layer pixel format namespace of an image (as an enum, spinPixelFormatNamespaceID)

See also

[spinError](#)
[spinPixelFormatNamespaceID](#)

Parameters

<i>hImage</i>	The image of the TL pixel format namespace to retrieve
<i>pPixelFormatNamespace</i>	The pixel format namespace pointer in which the pixel format namespace is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.35 spinImageGetValidPayloadSize()

```
SPINNAKERC_API spinImageGetValidPayloadSize (
    spinImage hImage,
    size_t * pSize )
```

Retrieves the valid payload size of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the payload size to retrieve
<i>pSize</i>	The unsigned integer pointer in which the size of the valid payload is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.36 spinImageGetWidth()

```
SPINNAKERC_API spinImageGetWidth (
    spinImage hImage,
    size_t * pWidth )
```

Retrieves the width of an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image of the width to retrieve
<i>pWidth</i>	The unsigned integer pointer in which the width is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.37 spinImageHasCRC()

```
SPINNAKERC_API spinImageHasCRC (
    spinImage hImage,
    bool8_t * pbHasCRC )
```

Checks whether an image has CRC.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pbHasCRC</i>	The boolean pointer to return whether the image has CRC available

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.38 spinImageIsIncomplete()

```
SPINNAKERC_API spinImageIsIncomplete (
    spinImage hImage,
    bool8_t * pbIsIncomplete )
```

Checks whether an image is incomplete.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to check
<i>pbIsIncomplete</i>	The boolean pointer to return whether or not the image is incomplete

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.39 spinImageRelease()

```
SPINNAKERC_API spinImageRelease (
    spinImage hImage )
```

Releases an image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
---------------	-----------------------

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.40 spinImageReset()

```
SPINNAKERC_API spinImageReset (
    spinImage hImage,
```



```

size_t width,
size_t height,
size_t offsetX,
size_t offsetY,
spinPixelFormatEnums pixelFormat )

```

Resets an image with some set properties.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be reset
<i>width</i>	The width to be reset to
<i>height</i>	The height to be reset to
<i>offsetX</i>	The offset to be reset to along the X axis
<i>offsetY</i>	The offset to be reset to along the Y axis
<i>pixelFormat</i>	The pixel format to be reset to

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.13.2.41 spinImageResetEx()

```

SPINNAKERC_API spinImageResetEx (
    spinImage hImage,
    size_t width,
    size_t height,
    size_t offsetX,
    size_t offsetY,
    spinPixelFormatEnums pixelFormat,
    void * pData )

```

Resets an image with some set properties and image data.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to reset
<i>width</i>	The width to be reset to
<i>height</i>	The height to be reset to
<i>offsetX</i>	The offset to be reset to along the X axis
<i>offsetY</i>	The offset to be reset to along the Y axis
<i>pixelFormat</i>	The pixel format to be reset to
<i>pData</i>	The image data to reset to

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.42 spinImageSave()

```
SPINNAKERC_API spinImageSave (
    spinImage hImage,
    const char * pFilename,
    spinImageFileFormat format )
```

Saves an image using a specified file format (using an enum, `spinImageFileFormat`)

See also

[spinError](#)
[spinImageFileFormat](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pFilename</i>	The filename to use to save the image (with or without the appropriate file extension) format The file format to use to save the image

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.43 spinImageSaveBmp()

```
SPINNAKERC_API spinImageSaveBmp (
    spinImage hImage,
    const char * pFilename,
    const spinBMPOption * pOption )
```

Saves an image as a BMP image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pFilename</i>	The filename to use to save the image (with or without the appropriate file extension)
<i>pOption</i>	The image options related to saving as BMP; includes whether to save as indexed 8-bit

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.44 `spinImageSaveFromExt()`

```
SPINNAKERC_API spinImageSaveFromExt (
    spinImage hImage,
    const char * pFilename )
```

Saves an image using a specified file format (using the extension of the filename)

See also

[`spinError`](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pFilename</i>	The filename to use to save the image (with or without the appropriate file extension)

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.45 `spinImageSaveJpeg()`

```
SPINNAKERC_API spinImageSaveJpeg (
    spinImage hImage,
    const char * pFilename,
    const spinJPEGOption * pOption )
```

Saves an image as a JPEG image.

See also

[`spinError`](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pFilename</i>	The filename to use to save the image (with or without the appropriate file extension)
<i>pOption</i>	The image options related to saving as JPEG; includes quality and whether to save as progressive

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.46 spinImageSaveJpg2()

```
SPINNAKERC_API spinImageSaveJpg2 (
    spinImage hImage,
    const char * pFilename,
    const spinJPG2Option * pOption )
```

Saves an image as a JPEG 2000 image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pFilename</i>	The filename to use to save the image (with or without the appropriate file extension)
<i>pOption</i>	The image options related to saving as JPEG 2000; includes quality

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.47 spinImageSavePgm()

```
SPINNAKERC_API spinImageSavePgm (
    spinImage hImage,
    const char * pFilename,
    const spinPGMOption * pOption )
```

Saves an image as an PGM image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pFilename</i>	The filename to use to save the image (with or without the appropriate file extension)
<i>pOption</i>	The image options related to saving as PGM; includes whether to save as binary

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.48 spinImageSavePng()

```
SPINNAKER_API spinImageSavePng (
    spinImage hImage,
    const char * pFilename,
    const spinPNGOption * pOption )
```

Saves an image as a PNG image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pFilename</i>	The filename to use to save the image (with or without the appropriate file extension)
<i>pOption</i>	The image options related to saving as PNG; includes compression level and whether to save as interlaced

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.49 spinImageSavePpm()

```
SPINNAKER_API spinImageSavePpm (
    spinImage hImage,
    const char * pFilename,
    const spinPPMOption * pOption )
```

Saves an image as a PPM image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pFilename</i>	The filename to use to save the image (with or without the appropriate file extension)
<i>pOption</i>	The image options related to saving as PPM; includes whether to save as binary

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.50 spinImageSaveTiff()

```
SPINNAKERC_API spinImageSaveTiff (
    spinImage hImage,
    const char * pFilename,
    const spinTIFFOption * pOption )
```

Saves an image as a TIFF image.

See also

[spinError](#)

Parameters

<i>hImage</i>	The image to be saved
<i>pFilename</i>	The filename to use to save the image (with or without the appropriate file extension)
<i>pOption</i>	The image options related to saving as TIFF; includes compression method

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.13.2.51 spinImageSetDefaultColorProcessing()

```
SPINNAKERC_API spinImageSetDefaultColorProcessing (
    spinColorProcessingAlgorithm algorithm )
```

Sets the default color processing algorithm of all images (if not otherwise set)

See also

[spinError](#)

Parameters

<i>algorithm</i>	The color processing algorithm used by default
------------------	--

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14 Event Access

The functions in this section allow for the creation and destruction of events.

Functions

- [SPINNAKERC_API spinDeviceEventHandlerCreate](#) ([spinDeviceEventHandler](#) *phDeviceEventHandler, [spinDeviceEventFunction](#) pFunction, void *pUserData)
Creates a device event handler.
- [SPINNAKERC_API spinDeviceEventHandlerDestroy](#) ([spinDeviceEventHandler](#) hDeviceEventHandler)
Destroys a device event handler.
- [SPINNAKERC_API spinImageEventHandlerCreate](#) ([spinImageEventHandler](#) *phImageEventHandler, [spinImageEventFunction](#) pFunction, void *pUserData)
Creates an image event handler.
- [SPINNAKERC_API spinImageEventHandlerDestroy](#) ([spinImageEventHandler](#) hImageEventHandler)
Destroys an image event handler.
- [SPINNAKERC_API spinDeviceArrivalEventHandlerCreate](#) ([spinDeviceArrivalEventHandler](#) *phDeviceArrivalEventHandler, [spinArrivalEventFunction](#) pFunction, void *pUserData)
Creates a device arrival event handler.
- [SPINNAKERC_API spinDeviceArrivalEventHandlerDestroy](#) ([spinDeviceArrivalEventHandler](#) hDeviceArrivalEventHandler)
Destroys a device arrival event handler.
- [SPINNAKERC_API spinDeviceRemovalEventHandlerCreate](#) ([spinDeviceRemovalEventHandler](#) *phDeviceRemovalEventHandler, [spinRemovalEventFunction](#) pFunction, void *pUserData)
Creates a device removal event handler.
- [SPINNAKERC_API spinDeviceRemovalEventHandlerDestroy](#) ([spinDeviceRemovalEventHandler](#) hDeviceRemovalEventHandler)
Destroys a device removal event handler.
- [SPINNAKERC_API spinInterfaceEventHandlerCreate](#) ([spinInterfaceEventHandler](#) *phInterfaceEventHandler, [spinArrivalEventFunction](#) pArrivalFunction, [spinRemovalEventFunction](#) pRemovalFunction, void *pUserData)
Creates an interface event handler (both device arrival and device removal)
- [SPINNAKERC_API spinInterfaceEventHandlerDestroy](#) ([spinInterfaceEventHandler](#) hInterfaceEventHandler)
Destroys an interface event handler (both device arrival and device removal)
- [SPINNAKERC_API spinLogEventHandlerCreate](#) ([spinLogEventHandler](#) *phLogEventHandler, [spinLogEventFunction](#) pFunction, void *pUserData)
Creates a log event handler.
- [SPINNAKERC_API spinLogEventHandlerDestroy](#) ([spinLogEventHandler](#) hLogEventHandler)
Destroys a log event handler.

4.14.1 Detailed Description

The functions in this section allow for the creation and destruction of events.

4.14.2 Function Documentation

4.14.2.1 spinDeviceArrivalEventHandlerCreate()

```
SPINNAKERC_API spinDeviceArrivalEventHandlerCreate (
    spinDeviceArrivalEventHandler * phDeviceArrivalEventHandler,
    spinArrivalEventFunction pFunction,
    void * pUserData )
```

Creates a device arrival event handler.

See also

[spinError](#)

Parameters

<i>phDeviceArrivalEventHandler</i>	The device arrival event handler pointer in which the device arrival event context is created
<i>pFunction</i>	The function to be called at device event occurrences; signature to match: void(spinArrivalEventFunction)(void pUserData)
<i>pUserData</i>	Properties that can be passed into the event function

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14.2.2 spinDeviceArrivalEventHandlerDestroy()

```
SPINNAKERC_API spinDeviceArrivalEventHandlerDestroy (
    spinDeviceArrivalEventHandler hDeviceArrivalEventHandler )
```

Destroys a device arrival event handler.

See also

[spinError](#)

Parameters

<i>hDeviceArrivalEventHandler</i>	The device arrival event handler to destroy
-----------------------------------	---

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14.2.3 spinDeviceEventHandlerCreate()

```
SPINNAKERC_API spinDeviceEventHandlerCreate (
    spinDeviceEventHandler * phDeviceEventHandler,
    spinDeviceEventFunction pFunction,
    void * pUserData )
```

Creates a device event handler.

See also

[spinError](#)

Parameters

<i>phDeviceEventHandler</i>	The device event handler pointer in which the device event context is created
<i>pFunction</i>	The function to be called at device event occurrences; signature to match: void(spinDeviceEventFunction)(const spinDeviceEventData hEventData, const char pEventName, void* pUserData)
<i>pUserData</i>	Properties that can be passed into the event function

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14.2.4 spinDeviceEventHandlerDestroy()

```
SPINNAKERC_API spinDeviceEventHandlerDestroy (
    spinDeviceEventHandler hDeviceEventHandler )
```

Destroys a device event handler.

See also

[spinError](#)

Parameters

<i>hDeviceEventHandler</i>	The device event handler to destroy
----------------------------	-------------------------------------

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14.2.5 spinDeviceRemovalEventHandlerCreate()

```
SPINNAKERC_API spinDeviceRemovalEventHandlerCreate (
    spinDeviceRemovalEventHandler * phDeviceRemovalEventHandler,
    spinRemovalEventFunction pFunction,
    void * pUserData )
```

Creates a device removal event handler.

See also

[spinError](#)

Parameters

<i>phDeviceRemovalEventHandler</i>	The device removal event handler pointer in which the device removal event context is created
<i>pFunction</i>	The function to be called at device event occurrences; signature to match: void(spinRemovalEventFunction)(uint64_t deviceSerialNumber, void pUserData)
<i>pUserData</i>	Properties that can be passed into the event function

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14.2.6 spinDeviceRemovalEventHandlerDestroy()

```
SPINNAKERC_API spinDeviceRemovalEventHandlerDestroy (
    spinDeviceRemovalEventHandler hDeviceRemovalEventHandler )
```

Destroys a device removal event handler.

See also

[spinError](#)

Parameters

<i>hDeviceRemovalEventHandler</i>	The device removal event handler to destroy
-----------------------------------	---

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14.2.7 spinImageEventHandlerCreate()

```
SPINNAKERC_API spinImageEventHandlerCreate (
    spinImageEventHandler * phImageEventHandler,
    spinImageEventFunction pFunction,
    void * pUserData )
```

Creates an image event handler.

See also

[spinError](#)

Parameters

<i>phImageEventHandler</i>	The image event handler pointer in which the image event context is created
<i>pFunction</i>	The function to be called at image event occurrences; signature to match: void(spinImageEventFunction)(const spinImage hImage, void pUserData)
<i>pUserData</i>	Properties that can be passed into the event function

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14.2.8 spinImageEventHandlerDestroy()

```
SPINNAKERC_API spinImageEventHandlerDestroy (
    spinImageEventHandler hImageEventHandler )
```

Destroys an image event handler.

See also

[spinError](#)

Parameters

<i>hImageEventHandler</i>	The image event handler to destroy
---------------------------	------------------------------------

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14.2.9 `spinInterfaceEventHandlerCreate()`

```
SPINNAKERC_API spinInterfaceEventHandlerCreate (
    spinInterfaceEventHandler * phInterfaceEventHandler,
    spinArrivalEventFunction pArrivalFunction,
    spinRemovalEventFunction pRemovalFunction,
    void * pUserData )
```

Creates an interface event handler (both device arrival and device removal)

See also

[spinError](#)

Parameters

<i>phInterfaceEventHandler</i>	The interface event handler pointer in which the interface event context is created
<i>pArrivalFunction</i>	The function to be called at arrival event occurrences; signature to match: void(spinArrivalEventFunction)(void pUserData)
<i>hRemovalFunction</i>	The function to be called at removal event occurrences; signature to match: void(spinRemovalEventFunction)(uint64_t deviceSerialNumber, void pUserData)
<i>pUserData</i>	Properties that can be passed into the event function

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.14.2.10 `spinInterfaceEventHandlerDestroy()`

```
SPINNAKERC_API spinInterfaceEventHandlerDestroy (
    spinInterfaceEventHandler hInterfaceEventHandler )
```

Destroys an interface event handler (both device arrival and device removal)

See also

[spinError](#)

Parameters

<i>hInterfaceEventHandler</i>	The interface event handler to destroy
-------------------------------	--

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.14.2.11 spinLogEventHandlerCreate()

```
SPINNAKERC_API spinLogEventHandlerCreate (
    spinLogEventHandler * phLogEventHandler,
    spinLogEventFunction pFunction,
    void * pUserData )
```

Creates a log event handler.

See also

[spinError](#)

Parameters

<i>phLogEventHandler</i>	The log event handler pointer in which the log event context is created
<i>pFunction</i>	The function to be called at device event occurrences; signature to match: void(spinLogEventFunction)(const spinLogEventData hEventData, void pUserData)
<i>pUserData</i>	Properties that can be passed into the event function

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.14.2.12 spinLogEventHandlerDestroy()

```
SPINNAKERC_API spinLogEventHandlerDestroy (
    spinLogEventHandler hLogEventHandler )
```

Destroys a log event handler.

See also

[spinError](#)

Parameters

<i>hLogEventHandler</i>	The log event handler to destroy
-------------------------	----------------------------------

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.15 ImageStatistics Access

The functions in this section provide access to information and functionality related to image statistics.

Functions

- [SPINNAKERC_API spinImageStatisticsCreate](#) ([spinImageStatistics](#) *phStatistics)
Creates an image statistics context.
- [SPINNAKERC_API spinImageStatisticsDestroy](#) ([spinImageStatistics](#) hStatistics)
Destroys an image statistics context.
- [SPINNAKERC_API spinImageStatisticsEnableAll](#) ([spinImageStatistics](#) hStatistics)
Enables all channels of an image statistics context.
- [SPINNAKERC_API spinImageStatisticsDisableAll](#) ([spinImageStatistics](#) hStatistics)
Disables all channels of an image statistics context.
- [SPINNAKERC_API spinImageStatisticsEnableGreyOnly](#) ([spinImageStatistics](#) hStatistics)
Disables all channels of an image statistics context except grey-scale.
- [SPINNAKERC_API spinImageStatisticsEnableRgbOnly](#) ([spinImageStatistics](#) hStatistics)
Disables all channels of an image statistics context except red, blue, and green.
- [SPINNAKERC_API spinImageStatisticsEnableHslOnly](#) ([spinImageStatistics](#) hStatistics)
Disables all channels of an image statistics context except hue, saturation, and lightness.
- [SPINNAKERC_API spinImageStatisticsGetChannelStatus](#) ([spinImageStatistics](#) hStatistics, [spinStatisticsChannel](#) channel, [bool8_t](#) *pbEnabled)
Checks whether an image statistics context is enabled.
- [SPINNAKERC_API spinImageStatisticsSetChannelStatus](#) ([spinImageStatistics](#) hStatistics, [spinStatisticsChannel](#) channel, [bool8_t](#) bEnable)
Sets the status of an image statistics channel.
- [SPINNAKERC_API spinImageStatisticsGetRange](#) ([spinImageStatistics](#) hStatistics, [spinStatisticsChannel](#) channel, unsigned int *pMin, unsigned int *pMax)
Retrieves the range of an image statistics channel.
- [SPINNAKERC_API spinImageStatisticsGetPixelValueRange](#) ([spinImageStatistics](#) hStatistics, [spinStatisticsChannel](#) channel, unsigned int *pMin, unsigned int *pMax)
Retrieves the pixel value range of an image statistics channel.
- [SPINNAKERC_API spinImageStatisticsGetNumPixelValues](#) ([spinImageStatistics](#) hStatistics, [spinStatisticsChannel](#) channel, unsigned int *pNumValues)
Retrieves the number of pixel values of an image statistics channel.
- [SPINNAKERC_API spinImageStatisticsGetMean](#) ([spinImageStatistics](#) hStatistics, [spinStatisticsChannel](#) channel, float *pMean)
Retrieves the mean of pixel values of an image statistics channel.
- [SPINNAKERC_API spinImageStatisticsGetHistogram](#) ([spinImageStatistics](#) hStatistics, [spinStatisticsChannel](#) channel, int **ppHistogram)
Retrieves a histogram of an image statistics channel.
- [SPINNAKERC_API spinImageStatisticsGetAll](#) ([spinImageStatistics](#) hStatistics, [spinStatisticsChannel](#) channel, unsigned int *pRangeMin, unsigned int *pRangeMax, unsigned int *pPixelValueMin, unsigned int *pPixelValueMax, unsigned int *pNumPixelValues, float *pPixelValueMean, int **ppHistogram)
Retrieves all available information of an image statistics channel.

4.15.1 Detailed Description

The functions in this section provide access to information and functionality related to image statistics.

This includes context creation and destruction, the enabling and disabling of channels, and value retrieval.

4.15.2 Function Documentation

4.15.2.1 spinImageStatisticsCreate()

```
SPINNAKERC_API spinImageStatisticsCreate (
    spinImageStatistics * phStatistics )
```

Creates an image statistics context.

Parameters

<i>phStatistics</i>	The statistics handle pointer in which the image statistics context is returned
---------------------	---

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.15.2.2 spinImageStatisticsDestroy()

```
SPINNAKERC_API spinImageStatisticsDestroy (
    spinImageStatistics hStatistics )
```

Destroys an image statistics context.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context to destroy
--------------------	---

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.15.2.3 spinImageStatisticsDisableAll()

```
SPINNAKERC_API spinImageStatisticsDisableAll (
    spinImageStatistics hStatistics )
```

Disables all channels of an image statistics context.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context to disable all channels
--------------------	--

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.15.2.4 spinImageStatisticsEnableAll()

```
SPINNAKERC_API spinImageStatisticsEnableAll (  
    spinImageStatistics hStatistics )
```

Enables all channels of an image statistics context.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context to enable all channels
--------------------	---

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.15.2.5 spinImageStatisticsEnableGreyOnly()

```
SPINNAKERC_API spinImageStatisticsEnableGreyOnly (  
    spinImageStatistics hStatistics )
```

Disables all channels of an image statistics context except grey-scale.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context to enable only grey
--------------------	--

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.15.2.6 spinImageStatisticsEnableHslOnly()

```
SPINNAKERC_API spinImageStatisticsEnableHslOnly (  
    spinImageStatistics hStatistics )
```

Disables all channels of an image statistics context except hue, saturation, and lightness.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context to enable only HSL
--------------------	---

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.15.2.7 spinImageStatisticsEnableRgbOnly()

```
SPINNAKERC_API spinImageStatisticsEnableRgbOnly (  
    spinImageStatistics hStatistics )
```

Disables all channels of an image statistics context except red, blue, and green.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context to enable only RGB
--------------------	---

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.15.2.8 `spinImageStatisticsGetAll()`

```
SPINNAKERC_API spinImageStatisticsGetAll (
    spinImageStatistics hStatistics,
    spinStatisticsChannel channel,
    unsigned int * pRangeMin,
    unsigned int * pRangeMax,
    unsigned int * pPixelValueMin,
    unsigned int * pPixelValueMax,
    unsigned int * pNumPixelValues,
    float * pPixelValueMean,
    int ** ppHistogram )
```

Retrieves all available information of an image statistics channel.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context of the channel
<i>channel</i>	The channel of the information to retrieve
<i>pRangeMin</i>	The unsigned integer pointer in which the minimum value of the range is returned
<i>pRangeMax</i>	The unsigned integer pointer in which the maximum value of the range is returned
<i>pPixelValueMin</i>	The unsigned integer pointer in which the minimum pixel value of the range is returned
<i>pPixelValueMax</i>	The unsigned integer pointer in which the maximum pixel value of the range is returned
<i>pNumPixelValues</i>	The unsigned integer pointer in which the number of pixel values is returned
<i>pPixelValueMean</i>	The float pointer in which the mean pixel value is returned
<i>ppiHistogram</i>	The pointer to the pointer in which the histogram data is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.15.2.9 `spinImageStatisticsGetChannelStatus()`

```
SPINNAKERC_API spinImageStatisticsGetChannelStatus (
    spinImageStatistics hStatistics,
    spinStatisticsChannel channel,
    bool8_t * pbEnabled )
```

Checks whether an image statistics context is enabled.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context of the channel
<i>channel</i>	The channel to check
<i>pbEnabled</i>	The boolean pointer to return whether or not the channel is enabled

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.15.2.10 `spinImageStatisticsGetHistogram()`

```
SPINNAKERC_API spinImageStatisticsGetHistogram (
    spinImageStatistics hStatistics,
    spinStatisticsChannel channel,
    int ** ppHistogram )
```

Retrieves a histogram of an image statistics channel.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context of the channel
<i>channel</i>	The channel of the histogram to be returned
<i>pHistogram</i>	The pointer to the integer pointer in which the histogram data is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.15.2.11 `spinImageStatisticsGetMean()`

```
SPINNAKERC_API spinImageStatisticsGetMean (
    spinImageStatistics hStatistics,
    spinStatisticsChannel channel,
    float * pMean )
```

Retrieves the mean of pixel values of an image statistics channel.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context of the channel
<i>channel</i>	The channel of the mean pixel value to be retrieved
<i>pMean</i>	The float pointer in which the mean pixel value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.15.2.12 `spinImageStatisticsGetNumPixelValues()`

```
SPINNAKERC_API spinImageStatisticsGetNumPixelValues (
    spinImageStatistics hStatistics,
    spinStatisticsChannel channel,
    unsigned int * pNumValues )
```

Retrieves the number of pixel values of an image statistics channel.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context of the channel
<i>channel</i>	The channel where the pixel values to be counted are
<i>iNumValues</i>	The unsigned integer pointer in which the number of pixel values is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.15.2.13 `spinImageStatisticsGetPixelValueRange()`

```
SPINNAKERC_API spinImageStatisticsGetPixelValueRange (
    spinImageStatistics hStatistics,
    spinStatisticsChannel channel,
    unsigned int * pMin,
    unsigned int * pMax )
```

Retrieves the pixel value range of an image statistics channel.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context of the channel
<i>channel</i>	The channel of the pixel value range to retrieve
<i>pMin</i>	The unsigned integer pointer in which the minimum value of the pixel value range is returned
<i>pMax</i>	The unsigned integer pointer in which the maximum value of the pixel value range is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.15.2.14 spinImageStatisticsGetRange()

```
SPINNAKERC_API spinImageStatisticsGetRange (
    spinImageStatistics hStatistics,
    spinStatisticsChannel channel,
    unsigned int * pMin,
    unsigned int * pMax )
```

Retrieves the range of an image statistics channel.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context of the channel
<i>channel</i>	The channel of the range to retrieve
<i>pMin</i>	The unsigned integer pointer in which the minimum value of the range is returned
<i>pMax</i>	The unsigned integer pointer in which the maximum value of the range is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.15.2.15 spinImageStatisticsSetChannelStatus()

```
SPINNAKERC_API spinImageStatisticsSetChannelStatus (
    spinImageStatistics hStatistics,
    spinStatisticsChannel channel,
    bool8_t bEnable )
```

Sets the status of an image statistics channel.

See also

[spinError](#)

Parameters

<i>hStatistics</i>	The image statistics context of the channel
<i>channel</i>	The channel to enable/disable
<i>bEnable</i>	The boolean value to set; true enables, false disables

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.16 Logging Event Data Access

The functions in this section allow for the retrieval of logging event data.

Functions

- [SPINNAKERC_API spinLogDataGetCategoryName](#) ([spinLogEventData](#) hLogEventData, char *pBuf, size_t *pBufLen)
Retrieves the category name of a log event.
- [SPINNAKERC_API spinLogDataGetPriority](#) ([spinLogEventData](#) hLogEventData, int64_t *pValue)
Retrieves the priority of a log event.
- [SPINNAKERC_API spinLogDataGetPriorityName](#) ([spinLogEventData](#) hLogEventData, char *pBuf, size_t *pBufLen)
Retrieves the priority name of a log event.
- [SPINNAKERC_API spinLogDataGetTimestamp](#) ([spinLogEventData](#) hLogEventData, char *pBuf, size_t *pBufLen)
Retrieves the timestamp of a log event.
- [SPINNAKERC_API spinLogDataGetNDC](#) ([spinLogEventData](#) hLogEventData, char *pBuf, size_t *pBufLen)
Retrieves the NDC of a log event.
- [SPINNAKERC_API spinLogDataGetThreadName](#) ([spinLogEventData](#) hLogEventData, char *pBuf, size_t *pBufLen)
Retrieves the thread name of a log event.
- [SPINNAKERC_API spinLogDataGetLogMessage](#) ([spinLogEventData](#) hLogEventData, char *pBuf, size_t *pBufLen)
Retrieves the log message of a log event.

4.16.1 Detailed Description

The functions in this section allow for the retrieval of logging event data.

4.16.2 Function Documentation

4.16.2.1 spinLogDataGetCategoryName()

```
SPINNAKERC_API spinLogDataGetCategoryName (
    spinLogEventData hLogEventData,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the category name of a log event.

See also

[spinError](#)

Parameters

<i>hLogEventData</i>	The log event data received from the log event
<i>pBuf</i>	The c-string character buffer in which the category name of the log event is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.16.2.2 `spinLogDataGetLogMessage()`

```
SPINNAKER_API spinLogDataGetLogMessage (
    spinLogEventData hLogEventData,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the log message of a log event.

See also

[spinError](#)

Parameters

<i>hLogEventData</i>	The log event data received from the log event
<i>pBuf</i>	The c-string character buffer in which the log message of the log event is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.16.2.3 `spinLogDataGetNDC()`

```
SPINNAKER_API spinLogDataGetNDC (
    spinLogEventData hLogEventData,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the NDC of a log event.

See also

[spinError](#)

Parameters

<i>hLogEventData</i>	The log event data received from the log event
<i>pBuf</i>	The c-string character buffer in which the NDC of the log event is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.16.2.4 `spinLogDataGetPriority()`

```
SPINNAKERC_API spinLogDataGetPriority (
    spinLogEventData hLogEventData,
    int64_t * pValue )
```

Retrieves the priority of a log event.

See also

[spinError](#)

Parameters

<i>hLogEventData</i>	The log event data received from the log event
<i>pValue</i>	The integer pointer in which the priority value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.16.2.5 `spinLogDataGetPriorityName()`

```
SPINNAKERC_API spinLogDataGetPriorityName (
    spinLogEventData hLogEventData,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the priority name of a log event.

See also

[spinError](#)

Parameters

<i>hLogEventData</i>	The log event data received from the log event
<i>pBuf</i>	The c-string character buffer in which the priority name of the log event is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.16.2.6 `spinLogDataGetThreadName()`

```
SPINNAKERC_API spinLogDataGetThreadName (  
    spinLogEventData hLogEventData,  
    char * pBuf,  
    size_t * pBufLen )
```

Retrieves the thread name of a log event.

See also

[spinError](#)

Parameters

<i>hLogEventData</i>	The log event data received from the log event
<i>pBuf</i>	The c-string character buffer in which the thread name of the log event is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.16.2.7 `spinLogDataGetTimestamp()`

```
SPINNAKERC_API spinLogDataGetTimestamp (  
    spinLogEventData hLogEventData,  
    char * pBuf,  
    size_t * pBufLen )
```

Retrieves the timestamp of a log event.

See also

[spinError](#)

Parameters

<i>hLogEventData</i>	The log event data received from the log event
<i>pBuf</i>	The c-string character buffer in which the timestamp of the log event is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.17 Device Event Data Access

The functions in this section allow for the retrieval of device event data.

Functions

- [SPINNAKERC_API spinDeviceEventGetId](#) ([spinDeviceEventData](#) hDeviceEventData, [uint64_t](#) *pEventId)
Retrieves the event ID of a device event.
- [SPINNAKERC_API spinDeviceEventGetPayloadData](#) ([spinDeviceEventData](#) hDeviceEventData, [const uint8_t](#) *pBuf, [size_t](#) *pBufSize)
Retrieves the payload data of a device event.
- [SPINNAKERC_API spinDeviceEventGetPayloadDataSize](#) ([spinDeviceEventData](#) hDeviceEventData, [size_t](#) *pBufSize)
Retrieves the payload data size of a device event.
- [SPINNAKERC_API spinDeviceEventGetName](#) ([spinDeviceEventData](#) hDeviceEventData, [char](#) *pBuf, [size_t](#) *pBufLen)
Retrieves the event name of a device event.

4.17.1 Detailed Description

The functions in this section allow for the retrieval of device event data.

4.17.2 Function Documentation

4.17.2.1 spinDeviceEventGetId()

```
SPINNAKERC_API spinDeviceEventGetId (
    spinDeviceEventData hDeviceEventData,
    uint64_t * pEventId )
```

Retrieves the event ID of a device event.

See also

[spinError](#)

Parameters

<i>hDeviceEventData</i>	The log event data received from the log event
<i>pEventId</i>	The unsigned integer pointer in which the event ID is returned

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.17.2.2 spinDeviceEventGetName()

```
SPINNAKERC_API spinDeviceEventGetName (
    spinDeviceEventData hDeviceEventData,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the event name of a device event.

See also

[spinError](#)

Parameters

<i>hDeviceEventData</i>	The log event data received from the log event
<i>pBuf</i>	The c-string character buffer in which the name of the device event is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.17.2.3 spinDeviceEventGetPayloadData()

```
SPINNAKERC_API spinDeviceEventGetPayloadData (
    spinDeviceEventData hDeviceEventData,
    const uint8_t * pBuf,
    size_t * pBufSize )
```

Retrieves the payload data of a device event.

See also

[spinError](#)

Parameters

<i>hDeviceEventData</i>	The log event data received from the log event
<i>pBuf</i>	The unsigned integer pointer in which the event payload is returned
<i>pBufSize</i>	The unsigned integer pointer in which the size of the payload is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.17.2.4 spinDeviceEventGetPayloadDataSize()

```
SPINNAKERC_API spinDeviceEventGetPayloadDataSize (
    spinDeviceEventData hDeviceEventData,
    size_t * pBufSize )
```

Retrieves the payload data size of a device event.

See also

[spinError](#)

Parameters

<i>hDeviceEventData</i>	The log event data received from the log event
<i>pBufSize</i>	The unsigned integer pointer in which the size of the payload is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.18 Chunk data access

The functions in this section provide access to chunk data stored on images.

Functions

- [SPINNAKERC_API spinImageChunkDataGetIntValue](#) ([spinImage](#) hImage, const char *pName, int64_t *pValue)
- [SPINNAKERC_API spinImageChunkDataGetFloatValue](#) ([spinImage](#) hImage, const char *pName, double *pValue)

4.18.1 Detailed Description

The functions in this section provide access to chunk data stored on images.

4.18.2 Function Documentation

4.18.2.1 spinImageChunkDataGetFloatValue()

```
SPINNAKERC_API spinImageChunkDataGetFloatValue (  
    spinImage hImage,  
    const char * pName,  
    double * pValue )
```


4.18.2.2 spinImageChunkDataGetIntValue()

```
SPINNAKERC_API spinImageChunkDataGetIntValue (  
    spinImage hImage,  
    const char * pName,  
    int64_t * pValue )
```


4.19 Spinnaker C Handles

Spinnaker C handle definitions.

Collaboration diagram for Spinnaker C Handles:



Typedefs

- typedef void * [spinSystem](#)
Handle for system functionality.
- typedef void * [spinInterfaceList](#)
Handle for interface list functionality.
- typedef void * [spinInterface](#)
Handle for interface functionality.
- typedef void * [spinCameraList](#)
Handle for interface functionality.
- typedef void * [spinCamera](#)
Handle for camera functionality.
- typedef void * [spinImage](#)
Handle for image functionality.
- typedef void * [spinImageStatistics](#)
Handle for image statistics functionality.
- typedef void * [spinDeviceEventHandler](#)
Handle for device event handler functionality.
- typedef void * [spinImageEventHandler](#)
Handle for image event handler functionality.
- typedef void * [spinDeviceArrivalEventHandler](#)
Handle for arrival event handler functionality.
- typedef void * [spinDeviceRemovalEventHandler](#)
Handle for removal event handler functionality.
- typedef void * [spinInterfaceEventHandler](#)
Handle for interface event handler functionality.
- typedef void * [spinLogEventHandler](#)
Handle for logging event handler functionality.
- typedef void * [spinLogEventData](#)
Handle for logging event data functionality.
- typedef void * [spinDeviceEventData](#)
Handle for device event data functionality.
- typedef void * [spinVideo](#)
Handle for video recording functionality.

4.19.1 Detailed Description

Spinnaker C handle definitions.

4.19.2 Typedef Documentation

4.19.2.1 spinCamera

```
typedef void* spinCamera
```

Handle for camera functionality.

Created by calling [spinCameraListGet\(\)](#), which requires a call to [spinCameraRelease\(\)](#) to release.

4.19.2.2 spinCameraList

```
typedef void* spinCameraList
```

Handle for interface functionality.

Created by calling [spinSystemGetCameras\(\)](#) or [spinInterfaceGetCameras\(\)](#), which require a call to [spinCameraListClear\(\)](#) to clear, or [spinCameraListCreateEmpty\(\)](#), which requires a call to [spinCameraListDestroy\(\)](#) to destroy.

4.19.2.3 spinDeviceArrivalEventHandler

```
typedef void* spinDeviceArrivalEventHandler
```

Handle for arrival event handler functionality.

Created by calling [spinArrivalEventCreate\(\)](#), which requires a call to [spinDeviceArrivalEventHandlerDestroy\(\)](#) to destroy.

4.19.2.4 spinDeviceEventData

```
typedef void* spinDeviceEventData
```

Handle for device event data functionality.

Received in device event function. No need to release, clear, or destroy.

4.19.2.5 spinDeviceEventHandler

```
typedef void* spinDeviceEventHandler
```

Handle for device event handler functionality.

Created by calling [spinDeviceEventHandlerCreate\(\)](#), which requires a call to [spinDeviceEventHandlerDestroy\(\)](#) to destroy.

4.19.2.6 spinDeviceRemovalEventHandler

```
typedef void* spinDeviceRemovalEventHandler
```

Handle for removal event handler functionality.

Created by calling [spinDeviceRemovalEventHandlerCreate\(\)](#), which requires a call to [spinDeviceRemovalEventHandlerDestroy\(\)](#) to destroy.

4.19.2.7 spinImage

```
typedef void* spinImage
```

Handle for image functionality.

Created by calling [spinCameraGetNextImage\(\)](#) or [spinCameraGetNextImageEx\(\)](#), which require a call to [spinImageRelease\(\)](#) to remove from buffer, or [spinImageCreateEmpty\(\)](#), [spinImageCreateEx\(\)](#), or [spinImageCreate\(\)](#), which require a call to [spinImageDestroy\(\)](#) to destroy.

4.19.2.8 spinImageEventHandler

```
typedef void* spinImageEventHandler
```

Handle for image event handler functionality.

Created by calling [spinImageEventHandlerCreate\(\)](#), which requires a call to [spinImageEventHandlerDestroy\(\)](#) to destroy.

4.19.2.9 spinImageStatistics

```
typedef void* spinImageStatistics
```

Handle for image statistics functionality.

Created by calling [spinImageStatisticsCreate\(\)](#), which requires a call to [spinImageStatisticsDestroy\(\)](#) to destroy.

4.19.2.10 spinInterface

```
typedef void* spinInterface
```

Handle for interface functionality.

Created by calling [spinInterfaceListGet\(\)](#), which requires a call to [spinInterfaceRelease\(\)](#) to release.

4.19.2.11 spinInterfaceEventHandler

```
typedef void* spinInterfaceEventHandler
```

Handle for interface event handler functionality.

Created by calling [spinInterfaceEventHandlerCreate\(\)](#), which requires a call to [spinInterfaceEventHandlerDestroy\(\)](#) to destroy.

4.19.2.12 spinInterfaceList

```
typedef void* spinInterfaceList
```

Handle for interface list functionality.

Created by calling [spinSystemGetInterfaces\(\)](#), which requires a call to [spinInterfaceListClear\(\)](#) to clear, or [spinInterfaceListCreateEmpty\(\)](#), which requires a call to [spinInterfaceListDestroy\(\)](#) to destroy.

4.19.2.13 spinLogEventData

```
typedef void* spinLogEventData
```

Handle for logging event data functionality.

Received in log event function. No need to release, clear, or destroy.

4.19.2.14 spinLogEventHandler

```
typedef void* spinLogEventHandler
```

Handle for logging event handler functionality.

Created by calling [spinLogEventHandlerCreate\(\)](#), which requires a call to [spinLogEventHandlerDestroy\(\)](#) to destroy.

4.19.2.15 spinSystem

```
typedef void* spinSystem
```

Handle for system functionality.

Created by calling [spinSystemGetInstance\(\)](#), which requires a call to [spinSystemReleaseInstance\(\)](#) to release.

4.19.2.16 spinVideo

```
typedef void* spinVideo
```


Handle for video recording functionality.

Created by calling [spinVideoOpenUncompressed\(\)](#), [spinVideoOpenMJPEG\(\)](#), and [spinVideoOpenH264\(\)](#), which require a call to [spinVideoClose\(\)](#) to destroy.

4.20 Spinnaker C Function Signatures

Spinnaker C function signature definitions.

Collaboration diagram for Spinnaker C Function Signatures:



Typedefs

- typedef void(* [spinDeviceEventFunction](#)) (const [spinDeviceEventData](#) hEventData, const char *pEventName, void *pUserData)
- Function signatures are used to create and trigger callbacks and events.*
- typedef void(* [spinImageEventFunction](#)) (const [spinImage](#) hImage, void *pUserData)
 - typedef void(* [spinArrivalEventFunction](#)) (uint64_t deviceSerialNumber, void *pUserData)
 - typedef void(* [spinRemovalEventFunction](#)) (uint64_t deviceSerialNumber, void *pUserData)
 - typedef void(* [spinLogEventFunction](#)) (const [spinLogEventData](#) hEventData, void *pUserData)

4.20.1 Detailed Description

Spinnaker C function signature definitions.

4.20.2 Typedef Documentation

4.20.2.1 spinArrivalEventFunction

```
typedef void(* spinArrivalEventFunction) (uint64_t deviceSerialNumber, void *pUserData)
```

4.20.2.2 spinDeviceEventFunction

```
typedef void(* spinDeviceEventFunction) (const spinDeviceEventData hEventData, const char *pEventName, void *pUserData)
```

Function signatures are used to create and trigger callbacks and events.

4.20.2.3 spinImageEventFunction

```
typedef void(* spinImageEventFunction) (const spinImage hImage, void *pUserData)
```

4.20.2.4 spinLogEventFunction

```
typedef void(* spinLogEventFunction) (const spinLogEventData hEventData, void *pUserData)
```


4.20.2.5 spinRemovalEventFunction

```
typedef void(* spinRemovalEventFunction) (uint64_t deviceSerialNumber, void *pUserData)
```

4.21 Spinnaker C Enumerations

Spinnaker C enumeration definitions.

Collaboration diagram for Spinnaker C Enumerations:



Enumerations

```

• enum spinError {
    SPINNAKER_ERR_SUCCESS = 0,
    SPINNAKER_ERR_ERROR = -1001,
    SPINNAKER_ERR_NOT_INITIALIZED = -1002,
    SPINNAKER_ERR_NOT_IMPLEMENTED = -1003,
    SPINNAKER_ERR_RESOURCE_IN_USE = -1004,
    SPINNAKER_ERR_ACCESS_DENIED = -1005,
    SPINNAKER_ERR_INVALID_HANDLE = -1006,
    SPINNAKER_ERR_INVALID_ID = -1007,
    SPINNAKER_ERR_NO_DATA = -1008,
    SPINNAKER_ERR_INVALID_PARAMETER = -1009,
    SPINNAKER_ERR_IO = -1010,
    SPINNAKER_ERR_TIMEOUT = -1011,
    SPINNAKER_ERR_ABORT = -1012,
    SPINNAKER_ERR_INVALID_BUFFER = -1013,
    SPINNAKER_ERR_NOT_AVAILABLE = -1014,
    SPINNAKER_ERR_INVALID_ADDRESS = -1015,
    SPINNAKER_ERR_BUFFER_TOO_SMALL = -1016,
    SPINNAKER_ERR_INVALID_INDEX = -1017,
    SPINNAKER_ERR_PARSING_CHUNK_DATA = -1018,
    SPINNAKER_ERR_INVALID_VALUE = -1019,
    SPINNAKER_ERR_RESOURCE_EXHAUSTED = -1020,
    SPINNAKER_ERR_OUT_OF_MEMORY = -1021,
    SPINNAKER_ERR_BUSY = -1022,
    GENICAM_ERR_INVALID_ARGUMENT = -2001,
    GENICAM_ERR_OUT_OF_RANGE = -2002,
    GENICAM_ERR_PROPERTY = -2003,
    GENICAM_ERR_RUN_TIME = -2004,
    GENICAM_ERR_LOGICAL = -2005,
    GENICAM_ERR_ACCESS = -2006,
    GENICAM_ERR_TIMEOUT = -2007,
    GENICAM_ERR_DYNAMIC_CAST = -2008,
    GENICAM_ERR_GENERIC = -2009,
    GENICAM_ERR_BAD_ALLOCATION = -2010,
    SPINNAKER_ERR_IM_CONVERT = -3001,
    SPINNAKER_ERR_IM_COPY = -3002,
    SPINNAKER_ERR_IM_MALLOC = -3003,
    SPINNAKER_ERR_IM_NOT_SUPPORTED = -3004,
  
```

```
SPINNAKER_ERR_IM_HISTOGRAM_RANGE = -3005,
SPINNAKER_ERR_IM_HISTOGRAM_MEAN = -3006,
SPINNAKER_ERR_IM_MIN_MAX = -3007,
SPINNAKER_ERR_IM_COLOR_CONVERSION = -3008,
SPINNAKER_ERR_CUSTOM_ID = -10000 }
```

The error codes used in Spinnaker C.

- enum `spinColorProcessingAlgorithm` {
`DEFAULT`,
`NO_COLOR_PROCESSING`,
`NEAREST_NEIGHBOR`,
`NEAREST_NEIGHBOR_AVG`,
`BILINEAR`,
`EDGE_SENSING`,
`HQ_LINEAR`,
`IPP`,
`DIRECTIONAL_FILTER`,
`RIGOROUS`,
`WEIGHTED_DIRECTIONAL_FILTER` }

Color processing algorithms.

- enum `spinStatisticsChannel` {
`GREY`,
`RED`,
`GREEN`,
`BLUE`,
`HUE`,
`SATURATION`,
`LIGHTNESS`,
`NUM_STATISTICS_CHANNELS` }

Channels that allow statistics to be calculated.

- enum `spinImageFileFormat` {
`FROM_FILE_EXT` = -1,
`PGM`,
`PPM`,
`BMP`,
`JPEG`,
`JPEG2000`,
`TIFF`,
`PNG`,
`RAW`,
`IMAGE_FILE_FORMAT_FORCE_32BITS` = 0x7FFFFFFF }

File formats to be used for saving images to disk.

- enum `spinPixelFormatNamespaceID` {
`SPINNAKER_PIXELFORMAT_NAMESPACE_UNKNOWN` = 0,
`SPINNAKER_PIXELFORMAT_NAMESPACE_GEV` = 1,
`SPINNAKER_PIXELFORMAT_NAMESPACE_IIDC` = 2,
`SPINNAKER_PIXELFORMAT_NAMESPACE_PFNC_16BIT` = 3,
`SPINNAKER_PIXELFORMAT_NAMESPACE_PFNC_32BIT` = 4,
`SPINNAKER_PIXELFORMAT_NAMESPACE_CUSTOM_ID` = 1000 }

This enum represents the namespace in which the TL specific pixel format resides.

- enum `spinImageStatus` {
`IMAGE_UNKNOWN_ERROR` = -1,
`IMAGE_NO_ERROR` = 0,
`IMAGE_CRC_CHECK_FAILED` = 1,
`IMAGE_DATA_OVERFLOW` = 2,
`IMAGE_MISSING_PACKETS` = 3,
`IMAGE_LEADER_BUFFER_SIZE_INCONSISTENT` = 4,
`IMAGE_TRAILER_BUFFER_SIZE_INCONSISTENT` = 5,


```

IMAGE_PACKETID_INCONSISTENT = 6,
IMAGE_MISSING_LEADER = 7,
IMAGE_MISSING_TRAILER = 8,
IMAGE_DATA_INCOMPLETE = 9,
IMAGE_INFO_INCONSISTENT = 10,
IMAGE_CHUNK_DATA_INVALID = 11,
IMAGE_NO_SYSTEM_RESOURCES = 12 }

```

Status of images returned from `spinImageGetStatus()` call.

- enum `spinnakerLogLevel` {
`LOG_LEVEL_OFF` = -1,
`LOG_LEVEL_FATAL` = 0,
`LOG_LEVEL_ALERT` = 100,
`LOG_LEVEL_CRIT` = 200,
`LOG_LEVEL_ERROR` = 300,
`LOG_LEVEL_WARN` = 400,
`LOG_LEVEL_NOTICE` = 500,
`LOG_LEVEL_INFO` = 600,
`LOG_LEVEL_DEBUG` = 700,
`LOG_LEVEL_NOTSET` = 800 }

log levels

- enum `spinPayloadTypeInfoIds` {
`PAYLOAD_TYPE_UNKNOWN` = 0,
`PAYLOAD_TYPE_IMAGE` = 1,
`PAYLOAD_TYPE_RAW_DATA` = 2,
`PAYLOAD_TYPE_FILE` = 3,
`PAYLOAD_TYPE_CHUNK_DATA` = 4,
`PAYLOAD_TYPE_JPEG` = 5,
`PAYLOAD_TYPE_JPEG2000` = 6,
`PAYLOAD_TYPE_H264` = 7,
`PAYLOAD_TYPE_CHUNK_ONLY` = 8,
`PAYLOAD_TYPE_DEVICE_SPECIFIC` = 9,
`PAYLOAD_TYPE_MULTI_PART` = 10,
`PAYLOAD_TYPE_CUSTOM_ID` = 1000,
`PAYLOAD_TYPE_EXTENDED_CHUNK` = 1001 }

4.21.1 Detailed Description

Spinnaker C enumeration definitions.

4.21.2 Enumeration Type Documentation

4.21.2.1 `spinColorProcessingAlgorithm`

```
enum spinColorProcessingAlgorithm
```

Color processing algorithms.

Please refer to our knowledge base at article at <https://www.flir.com/support-center/iis/machine-vision/kn> for complete details for each algorithm.

Enumerator

DEFAULT	Default method.
NO_COLOR_PROCESSING	No color processing.
NEAREST_NEIGHBOR	Fastest but lowest quality. Equivalent to FLYCAPTURE_NEAREST_NEIGHBOR_FAST in FlyCapture.
NEAREST_NEIGHBOR_AVG	Nearest Neighbor with averaged green pixels. Higher quality but slower compared to nearest neighbor without averaging.
BILINEAR	Weighted average of surrounding 4 pixels in a 2x2 neighborhood.
EDGE_SENSING	Weights surrounding pixels based on localized edge orientation.
HQ_LINEAR	Well-balanced speed and quality.
IPP	Multi-threaded with similar results to edge sensing.
DIRECTIONAL_FILTER	Best quality but much faster than rigorous.
RIGOROUS	Slowest but produces good results.
WEIGHTED_DIRECTIONAL_FILTER	Weighted pixel average from different directions.

4.21.2.2 spinError

enum `spinError`

The error codes used in Spinnaker C.

These codes are returned from every function in Spinnaker C. The error codes in the range of -2000 to -2999 are reserved for GenICam related errors. The error codes in the range of -3000 to -3999 are reserved for image processing related errors.

Enumerator

SPINNAKER_ERR_SUCCESS	An error code of 0 means that the function has run without error.
SPINNAKER_ERR_ERROR	The error codes in the range of -1000 to -1999 are reserved for Spinnaker exceptions.
SPINNAKER_ERR_NOT_INITIALIZED	
SPINNAKER_ERR_NOT_IMPLEMENTED	
SPINNAKER_ERR_RESOURCE_IN_USE	
SPINNAKER_ERR_ACCESS_DENIED	
SPINNAKER_ERR_INVALID_HANDLE	
SPINNAKER_ERR_INVALID_ID	
SPINNAKER_ERR_NO_DATA	
SPINNAKER_ERR_INVALID_PARAMETER	
SPINNAKER_ERR_IO	
SPINNAKER_ERR_TIMEOUT	
SPINNAKER_ERR_ABORT	
SPINNAKER_ERR_INVALID_BUFFER	
SPINNAKER_ERR_NOT_AVAILABLE	
SPINNAKER_ERR_INVALID_ADDRESS	
SPINNAKER_ERR_BUFFER_TOO_SMALL	
SPINNAKER_ERR_INVALID_INDEX	
SPINNAKER_ERR_PARSING_CHUNK_DATA	

Enumerator

SPINNAKER_ERR_INVALID_VALUE	
SPINNAKER_ERR_RESOURCE_EXHAUSTED	
SPINNAKER_ERR_OUT_OF_MEMORY	
SPINNAKER_ERR_BUSY	
GENICAM_ERR_INVALID_ARGUMENT	The error codes in the range of -2000 to -2999 are reserved for Gen API related errors.
GENICAM_ERR_OUT_OF_RANGE	
GENICAM_ERR_PROPERTY	
GENICAM_ERR_RUN_TIME	
GENICAM_ERR_LOGICAL	
GENICAM_ERR_ACCESS	
GENICAM_ERR_TIMEOUT	
GENICAM_ERR_DYNAMIC_CAST	
GENICAM_ERR_GENERIC	
GENICAM_ERR_BAD_ALLOCATION	
SPINNAKER_ERR_IM_CONVERT	The error codes in the range of -3000 to -3999 are reserved for image processing related errors.
SPINNAKER_ERR_IM_COPY	
SPINNAKER_ERR_IM_MALLOC	
SPINNAKER_ERR_IM_NOT_SUPPORTED	
SPINNAKER_ERR_IM_HISTOGRAM_RANGE	
SPINNAKER_ERR_IM_HISTOGRAM_MEAN	
SPINNAKER_ERR_IM_MIN_MAX	
SPINNAKER_ERR_IM_COLOR_CONVERSION	
SPINNAKER_ERR_CUSTOM_ID	Error codes less than -10000 are reserved for user-defined custom errors.

4.21.2.3 spinImageFileFormat

```
enum spinImageFileFormat
```

File formats to be used for saving images to disk.

Enumerator

FROM_FILE_EXT	Determine file format from file extension.
PGM	Portable gray map.
PPM	Portable pixmap.
BMP	Bitmap.
JPEG	JPEG.
JPEG2000	JPEG 2000.
TIFF	Tagged image file format.
PNG	Portable network graphics.
RAW	Raw data.
IMAGE_FILE_FORMAT_FORCE_32BITS	

4.21.2.4 spinImageStatus

enum `spinImageStatus`

Status of images returned from `spinImageGetStatus()` call.

Enumerator

IMAGE_UNKNOWN_ERROR	Image has an unknown error.
IMAGE_NO_ERROR	Image is returned from <code>GetNextImage()</code> call without any errors.
IMAGE_CRC_CHECK_FAILED	Image failed CRC check.
IMAGE_DATA_OVERFLOW	Received more data than the size of the image.
IMAGE_MISSING_PACKETS	Image has missing packets. Potential fixes include enabling jumbo packets and adjusting packet size/delay. For more information see https://www.flir.com/support-center/iis/machine-vision/application
IMAGE_LEADER_BUFFER_SIZE_INCONSISTENT	Image leader is incomplete. Could be caused by missing packet(s). See link above.
IMAGE_TRAILER_BUFFER_SIZE_INCONSISTENT	Image trailer is incomplete. Could be caused by missing packet(s). See link above.
IMAGE_PACKETID_INCONSISTENT	Image has an inconsistent packet id. Could be caused by missing packet(s). See link above.
IMAGE_MISSING_LEADER	Image leader is missing. Could be caused by missing packet(s). See link above.
IMAGE_MISSING_TRAILER	Image trailer is missing. Could be caused by missing packet(s). See link above.
IMAGE_DATA_INCOMPLETE	Image data is incomplete. Could be caused by missing packet(s). See link above.
IMAGE_INFO_INCONSISTENT	Image info is corrupted. Could be caused by missing packet(s). See link above.
IMAGE_CHUNK_DATA_INVALID	Image chunk data is invalid.
IMAGE_NO_SYSTEM_RESOURCES	Image cannot be processed due to lack of system resources.

4.21.2.5 spinnakerLogLevel

enum `spinnakerLogLevel`

log levels

Enumerator

LOG_LEVEL_OFF	
LOG_LEVEL_FATAL	

Enumerator

LOG_LEVEL_ALERT	
LOG_LEVEL_CRIT	
LOG_LEVEL_ERROR	
LOG_LEVEL_WARN	
LOG_LEVEL_NOTICE	
LOG_LEVEL_INFO	
LOG_LEVEL_DEBUG	
LOG_LEVEL_NOTSET	

4.21.2.6 spinPayloadTypeInfoIDs

```
enum spinPayloadTypeInfoIDs
```

Enumerator

PAYLOAD_TYPE_UNKNOWN	
PAYLOAD_TYPE_IMAGE	
PAYLOAD_TYPE_RAW_DATA	
PAYLOAD_TYPE_FILE	
PAYLOAD_TYPE_CHUNK_DATA	
PAYLOAD_TYPE_JPEG	
PAYLOAD_TYPE_JPEG2000	
PAYLOAD_TYPE_H264	
PAYLOAD_TYPE_CHUNK_ONLY	
PAYLOAD_TYPE_DEVICE_SPECIFIC	
PAYLOAD_TYPE_MULTI_PART	
PAYLOAD_TYPE_CUSTOM_ID	
PAYLOAD_TYPE_EXTENDED_CHUNK	

4.21.2.7 spinPixelFormatNamespaceID

```
enum spinPixelFormatNamespaceID
```

This enum represents the namespace in which the TL specific pixel format resides.

This enum is returned from a captured image when calling [spinImageGetTLPixelFormatNamespace\(\)](#). It can be used to interpret the raw pixel format returned from [spinImageGetTLPixelFormat\(\)](#).

See also

[spinImageGetTLPixelFormat\(\)](#)
[spinImageGetTLPixelFormatNamespace\(\)](#)

Enumerator

SPINNAKER_PIXELFORMAT_NAMESPACE_UNKNOWN	
SPINNAKER_PIXELFORMAT_NAMESPACE_GEV	
SPINNAKER_PIXELFORMAT_NAMESPACE_IIDC	
SPINNAKER_PIXELFORMAT_NAMESPACE_PFNC_16BIT	
SPINNAKER_PIXELFORMAT_NAMESPACE_PFNC_32BIT	
SPINNAKER_PIXELFORMAT_NAMESPACE_CUSTOM_ID	

4.21.2.8 spinStatisticsChannel

enum [spinStatisticsChannel](#)

Channels that allow statistics to be calculated.


Enumerator

GREY	
RED	
GREEN	
BLUE	
HUE	
SATURATION	
LIGHTNESS	
NUM_STATISTICS_CHANNELS	

4.22 Spinnaker C Structures

Spinnaker C structure definitions.

Collaboration diagram for Spinnaker C Structures:



Data Structures

- struct [spinPNGOption](#)
Options for saving PNG images.
- struct [spinPPMOption](#)
Options for saving PPM images.
- struct [spinPGMOption](#)
Options for saving PGM images.
- struct [spinTIFFOption](#)
Options for saving TIFF images.
- struct [spinJPEGOption](#)
Options for saving JPEG images.
- struct [spinJPG2Option](#)
Options for saving JPEG 2000 images.
- struct [spinBMPOption](#)
Options for saving BMP images.
- struct [spinMJPGOption](#)
Options for saving MJPG videos.
- struct [spinH264Option](#)
Options for saving H264 videos.
- struct [spinAVIOption](#)
Options for saving uncompressed videos.
- struct [spinLibraryVersion](#)
Provides easier access to the current version of Spinnaker.
- struct [actionCommandResult](#)
Action Command Result.

Enumerations

- enum [spinCompressionMethod](#) {
[NONE](#) = 1,
[PACKBITS](#),
[DEFLATE](#),
[ADOBE_DEFLATE](#),
[CCITTFAX3](#),
[CCITTFAX4](#),
[LZW](#),
[JPG](#) }

Compression method used in saving TIFF images in the [spinTIFFOption](#) struct.

- enum [actionCommandStatus](#) {
[ACTION_COMMAND_STATUS_OK](#) = 0,
[ACTION_COMMAND_STATUS_NO_REF_TIME](#) = 0x8013,
[ACTION_COMMAND_STATUS_OVERFLOW](#) = 0x8015,
[ACTION_COMMAND_STATUS_ACTION_LATE](#) = 0x8016,
[ACTION_COMMAND_STATUS_ERROR](#) = 0x8FFF }

Possible Status Codes Returned from Action Command.

4.22.1 Detailed Description

Spinnaker C structure definitions.

4.22.2 Enumeration Type Documentation

4.22.2.1 actionCommandStatus

enum [actionCommandStatus](#)

Possible Status Codes Returned from Action Command.

Enumerator

ACTION_COMMAND_STATUS_OK	The device acknowledged the command.
ACTION_COMMAND_STATUS_NO_REF_TIME	
ACTION_COMMAND_STATUS_OVERFLOW	
ACTION_COMMAND_STATUS_ACTION_LATE	
ACTION_COMMAND_STATUS_ERROR	

4.22.2.2 spinCompressionMethod

enum [spinCompressionMethod](#)


Compression method used in saving TIFF images in the [spinTIFFOption](#) struct.

Enumerator

NONE	
PACKBITS	
DEFLATE	
ADOBE_DEFLATE	
CCITTFAX3	
CCITTFAX4	
LZW	
JPG	

4.23 Spinnaker C GenICam API

Collaboration diagram for Spinnaker C GenICam API:



Modules

- [Node Map Access](#)

The functions in this section provide access to information, objects, and functionality related to nodemaps.

- [Node Access](#)

The functions in this section provide access to information and objects retrieved from nodes.

- [IValue Access](#)

The functions in this section provide access to nodes as value nodes.

- [String Access](#)

The functions in this section provide access to string nodes using character pointers and arrays.

- [Integer Access](#)

The functions in this section provide access to integer nodes using the `int64_t` data type.

- [IFloat Access](#)

The functions in this section provide access to float nodes using `double` as the data type.

- [IEnumeration Access](#)

The functions in this section provide access to enum nodes.

- [IEnumEntry Access](#)

The functions in this section provide access to entry nodes This includes retrieving the integer value or the symbolic of an entry.

- [IBoolean Access](#)

The functions in this section provide access to boolean nodes using the `bool8_t` data type, values represented with 'True' and 'False'.

- [ICommand Access](#)

The functions in this section all provide access to information and objects retrieved from nodes.

- [ICategory Access](#)

The functions in this section all provide access to information and objects retrieved from nodes.

- [IRegister Access](#)

The functions in this section provide access to register nodes.

- [Spinnaker C GenICam Handles](#)

Handle definitions for Spinnaker C GenICam API.

- [Spinnaker C GenICam Enumerations](#)

Enumeration definitions for Spinnaker C GenICam API.

4.23.1 Detailed Description

4.24 Node Map Access

The functions in this section provide access to information, objects, and functionality related to nodemaps.

Collaboration diagram for Node Map Access:



Functions

- [SPINNAKERC_API spinNodeMapGetNode](#) ([spinNodeMapHandle](#) hNodeMap, const char *pName, [spin↔NodeHandle](#) *phNode)
Retrieves a node from the nodemap by name.
- [SPINNAKERC_API spinNodeMapGetNumNodes](#) ([spinNodeMapHandle](#) hNodeMap, size_t *pValue)
Gets the number of nodes in the map.
- [SPINNAKERC_API spinNodeMapGetNodeByIndex](#) ([spinNodeMapHandle](#) hNodeMap, size_t index, [spin↔NodeHandle](#) *phNode)
Retrieves a node from the nodemap by index.
- [SPINNAKERC_API spinNodeMapPoll](#) ([spinNodeMapHandle](#) hNodeMap, int64_t timestamp)
Fires nodes which have a polling time.

4.24.1 Detailed Description

The functions in this section provide access to information, objects, and functionality related to nodemaps.

This includes nodes, node counts, and polling.

4.24.2 Function Documentation

4.24.2.1 spinNodeMapGetNode()

```

SPINNAKERC_API spinNodeMapGetNode (
    spinNodeMapHandle hNodeMap,
    const char * pName,
    spinNodeHandle * pNode )
  
```

Retrieves a node from the nodemap by name.

See also

[spinError](#)

Parameters

<i>hNodeMap</i>	The node map where the node is
<i>pName</i>	The name of the node
<i>phNode</i>	The node handle pointer in which the node is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.24.2.2 `spinNodeMapGetNodeByIndex()`

```
SPINNAKERC_API spinNodeMapGetNodeByIndex (
    spinNodeMapHandle hNodeMap,
    size_t index,
    spinNodeHandle * phNode )
```

Retrieves a node from the nodemap by index.

See also

[spinError](#)

Parameters

<i>hNodeMap</i>	The node map where the node is
<i>index</i>	The index of the node
<i>phNode</i>	The node handle pointer in which the node is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.24.2.3 `spinNodeMapGetNumNodes()`

```
SPINNAKERC_API spinNodeMapGetNumNodes (
    spinNodeMapHandle hNodeMap,
    size_t * pValue )
```

Gets the number of nodes in the map.

See also

[spinError](#)

Parameters

<i>hNodeMap</i>	The node map where the nodes to be counted are
<i>pValue</i>	The unsigned integer pointer in which the number of nodes is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.24.2.4 `spinNodeMapPoll()`

```
SPINNAKERC_API spinNodeMapPoll (  
    spinNodeMapHandle hNodeMap,  
    int64_t timestamp )
```

Fires nodes which have a polling time.

See also

[spinError](#)

Parameters

<i>hNodeMap</i>	The nodemap to poll
<i>timestamp</i>	The timestamp

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.25 Node Access

The functions in this section provide access to information and objects retrieved from nodes.

Collaboration diagram for Node Access:



Functions

- [SPINNAKERC_API spinNodesImplemented](#) ([spinNodeHandle](#) hNode, [bool8_t](#) *pbResult)
Checks whether a node is implemented.
- [SPINNAKERC_API spinNodesReadable](#) ([spinNodeHandle](#) hNode, [bool8_t](#) *pbResult)
Checks whether a node is readable.
- [SPINNAKERC_API spinNodesWritable](#) ([spinNodeHandle](#) hNode, [bool8_t](#) *pbResult)
Checks whether a node is writable.
- [SPINNAKERC_API spinNodesAvailable](#) ([spinNodeHandle](#) hNode, [bool8_t](#) *pbResult)
Checks whether a node is available.
- [SPINNAKERC_API spinNodesEqual](#) ([spinNodeHandle](#) hNodeFirst, [spinNodeHandle](#) hNodeSecond, [bool8_t](#) *pbResult)
Checks whether two nodes are equal.
- [SPINNAKERC_API spinNodeGetAccessMode](#) ([spinNodeHandle](#) hNode, [spinAccessMode](#) *pAccessMode)
Retrieves the access mode of a node (as an enum, spinAccessMode)
- [SPINNAKERC_API spinNodeGetName](#) ([spinNodeHandle](#) hNode, [char](#) *pBuf, [size_t](#) *pBufLen)
Retrieves the name of a node (no whitespace)
- [SPINNAKERC_API spinNodeGetNameSpace](#) ([spinNodeHandle](#) hNode, [spinNameSpace](#) *pNamespace)
Retrieve the namespace of a node (as an enum, spinNameSpace)
- [SPINNAKERC_API spinNodeGetVisibility](#) ([spinNodeHandle](#) hNode, [spinVisibility](#) *pVisibility)
Retrieves the recommended visibility of a node (as an enum, spinVisibility)
- [SPINNAKERC_API spinNodeInvalidateNode](#) ([spinNodeHandle](#) hNode)
Invalidates a node in case its values may have changed, rendering it no longer valid.
- [SPINNAKERC_API spinNodeGetCachingMode](#) ([spinNodeHandle](#) hNode, [spinCachingMode](#) *pCachingMode)
Retrieves the caching mode of a node (as an enum, spinCachingMode)
- [SPINNAKERC_API spinNodeGetToolTip](#) ([spinNodeHandle](#) hNode, [char](#) *pBuf, [size_t](#) *pBufLen)
Retrieves a short description of a node.
- [SPINNAKERC_API spinNodeGetDescription](#) ([spinNodeHandle](#) hNode, [char](#) *pBuf, [size_t](#) *pBufLen)
Retrieves a longer description of a node.
- [SPINNAKERC_API spinNodeGetDisplayName](#) ([spinNodeHandle](#) hNode, [char](#) *pBuf, [size_t](#) *pBufLen)
Retrieves the display name of a node (whitespace possible)
- [SPINNAKERC_API spinNodeGetType](#) ([spinNodeHandle](#) hNode, [spinNodeType](#) *pType)
Retrieves the type of a node (as an enum, spinNodeType)
- [SPINNAKERC_API spinNodeGetPollingTime](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pPollingTime)

Retrieve the polling time of a node.

- [SPINNAKERC_API spinNodeRegisterCallback](#) ([spinNodeHandle](#) hNode, [spinNodeCallbackFunction](#) pCb↔
Function, [spinNodeCallbackHandle](#) *phCb)

Registers a callback to a node.

- [SPINNAKERC_API spinNodeDeregisterCallback](#) ([spinNodeHandle](#) hNode, [spinNodeCallbackHandle](#) hCb)

Unregisters a callback from a node.

- [SPINNAKERC_API spinNodeGetImposedAccessMode](#) ([spinNodeHandle](#) hNode, [spinAccessMode](#) imposedAccessMode)

Retrieves the imposed access mode of a node.

- [SPINNAKERC_API spinNodeGetImposedVisibility](#) ([spinNodeHandle](#) hNode, [spinVisibility](#) imposedVisibility)

Retrieves the imposed visibility of a node.

4.25.1 Detailed Description

The functions in this section provide access to information and objects retrieved from nodes.

This includes node properties and callback registration.

4.25.2 Function Documentation

4.25.2.1 spinNodeDeregisterCallback()

```
SPINNAKERC_API spinNodeDeregisterCallback (
    spinNodeHandle hNode,
    spinNodeCallbackHandle hCb )
```

Unregisters a callback from a node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node from which to unregister the callback
<i>hCb</i>	The callback handle to unregister

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.2 spinNodeGetAccessMode()

```
SPINNAKERC_API spinNodeGetAccessMode (
    spinNodeHandle hNode,
    spinAccessMode * pAccessMode )
```

Retrieves the access mode of a node (as an enum, spinAccessMode)

See also

[spinError](#)
[spinAccessMode](#)

Parameters

<i>hNode</i>	The node of the access mode to retrieve
<i>pAccessMode</i>	The access mode enum pointer in which the access mode is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.3 spinNodeGetCachingMode()

```
SPINNAKERC_API spinNodeGetCachingMode (
    spinNodeHandle hNode,
    spinCachingMode * pCachingMode )
```

Retrieves the caching mode of a node (as an enum, spinCachingMode)

See also

[spinError](#)
[spinCachingMode](#)

Parameters

<i>hNode</i>	The node of the caching mode to retrieve
<i>pCachingMode</i>	The caching mode enum pointer in which the caching mode is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.4 spinNodeGetDescription()

```
SPINNAKERC_API spinNodeGetDescription (
    spinNodeHandle hNode,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves a longer description of a node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node of the description to retrieve
<i>pBuf</i>	The c-string character buffer in which the longer description of the node is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.5 spinNodeGetDisplayName()

```
SPINNAKERC_API spinNodeGetDisplayName (
    spinNodeHandle hNode,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the display name of a node (whitespace possible)

See also

[spinError](#)

Parameters

<i>hNode</i>	The node of the display name to retrieve
<i>pBuf</i>	The c-string character buffer in which the display name of the node is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.6 spinNodeGetImposedAccessMode()

```
SPINNAKERC_API spinNodeGetImposedAccessMode (
    spinNodeHandle hNode,
    spinAccessMode imposedAccessMode )
```

Retrieves the imposed access mode of a node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node of the imposed access mode to retrieve
<i>imposedAccessMode</i>	The access mode enum pointer in which the imposed access mode is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.7 spinNodeGetImposedVisibility()

```
SPINNAKERC_API spinNodeGetImposedVisibility (
    spinNodeHandle hNode,
    spinVisibility imposedVisibility )
```

Retrieves the imposed visibility of a node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node of the visibility to impose
<i>imposedVisibility</i>	The visibility enum pointer in which the imposed visibility is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.8 spinNodeGetName()

```
SPINNAKERC_API spinNodeGetName (
    spinNodeHandle hNode,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the name of a node (no whitespace)

See also

[spinError](#)

Parameters

<i>hNode</i>	The node of the name to retrieve
<i>pBuf</i>	The c-string character buffer in which the name of the node is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.9 spinNodeGetNamespace()

```
SPINNAKERC_API spinNodeGetNamespace (
    spinNodeHandle hNode,
    spinNamespace * pNamespace )
```

Retrieve the namespace of a node (as an enum, spinNamespace)

See also

[spinError](#)
[spinNamespace](#)

Parameters

<i>hNode</i>	The node of the namespace to retrieve
<i>pNamespace</i>	The namespace enum pointer in which the namespace is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.10 spinNodeGetPollingTime()

```
SPINNAKERC_API spinNodeGetPollingTime (
    spinNodeHandle hNode,
    int64_t * pPollingTime )
```

Retrieve the polling time of a node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node of the polling time to retrieve
<i>pPollingTime</i>	The integer pointer in which the polling time is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.11 spinNodeGetToolTip()

```
SPINNAKERC_API spinNodeGetToolTip (
    spinNodeHandle hNode,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves a short description of a node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node of the tooltip to retrieve
<i>pBuf</i>	The c-string character buffer in which the short description of the node is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.12 spinNodeGetType()

```
SPINNAKERC_API spinNodeGetType (
    spinNodeHandle hNode,
    spinNodeType * pType )
```

Retrieves the type of a node (as an enum, spinNodeType)

See also

[spinError](#)
[spinNodeType](#)

Parameters

<i>hNode</i>	The node of the node type to retrieve
<i>pType</i>	The node type enum pointer in which the type of node is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.13 spinNodeGetVisibility()

```
SPINNAKERC_API spinNodeGetVisibility (
    spinNodeHandle hNode,
    spinVisibility * pVisibility )
```

Retrieves the recommended visibility of a node (as an enum, spinVisibility)

See also

[spinError](#)
[spinVisibility](#)

Parameters

<i>hNode</i>	The node of the visibility to retrieve
<i>pVisibility</i>	The visibility enum pointer in which the visibility is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.14 spinNodeInvalidateNode()

```
SPINNAKERC_API spinNodeInvalidateNode (
    spinNodeHandle hNode )
```

Invalidates a node in case its values may have changed, rendering it no longer valid.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node whose values may have changed
--------------	--

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.15 spinNodesAvailable()

```
SPINNAKERC_API spinNodeIsAvailable (
    spinNodeHandle hNode,
    bool8_t * pbResult )
```

Checks whether a node is available.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node to check
<i>pbResult</i>	The boolean pointer to return whether or not the node is available

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.16 spinNodesEqual()

```
SPINNAKERC_API spinNodeIsEqual (
    spinNodeHandle hNodeFirst,
```

```
spinNodeHandle hNodeSecond,  
bool8_t * pbResult )
```

Checks whether two nodes are equal.

See also

[spinError](#)

Parameters

<i>hNodeFirst</i>	The first node to check
<i>hNodeSecond</i>	The second node to check
<i>pbResult</i>	The boolean pointer to return whether or not the two nodes are equal

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.17 spinNodesImplemented()

```
SPINNAKERC_API spinNodeIsImplemented (   
    spinNodeHandle hNode,  
    bool8_t * pbResult )
```

Checks whether a node is implemented.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node to check
<i>pbResult</i>	The boolean pointer to return whether or not the node is implemented

Returns

[spinError](#) The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.25.2.18 spinNodesReadable()

```
SPINNAKERC_API spinNodeIsReadable (   
    spinNodeHandle hNode,  
    bool8_t * pbResult )
```

Checks whether a node is readable.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node to check
<i>pbResult</i>	The boolean pointer to return whether or not the node is readable

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.25.2.19 `spinNodesWritable()`

```
SPINNAKERC_API spinNodeIsWritable (
    spinNodeHandle hNode,
    bool8_t * pbResult )
```

Checks whether a node is writable.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node to check
<i>pbResult</i>	The boolean pointer to return whether or not the node is writable

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.25.2.20 `spinNodeRegisterCallback()`

```
SPINNAKERC_API spinNodeRegisterCallback (
    spinNodeHandle hNode,
    spinNodeCallbackFunction pCbFunction,
    spinNodeCallbackHandle * phCb )
```

Registers a callback to a node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node on which to register the callback
<i>pCbFunction</i>	The function pointer of the function that will execute when the callback is triggered; must match signature "void spinNodeCallbackFunction(spinNodeHandle hNode)"
<i>phCb</i>	The callback handle pointer in which the callback is returned; used to unregister callbacks


Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.26 IValue Access

The functions in this section provide access to nodes as value nodes.

Collaboration diagram for IValue Access:



Functions

- [SPINNAKERC_API spinNodeToString](#) ([spinNodeHandle](#) hNode, char *pBuf, size_t *pBufLen)
Retrieves the value of any node type as a c-string.
- [SPINNAKERC_API spinNodeToStringEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, char *pBuf, size_t *pBufLen)
Retrieves the value of any node type as a c-string; manually set whether to verify the node.
- [SPINNAKERC_API spinNodeFromString](#) ([spinNodeHandle](#) hNode, const char *pBuf)
Sets the value of any node type from a c-string; it is important to ensure that the value of the c-string is appropriate to the node type.
- [SPINNAKERC_API spinNodeFromStringEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, const char *pBuf)
Sets the value of any node type from a c-string; manually set whether to verify the node; ensure the value of the c-string is appropriate to the node type.

4.26.1 Detailed Description

The functions in this section provide access to nodes as value nodes.

As value nodes are not an actual node type, the functions are named as regular nodes. Functions include reading from and writing to any node with a string.

4.26.2 Function Documentation

4.26.2.1 spinNodeFromString()

```

SPINNAKERC_API spinNodeFromString (
    spinNodeHandle hNode,
    const char * pBuf )
  
```

Sets the value of any node type from a c-string; it is important to ensure that the value of the c-string is appropriate to the node type.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node having its value changed
<i>pBuf</i>	The c-string of the value to set

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.26.2.2 `spinNodeFromStringEx()`

```
SPINNAKERC_API spinNodeFromStringEx (
    spinNodeHandle hNode,
    bool8_t bVerify,
    const char * pBuf )
```

Sets the value of any node type from a c-string; manually set whether to verify the node; ensure the value of the c-string is appropriate to the node type.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node having its value changed
<i>bVerify</i>	The boolean of whether to verify the node
<i>pBuf</i>	The c-string of the value to set

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.26.2.3 `spinNodeToString()`

```
SPINNAKERC_API spinNodeToString (
    spinNodeHandle hNode,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the value of any node type as a c-string.

See also

[spinError](#)

Parameters

<i>hNode</i>	The node of the value to read
<i>pBuf</i>	The c-string character buffer in which the value of the node is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.26.2.4 `spinNodeToStringEx()`

```
SPINNAKERC_API spinNodeToStringEx (
    spinNodeHandle hNode,
    bool8_t bVerify,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the value of any node type as a c-string; manually set whether to verify the node.

See also

[`spinError`](#)

Parameters

<i>hNode</i>	The node of the value to read
<i>bVerify</i>	The boolean of whether to verify the node
<i>pBuf</i>	The c-string character buffer in which the value of the node is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length


Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.27 String Access

The functions in this section provide access to string nodes using character pointers and arrays.

Collaboration diagram for String Access:



Functions

- [SPINNAKERC_API spinStringSetValue](#) ([spinNodeHandle](#) hNode, const char *pBuf)
Sets the value of a string node.
- [SPINNAKERC_API spinStringSetValueEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, const char *pBuf)
Sets the value of a string node; manually set whether to verify the node.
- [SPINNAKERC_API spinStringGetValue](#) ([spinNodeHandle](#) hNode, char *pBuf, [size_t](#) *pBufLen)
Retrieves the value of a string node as a c-string.
- [SPINNAKERC_API spinStringGetValueEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, char *pBuf, [size_t](#) *pBufLen)
Retrieves the value of a string node as a cstring; manually set whether to verify the node.
- [SPINNAKERC_API spinStringGetMaxLength](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pValue)
Retrieves the maximum length of the c-string to be returned.

4.27.1 Detailed Description

The functions in this section provide access to string nodes using character pointers and arrays.

This includes getters and setters of values and value lengths.

4.27.2 Function Documentation

4.27.2.1 spinStringGetMaxLength()

```

SPINNAKERC_API spinStringGetMaxLength (
    spinNodeHandle hNode,
    int64_t * pValue )
  
```

Retrieves the maximum length of the c-string to be returned.

See also

[spinError](#)

Parameters

<i>hNode</i>	The string node of the length to retrieve
<i>pValue</i>	The integer pointer in which the maximum length of the c-string is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.27.2.2 `spinStringGetValue()`

```
SPINNAKERC_API spinStringGetValue (
    spinNodeHandle hNode,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the value of a string node as a c-string.

See also

[spinError](#)

Parameters

<i>hNode</i>	The string node of the value to read
<i>pBuf</i>	The c-string character buffer in which the value of the node is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.27.2.3 `spinStringGetValueEx()`

```
SPINNAKERC_API spinStringGetValueEx (
    spinNodeHandle hNode,
    bool8_t bVerify,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the value of a string node as a cstring; manually set whether to verify the node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The string node of the value to read
<i>bVerify</i>	The boolean of whether to verify the node
<i>pBuf</i>	The c-string character buffer in which the value of the node is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.27.2.4 `spinStringSetValue()`

```
SPINNAKERC_API spinStringSetValue (  
    spinNodeHandle hNode,  
    const char * pBuf )
```

Sets the value of a string node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The string node having its value changed
<i>pBuf</i>	The c-string of the value to set

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.27.2.5 `spinStringSetValueEx()`

```
SPINNAKERC_API spinStringSetValueEx (  
    spinNodeHandle hNode,  
    bool8_t bVerify,  
    const char * pBuf )
```

Sets the value of a string node; manually set whether to verify the node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The string node having its value changed
<i>bVerify</i>	The boolean of whether to verify the node
<i>pBuf</i>	The c-string of the value to set

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.28 Integer Access

The functions in this section provide access to integer nodes using the `int64_t` data type.

Collaboration diagram for Integer Access:



Functions

- [SPINNAKERC_API spinIntegerSetValue](#) ([spinNodeHandle](#) hNode, `int64_t` value)
Sets the value of an integer node.
- [SPINNAKERC_API spinIntegerSetValueEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, `int64_t` value)
Sets the value of an integer node; manually set whether to verify the node.
- [SPINNAKERC_API spinIntegerGetValue](#) ([spinNodeHandle](#) hNode, `int64_t` *pValue)
Retrieves the value of an integer node.
- [SPINNAKERC_API spinIntegerGetValueEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, `int64_t` *pValue)
Retrieves the value of an integer node; manually set whether to verify the node.
- [SPINNAKERC_API spinIntegerGetMin](#) ([spinNodeHandle](#) hNode, `int64_t` *pValue)
Retrieves the minimum value of an integer node; all potential values must be greater than or equal to the minimum.
- [SPINNAKERC_API spinIntegerGetMax](#) ([spinNodeHandle](#) hNode, `int64_t` *pValue)
Retrieves the maximum value of an integer node; all potential values must be lesser than or equal to the maximum.
- [SPINNAKERC_API spinIntegerGetInc](#) ([spinNodeHandle](#) hNode, `int64_t` *pValue)
Retrieves the increment of an integer node; all possible values must be divisible by the increment.
- [SPINNAKERC_API spinIntegerGetRepresentation](#) ([spinNodeHandle](#) hNode, [spinRepresentation](#) *pValue)
Retrieves the numerical representation of the value of a node; i.e.

4.28.1 Detailed Description

The functions in this section provide access to integer nodes using the `int64_t` data type.

This includes value getters and setters, min, max, and increment functions, and node representation.

4.28.2 Function Documentation

4.28.2.1 spinIntegerGetInc()

```

SPINNAKERC_API spinIntegerGetInc (
    spinNodeHandle hNode,
    int64_t * pValue )
  
```

Retrieves the increment of an integer node; all possible values must be divisible by the increment.

See also

[spinError](#)

Parameters

<i>hNode</i>	The integer node of the increment to retrieve
<i>pValue</i>	The integer pointer in which the increment is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.28.2.2 spinIntegerGetMax()

```
SPINNAKERC_API spinIntegerGetMax (  
    spinNodeHandle hNode,  
    int64_t * pValue )
```

Retrieves the maximum value of an integer node; all potential values must be lesser than or equal to the maximum.

See also

[spinError](#)

Parameters

<i>hNode</i>	The integer node of the maximum value to retrieve
<i>pValue</i>	The integer pointer in which the maximum value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.28.2.3 spinIntegerGetMin()

```
SPINNAKERC_API spinIntegerGetMin (  
    spinNodeHandle hNode,  
    int64_t * pValue )
```

Retrieves the minimum value of an integer node; all potential values must be greater than or equal to the minimum.

See also

[spinError](#)

Parameters

<i>hNode</i>	The integer node of the minimum value to retrieve
<i>pValue</i>	The integer pointer in which the minimum value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.28.2.4 `spinIntegerGetRepresentation()`

```
SPINNAKERC_API spinIntegerGetRepresentation (
    spinNodeHandle hNode,
    spinRepresentation * pValue )
```

Retrieves the numerical representation of the value of a node; i.e.

linear, logarithmic, hexadecimal, MAC address, etc.

See also

[spinError](#)

Parameters

<i>hNode</i>	The integer node of the numerical representation to retrieve
<i>pValue</i>	The representation enum pointer in which the type of numerical representation is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.28.2.5 `spinIntegerGetValue()`

```
SPINNAKERC_API spinIntegerGetValue (
    spinNodeHandle hNode,
    int64_t * pValue )
```

Retrieves the value of an integer node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The integer node of the value to read
<i>pValue</i>	The integer pointer in which the value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.28.2.6 spinIntegerGetValueEx()

```
SPINNAKERC_API spinIntegerGetValueEx (
    spinNodeHandle hNode,
    bool8_t bVerify,
    int64_t * pValue )
```

Retrieves the value of an integer node; manually set whether to verify the node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The integer node of the value to read
<i>bVerify</i>	The boolean of whether to verify the node
<i>pValue</i>	The integer pointer in which the value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.28.2.7 spinIntegerSetValue()

```
SPINNAKERC_API spinIntegerSetValue (
    spinNodeHandle hNode,
    int64_t value )
```

Sets the value of an integer node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The integer node having its value changed
<i>value</i>	The integer value to set

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.28.2.8 `spinIntegerSetValueEx()`

```
SPINNAKERC_API spinIntegerSetValueEx (  
    spinNodeHandle hNode,  
    bool8_t bVerify,  
    int64_t value )
```

Sets the value of an integer node; manually set whether to verify the node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The integer node having its value changed
<i>bVerify</i>	The boolean of whether to verify the node
<i>value</i>	The integer value to set


Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.29 IFloat Access

The functions in this section provide access to float nodes using double as the data type.

Collaboration diagram for IFloat Access:



Functions

- [SPINNAKERC_API spinFloatSetValue](#) ([spinNodeHandle](#) hNode, double value)
Sets the value of a float node.
- [SPINNAKERC_API spinFloatSetValueEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, double value)
Sets the value of a float node; manually set whether to verify the node.
- [SPINNAKERC_API spinFloatGetValue](#) ([spinNodeHandle](#) hNode, double *pValue)
Retrieves the value of a float node.
- [SPINNAKERC_API spinFloatGetValueEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, double *pValue)
Retrieves the value of a float node; manually set whether to verify the node.
- [SPINNAKERC_API spinFloatGetMin](#) ([spinNodeHandle](#) hNode, double *pValue)
Retrieves the minimum value of a float node; all potential values must be greater than or equal to the minimum.
- [SPINNAKERC_API spinFloatGetMax](#) ([spinNodeHandle](#) hNode, double *pValue)
Retrieves the maximum value of a float node; all potential values must be lesser than or equal to the maximum.
- [SPINNAKERC_API spinFloatGetRepresentation](#) ([spinNodeHandle](#) hNode, [spinRepresentation](#) *pValue)
Retrieves the numerical representation of the value of a node; i.e.
- [SPINNAKERC_API spinFloatGetUnit](#) ([spinNodeHandle](#) hNode, char *pBuf, [size_t](#) *pBufLen)
Retrieves the units of the float node value.

4.29.1 Detailed Description

The functions in this section provide access to float nodes using double as the data type.

This includes value getters and setters, min and max functions, and node representation.

4.29.2 Function Documentation

4.29.2.1 spinFloatGetMax()

```

SPINNAKERC_API spinFloatGetMax (
    spinNodeHandle hNode,
    double * pValue )
  
```

Retrieves the maximum value of a float node; all potential values must be lesser than or equal to the maximum.

See also

[spinError](#)

Parameters

<i>hNode</i>	The float node of the maximum value to retrieve
<i>pValue</i>	The double pointer in which the maximum value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.29.2.2 `spinFloatGetMin()`

```
SPINNAKERC_API spinFloatGetMin (  
    spinNodeHandle hNode,  
    double * pValue )
```

Retrieves the minimum value of a float node; all potential values must be greater than or equal to the minimum.

See also

[spinError](#)

Parameters

<i>hNode</i>	The float node of the minimum value to retrieve
<i>pValue</i>	The double pointer in which the minimum value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.29.2.3 `spinFloatGetRepresentation()`

```
SPINNAKERC_API spinFloatGetRepresentation (  
    spinNodeHandle hNode,  
    spinRepresentation * pValue )
```

Retrieves the numerical representation of the value of a node; i.e.

linear, logarithmic, hexadecimal, MAC address, etc.

See also

[spinError](#)

Parameters

<i>hNode</i>	The float node of the numerical representation to retrieve
<i>pValue</i>	The representation enum pointer in which the type of numerical representation is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.29.2.4 `spinFloatGetUnit()`

```
SPINNAKERC_API spinFloatGetUnit (
    spinNodeHandle hNode,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the units of the float node value.

See also

[spinError](#)

Parameters

<i>hNode</i>	The float node of the units to retrieve
<i>pBuf</i>	The c-string character buffer in which the value units are returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.29.2.5 `spinFloatGetValue()`

```
SPINNAKERC_API spinFloatGetValue (
    spinNodeHandle hNode,
    double * pValue )
```

Retrieves the value of a float node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The float node of the value to read
<i>pValue</i>	The double pointer in which the value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.29.2.6 `spinFloatGetValueEx()`

```
SPINNAKERC_API spinFloatGetValueEx (
    spinNodeHandle hNode,
    bool8_t bVerify,
    double * pValue )
```

Retrieves the value of a float node; manually set whether to verify the node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The float node of the value to read
<i>pValue</i>	The double pointer in which the value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.29.2.7 `spinFloatSetValue()`

```
SPINNAKERC_API spinFloatSetValue (
    spinNodeHandle hNode,
    double value )
```

Sets the value of a float node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The float node having its value changed
<i>value</i>	The float value to set

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.29.2.8 spinFloatSetValueEx()

```
SPINNAKERC_API spinFloatSetValueEx (  
    spinNodeHandle hNode,  
    bool8_t bVerify,  
    double value )
```

Sets the value of a float node; manually set whether to verify the node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The float node having its value changed
<i>bVerify</i>	The boolean of whether to verify the node
<i>value</i>	The float value to set


Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.30 IEnumeration Access

The functions in this section provide access to enum nodes.

Collaboration diagram for IEnumeration Access:



Functions

- [SPINNAKERC_API spinEnumerationGetNumEntries](#) ([spinNodeHandle](#) hNode, [size_t](#) *pValue)
Retrieves the number of entries of an enum node.
- [SPINNAKERC_API spinEnumerationGetEntryByIndex](#) ([spinNodeHandle](#) hNode, [size_t](#) index, [spinNodeHandle](#) *phEntry)
Retrieves an entry node from an enum node using an index.
- [SPINNAKERC_API spinEnumerationGetEntryByName](#) ([spinNodeHandle](#) hNode, [const char](#) *pName, [spinNodeHandle](#) *phEntry)
Retrieves an entry node from an enum node using the entry's symbolic.
- [SPINNAKERC_API spinEnumerationGetCurrentEntry](#) ([spinNodeHandle](#) hNode, [spinNodeHandle](#) *phEntry)
Retrieves the currently selected entry node from an enum node.
- [SPINNAKERC_API spinEnumerationSetIntValue](#) ([spinNodeHandle](#) hNode, [int64_t](#) value)
Sets a new entry using its integer value retrieved from a call to [spinEnumerationEntryGetIntValue\(\)](#); note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).
- [SPINNAKERC_API spinEnumerationSetEnumValue](#) ([spinNodeHandle](#) hNode, [size_t](#) value)
Sets a new entry using its enum; note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).

4.30.1 Detailed Description

The functions in this section provide access to enum nodes.

This includes retrieving the number of entries, an entry by index or name, retrieving the current entry node, or setting the node using an integer.

4.30.2 Function Documentation

4.30.2.1 spinEnumerationGetCurrentEntry()

```
SPINNAKERC_API spinEnumerationGetCurrentEntry (
    spinNodeHandle hNode,
    spinNodeHandle * phEntry )
```

Retrieves the currently selected entry node from an enum node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The enum node from which the current entry node is retrieved
<i>phEntry</i>	The node handle pointer in which the current entry node is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.30.2.2 spinEnumerationGetEntryByIndex()

```
SPINNAKERC_API spinEnumerationGetEntryByIndex (
    spinNodeHandle hNode,
    size_t index,
    spinNodeHandle * phEntry )
```

Retrieves an entry node from an enum node using an index.

See also

[spinError](#)

Parameters

<i>hNode</i>	The enum node from which the entry node is retrieved
<i>index</i>	The index of the entry node
<i>phEntry</i>	The node handle pointer in which the entry node is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.30.2.3 spinEnumerationGetEntryByName()

```
SPINNAKERC_API spinEnumerationGetEntryByName (
    spinNodeHandle hNode,
    const char * pName,
    spinNodeHandle * phEntry )
```

Retrieves an entry node from an enum node using the entry's symbolic.

See also

[spinError](#)

Parameters

<i>hNode</i>	The enum node from which the entry node is retrieved
<i>pName</i>	The name of the entry node
<i>phEntry</i>	The node handle pointer in which the entry node is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.30.2.4 spinEnumerationGetNumEntries()

```
SPINNAKERC_API spinEnumerationGetNumEntries (
    spinNodeHandle hNode,
    size_t * pValue )
```

Retrieves the number of entries of an enum node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The enum node where the entries to be counted are
<i>pValue</i>	The unsigned integer pointer in which the number of entries is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.30.2.5 spinEnumerationSetEnumValue()

```
SPINNAKERC_API spinEnumerationSetEnumValue (
    spinNodeHandle hNode,
    size_t value )
```

Sets a new entry using its enum; note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).

See also

[spinEnumerationEntryGetEnumValue\(\)](#)
[spinError](#)

Parameters

<i>hNode</i>	The enum node have its entry changed
<i>value</i>	The enum value of the entry node to set; this corresponds to its integer value created in the library

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.30.2.6 `spinEnumerationSetIntValue()`

```
SPINNAKERC_API spinEnumerationSetIntValue (
    spinNodeHandle hNode,
    int64_t value )
```

Sets a new entry using its integer value retrieved from a call to [spinEnumerationEntryGetIntValue\(\)](#); note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [Spinnaker↔ DefsC.h](#).

See also

[spinEnumerationEntryGetIntValue\(\)](#)
[spinError](#)

Parameters

<i>hNode</i>	The enum node having its entry changed
<i>value</i>	The integer value of the entry node to set; this corresponds to the integer value internal to the camera

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.31 IEnumEntry Access

The functions in this section provide access to entry nodes This includes retrieving the integer value or the symbolic of an entry.

Collaboration diagram for IEnumEntry Access:



Functions

- [SPINNAKERC_API spinEnumerationEntryGetIntValue](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pValue)
Retrieves the integer value of an entry node; note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).
- [SPINNAKERC_API spinEnumerationEntryGetEnumValue](#) ([spinNodeHandle](#) hNode, [size_t](#) *pValue)
Retrieves the enum value (as an integer) of an entry node; note that enumeraiton entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).
- [SPINNAKERC_API spinEnumerationEntryGetSymbolic](#) ([spinNodeHandle](#) hNode, [char](#) *pBuf, [size_t](#) *pBufLen)
Retrieves the symbolic of an entry node as a c-string.

4.31.1 Detailed Description

The functions in this section provide access to entry nodes This includes retrieving the integer value or the symbolic of an entry.

4.31.2 Function Documentation

4.31.2.1 spinEnumerationEntryGetEnumValue()

```
SPINNAKERC_API spinEnumerationEntryGetEnumValue (
    spinNodeHandle hNode,
    size_t * pValue )
```

Retrieves the enum value (as an integer) of an entry node; note that enumeraiton entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).

See also

[spinEnumerationSetEnumValue\(\)](#)
[spinError](#)

Parameters

<i>hNode</i>	The entry node of the enum value to retrieve
<i>pValue</i>	The unsigned integer pointer in which the enum value of the entry is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.31.2.2 `spinEnumerationEntryGetIntValue()`

```
SPINNAKERC_API spinEnumerationEntryGetIntValue (
    spinNodeHandle hNode,
    int64_t * pValue )
```

Retrieves the integer value of an entry node; note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).

See also

[spinEnumerationSetIntValue\(\)](#)
[spinError](#)

Parameters

<i>hNode</i>	The entry node of the integer value to retrieve
<i>pValue</i>	The integer pointer in which the integer value of the entry is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.31.2.3 `spinEnumerationEntryGetSymbolic()`

```
SPINNAKERC_API spinEnumerationEntryGetSymbolic (
    spinNodeHandle hNode,
    char * pBuf,
    size_t * pBufLen )
```

Retrieves the symbolic of an entry node as a c-string.

See also

[spinError](#)

Parameters

<i>hNode</i>	The entry node of the symbolic to retrieve
<i>pBuf</i>	The c-string character buffer in which the symbolic of the entry node is returned
<i>pBufLen</i>	The unsigned integer pointer in which the length of the c-string is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.32 IBoolean Access

The functions in this section provide access to boolean nodes using the `bool8_t` data type, values represented with 'True' and 'False'.

Collaboration diagram for IBoolean Access:



Functions

- [SPINNAKERC_API spinBooleanSetValue](#) ([spinNodeHandle](#) hNode, [bool8_t](#) value)
Sets the value of a boolean node; boolean values are represented by 'True' (which equals '0') and 'False' (which equals '1')
- [SPINNAKERC_API spinBooleanGetValue](#) ([spinNodeHandle](#) hNode, [bool8_t](#) *pbValue)
Retrieves the value of a boolean node; boolean values are represented by 'True' (which equals '0') and 'False' (which equals '1')

4.32.1 Detailed Description

The functions in this section provide access to boolean nodes using the `bool8_t` data type, values represented with 'True' and 'False'.

This includes value getters and setters.

4.32.2 Function Documentation

4.32.2.1 spinBooleanGetValue()

```

SPINNAKERC_API spinBooleanGetValue (
    spinNodeHandle hNode,
    bool8_t * pbValue )
  
```

Retrieves the value of a boolean node; boolean values are represented by 'True' (which equals '0') and 'False' (which equals '1')

See also

[spinError](#)

Parameters

<i>hNode</i>	The boolean node of the value to read
<i>pValue</i>	The boolean pointer in which the value is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.32.2.2 `spinBooleanSetValue()`

```
SPINNAKERC_API spinBooleanSetValue (
    spinNodeHandle hNode,
    bool8_t value )
```

Sets the value of a boolean node; boolean values are represented by 'True' (which equals '0') and 'False' (which equals '1')

See also

[spinError](#)

Parameters

<i>hNode</i>	The boolean node having its value changed
<i>value</i>	The boolean value to set

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.33 ICommand Access

The functions in this section all provide access to information and objects retrieved from nodes.

Collaboration diagram for ICommand Access:



Functions

- [SPINNAKERC_API spinCommandExecute](#) ([spinNodeHandle](#) hNode)
Executes the action associated to a command node.
- [SPINNAKERC_API spinCommandIsDone](#) ([spinNodeHandle](#) hNode, [bool8_t](#) *pbValue)
Retrieves whether or not the action of a command node has completed.

4.33.1 Detailed Description

The functions in this section all provide access to information and objects retrieved from nodes.

This includes node properties and callbacks.

4.33.2 Function Documentation

4.33.2.1 spinCommandExecute()

```
SPINNAKERC_API spinCommandExecute (
    spinNodeHandle hNode )
```

Executes the action associated to a command node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The command node to execute
--------------	-----------------------------

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.33.2.2 spinCommandIsDone()

```
SPINNAKERC_API spinCommandIsDone (
    spinNodeHandle hNode,
    bool8_t * pbValue )
```

Retrieves whether or not the action of a command node has completed.

See also

[spinError](#)

Parameters

<i>hNode</i>	The command node to check
<i>pValue</i>	The boolean pointer to return whether or not the command has completed

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.34 ICategory Access

The functions in this section all provide access to information and objects retrieved from nodes.

Collaboration diagram for ICategory Access:



Functions

- [SPINNAKERC_API spinCategoryGetNumFeatures](#) ([spinNodeHandle](#) hNode, [size_t](#) *pValue)
Retrieves the number of a features (or child nodes) or a category node.
- [SPINNAKERC_API spinCategoryGetFeatureByIndex](#) ([spinNodeHandle](#) hNode, [size_t](#) index, [spinNodeHandle](#) *phFeature)
Retrieves a node from a category node using an index.

4.34.1 Detailed Description

The functions in this section all provide access to information and objects retrieved from nodes.

This includes node properties and callbacks.

4.34.2 Function Documentation

4.34.2.1 spinCategoryGetFeatureByIndex()

```

SPINNAKERC_API spinCategoryGetFeatureByIndex (
    spinNodeHandle hNode,
    size_t index,
    spinNodeHandle * phFeature )
  
```

Retrieves a node from a category node using an index.

See also

[spinError](#)

Parameters

<i>hNode</i>	The category node of the node to retrieve
<i>index</i>	The index of the feature node
<i>phFeature</i>	The node handle pointer in which the feature node is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.34.2.2 `spinCategoryGetNumFeatures()`

```
SPINNAKERC_API spinCategoryGetNumFeatures (
    spinNodeHandle hNode,
    size_t * pValue )
```

Retrieves the number of a features (or child nodes) or a category node.

See also

[`spinError`](#)

Parameters

<i>hNode</i>	The category node where the features to be counted are
<i>pValue</i>	The unsigned integer pointer in which the number of features is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.35 IRegister Access

The functions in this section provide access to register nodes.

Collaboration diagram for IRegister Access:



Functions

- [SPINNAKERC_API spinRegisterGet](#) ([spinNodeHandle](#) hNode, [uint8_t](#) *pBuf, [int64_t](#) length)
Retrieves the value of a register node.
- [SPINNAKERC_API spinRegisterGetEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, [bool8_t](#) bIgnoreCache, [uint8_t](#) *pBuf, [int64_t](#) length)
Retrieves the value of a register node; manually set whether to verify the node and whether to ignore the cache.
- [SPINNAKERC_API spinRegisterGetAddress](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pAddress)
Retrieves the address of a register node.
- [SPINNAKERC_API spinRegisterGetLength](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pLength)
Retrieves the length (in bytes) of the value of a register node.
- [SPINNAKERC_API spinRegisterSet](#) ([spinNodeHandle](#) hNode, [const uint8_t](#) *pBuf, [int64_t](#) length)
Sets the value of a register node.
- [SPINNAKERC_API spinRegisterSetEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, [const uint8_t](#) *pBuf, [int64_t](#) length)
Sets the value of a register node; manually set whether to verify the node.
- [SPINNAKERC_API spinRegisterSetReference](#) ([spinNodeHandle](#) hNode, [spinNodeHandle](#) hRef)
Uses a second node as a reference for a register node.

4.35.1 Detailed Description

The functions in this section provide access to register nodes.

This includes access to the node, its address and length, and reference.

4.35.2 Function Documentation

4.35.2.1 spinRegisterGet()

```
SPINNAKERC_API spinRegisterGet (
    spinNodeHandle hNode,
    uint8_t * pBuf,
    int64_t length )
```

Retrieves the value of a register node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The register node of the value to retrieve
<i>pBuf</i>	The unsigned integer buffer in which the value is returned
<i>length</i>	The integer pointer in which the length of the register array is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.35.2.2 spinRegisterGetAddress()

```
SPINNAKERC_API spinRegisterGetAddress (
    spinNodeHandle hNode,
    int64_t * pAddress )
```

Retrieves the address of a register node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The register node of the address to retrieve
<i>pAddress</i>	The integer pointer in which the address is returned

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.35.2.3 spinRegisterGetEx()

```
SPINNAKERC_API spinRegisterGetEx (
    spinNodeHandle hNode,
    bool8_t bVerify,
    bool8_t bIgnoreCache,
    uint8_t * pBuf,
    int64_t length )
```

Retrieves the value of a register node; manually set whether to verify the node and whether to ignore the cache.

See also

[spinError](#)

Parameters

<i>hNode</i>	The register node of the value to retrieve
<i>bVerify</i>	The boolean of whether to verify the node
<i>IgnoreCache</i>	The boolean of whether to ignore the cache
<i>pBuf</i>	The unsigned integer buffer in which the value is returned
<i>length</i>	The integer pointer in which the length of the register array is returned; the input value is the maximum length

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.35.2.4 spinRegisterGetLength()

```
SPINNAKERC_API spinRegisterGetLength (
    spinNodeHandle hNode,
    int64_t * pLength )
```

Retrieves the length (in bytes) of the value of a register node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The register node of the length to retrieve
<i>pLength</i>	The integer in which the number of bytes is returned

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.35.2.5 spinRegisterSet()

```
SPINNAKERC_API spinRegisterSet (  
    spinNodeHandle hNode,  
    const uint8_t * pBuf,  
    int64_t length )
```

Sets the value of a register node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The register node of the value to set
<i>pBuf</i>	The unsigned integer buffer of the value to set
<i>length</i>	The number of bytes of the value to set

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.35.2.6 spinRegisterSetEx()

```
SPINNAKERC_API spinRegisterSetEx (  
    spinNodeHandle hNode,  
    bool8_t bVerify,  
    const uint8_t * pBuf,  
    int64_t length )
```

Sets the value of a register node; manually set whether to verify the node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The register node of the value to set
<i>bVerify</i>	The boolean of whether to verify the node
<i>pBuf</i>	The unsigned integer buffer of the value to set
<i>length</i>	The number of bytes of the value to set

Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.35.2.7 spinRegisterSetReference()

```
SPINNAKERC_API spinRegisterSetReference (
    spinNodeHandle hNode,
    spinNodeHandle hRef )
```

Uses a second node as a reference for a register node.

See also

[spinError](#)

Parameters

<i>hNode</i>	The register node that houses the reference
<i>hRef</i>	The reference node


Returns

`spinError` The error code; returns `SPINNAKER_ERR_SUCCESS` (or 0) for no error

4.36 Spinnaker C GenICam Handles

Handle definitions for Spinnaker C GenICam API.

Collaboration diagram for Spinnaker C GenICam Handles:



Typedefs

- typedef void * [spinNodeMapHandle](#)
Handle for nodemap functionality.
- typedef void * [spinNodeHandle](#)
Handle for node functionality.
- typedef void * [spinNodeCallbackHandle](#)
Handle for callback functionality.
- typedef void(* [spinNodeCallbackFunction](#)) ([spinNodeHandle](#) hNode)
Function signatures are used to create and trigger callbacks and events.

4.36.1 Detailed Description

Handle definitions for Spinnaker C GenICam API.

4.36.2 Typedef Documentation

4.36.2.1 spinNodeCallbackFunction

```
typedef void(* spinNodeCallbackFunction) (spinNodeHandle hNode)
```

Function signatures are used to create and trigger callbacks and events.

4.36.2.2 spinNodeCallbackHandle

```
typedef void* spinNodeCallbackHandle
```

Handle for callback functionality.

Created by calling [spinNodeRegisterCallback\(\)](#), which requires a call to [spinNodeUnregisterCallback\(\)](#) destroy.

4.36.2.3 spinNodeHandle

```
typedef void* spinNodeHandle
```

Handle for node functionality.

Created by calling [spinNodeMapGetNode\(\)](#). No need to release, clear, or destroy.

4.36.2.4 spinNodeMapHandle

```
typedef void* spinNodeMapHandle
```


Handle for nodemap functionality.

Created by calling [spinCameraGetNodemap\(\)](#), [spinCameraGetTLDeviceNodeMap\(\)](#), [spinCameraGetTLStreamNodeMap\(\)](#) or [spinInterfaceGetTLNodeMap\(\)](#). No need to release, clear, or destroy.

4.37 Spinnaker C GenICam Enumerations

Enumeration definitions for Spinnaker C GenICam API.

Collaboration diagram for Spinnaker C GenICam Enumerations:



Enumerations

- enum `spinNodeType` {
`ValueNode`,
`BaseNode`,
`IntegerNode`,
`BooleanNode`,
`FloatNode`,
`CommandNode`,
`StringNode`,
`RegisterNode`,
`EnumerationNode`,
`EnumEntryNode`,
`CategoryNode`,
`PortNode`,
`UnknownNode` = -1 }
- enum `spinSign` {
`Signed`,
`Unsigned`,
`_UndefinedSign` }
- enum `spinAccessMode` {
`NI`,
`NA`,
`WO`,
`RO`,
`RW`,
`_UndefinedAccesMode`,
`_CycleDetectAccesMode` }
- enum `spinVisibility` {
`Beginner` = 0,
`Expert` = 1,
`Guru` = 2,
`Invisible` = 3,
`_UndefinedVisibility` = 99 }
- enum `spinCachingMode` {
`NoCache`,
`WriteThrough`,
`WriteAround`,
`_UndefinedCachingMode` }

- enum `spinRepresentation` {
`Linear`,
`Logarithmic`,
`Boolean`,
`PureNumber`,
`HexNumber`,
`IPV4Address`,
`MACAddress`,
`_UndefinedRepresentation` }
recommended representation of a node value
- enum `spinEndianness` {
`BigEndian`,
`LittleEndian`,
`_UndefinedEndian` }
Endianness of a value in a register.
- enum `spinNameSpace` {
`Custom`,
`Standard`,
`_UndefinedNameSpace` }
Defines if a node name is standard or custom.
- enum `spinStandardNameSpace` {
`None`,
`GEV`,
`IIDC`,
`CL`,
`USB`,
`_UndefinedStandardNameSpace` }
Defines from which standard namespace a node name comes from.
- enum `spinYesNo` {
`Yes` = 1,
`No` = 0,
`_UndefinedYesNo` = 2 }
Defines the chices of a Yes/No alternaitve.
- enum `spinSlope` {
`Increasing`,
`Decreasing`,
`Varying`,
`Automatic`,
`_UndefinedESlope` }
typedef for fomula type
- enum `spinXMLValidation` {
`xvLoad` = 0x00000001L,
`xvCycles` = 0x00000002L,
`xvSFNC` = 0x00000004L,
`xvDefault` = 0x00000000L,
`xvAll` = 0xffffffffL,
`_UndefinedEXMLValidation` = 0x80000000L }
typedef describing the different validity checks which can be performed on an XML file
- enum `spinDisplayNotation` {
`fnAutomatic`,
`fnFixed`,
`fnScientific`,
`_UndefinedEDisplayNotation` }
typedef for float notation
- enum `spinInterfaceType` {
`intfIValue`,


```

intfIBase,
intfInteger,
intfBoolean,
intfCommand,
intfFloat,
intfString,
intfRegister,
intfCategory,
intfEnumeration,
intfEnumEntry,
intfIPort }

```

typedef for interface type

- enum `spinLinkType` {
`ctAllDependingNodes`,
`ctAllTerminalNodes`,
`ctInvalidators`,
`ctReadingChildren`,
`ctWritingChildren`,
`ctDependingChildren` }

typedef for link type

- enum `spinIncMode` {
`noIncrement`,
`fixedIncrement`,
`listIncrement` }

typedef for increment mode

- enum `spinInputDirection` {
`idFrom`,
`idTo`,
`idNone` }

typedef for link type

4.37.1 Detailed Description

Enumeration definitions for Spinnaker C GenICam API.

4.37.2 Enumeration Type Documentation

4.37.2.1 `spinAccessMode`

```
enum spinAccessMode
```

Enumerator

NI	
NA	
WO	
RO	
RW	
_UndefinedAccesMode	
_CycleDetectAccesMode	

4.37.2.2 spinCachingMode

```
enum spinCachingMode
```

Enumerator

NoCache	
WriteThrough	
WriteAround	
_UndefinedCachingMode	

4.37.2.3 spinDisplayNotation

```
enum spinDisplayNotation
```

```
typedef for float notation
```

Enumerator

fnAutomatic	
fnFixed	the notation if either scientific or fixed depending on what is shorter
fnScientific	the notation is fixed, e.g. 123.4
_UndefinedEDisplayNotation	the notation is scientific, e.g. 1.234e2 Object is not yet initialized

4.37.2.4 spinEndianness

```
enum spinEndianness
```

Endianness of a value in a register.

Enumerator

BigEndian	Register is big endian.
LittleEndian	Register is little endian.
_UndefinedEndian	Object is not yet initialized.

4.37.2.5 spinIncMode

enum `spinIncMode`

typedef for increment mode

Enumerator

noIncrement	
fixedIncrement	
listIncrement	

4.37.2.6 spinInputDirection

enum `spinInputDirection`

typedef for link type

Enumerator

idFrom	
idTo	Indicates a swiss knife that it is used as worker for a converter computing FROM
idNone	Indicates a swiss knife that it is used as worker for a converter computing TO SwissKnife is not used within a converter

4.37.2.7 spinInterfaceType

enum `spinInterfaceType`

typedef for interface type

Enumerator

intfIValue	
intfIBase	IValue interface

Enumerator

intfInteger	IBase interface
intfBoolean	Integer interface
intfCommand	Boolean interface
intfFloat	Command interface
intfString	Float interface
intfRegister	String interface
intfCategory	Register interface
intfEnumeration	Category interface
intfEnumEntry	Enumeration interface
intfIPort	EnumEntry interface IPort interface

4.37.2.8 spinLinkType

```
enum spinLinkType
```

```
typedef for link type
```

Enumerator

ctAllDependingNodes	
ctAllTerminalNodes	All nodes which will be invalidated if this node becomes invalid
ctInvalidators	All terminal nodes which may be written to by this node

Enumerator

ctReadingChildren	List of references to nodes which may invalidate this node
ctWritingChildren	All child nodes which influence this node's AccessMode
ctDependingChildren	All child nodes which may be written to All child nodes which will cause this node to be invalidated

4.37.2.9 spinNameSpace

```
enum spinNameSpace
```

Defines if a node name is standard or custom.

Enumerator

Custom	name resides in custom namespace
Standard	name resides in one of the standard namespaces
_UndefinedNameSpace	Object is not yet initialized.

4.37.2.10 spinNodeType

```
enum spinNodeType
```

Enumerator

ValueNode	
BaseNode	
IntegerNode	
BooleanNode	
FloatNode	
CommandNode	
StringNode	
RegisterNode	
EnumerationNode	
EnumEntryNode	
CategoryNode	
PortNode	
UnknownNode	

4.37.2.11 spinRepresentation

enum `spinRepresentation`

recommended representation of a node value

Enumerator

Linear	Slider with linear behavior.
Logarithmic	Slider with logarithmic behaviour.
Boolean	Check box.
PureNumber	Decimal number in an edit control.
HexNumber	Hex number in an edit control.
IPV4Address	IP-Address.
MACAddress	MAC-Address.
_UndefinedRepresentation	

4.37.2.12 spinSign

enum `spinSign`

Enumerator

Signed	
Unsigned	
_UndefinedSign	

4.37.2.13 spinSlope

enum `spinSlope`

typedef for fomula type

Enumerator

Increasing	
Decreasing	strictly monotonous increasing
Varying	strictly monotonous decreasing

Enumerator

Automatic	slope changes, e.g. at run-time
_UndefinedESlope	slope is determined automatically by probing the function Object is not yet initialized

4.37.2.14 spinStandardNameSpace

enum `spinStandardNameSpace`

Defines from which standard namespace a node name comes from.

Enumerator

None	name resides in custom namespace
GEV	name resides in GigE Vision namespace
IIDC	name resides in 1394 IIDC namespace
CL	name resides in camera link namespace
USB	name resides in USB namespace
_UndefinedStandardNameSpace	Object is not yet initialized.

4.37.2.15 spinVisibility

enum `spinVisibility`

Enumerator

Beginner	
Expert	
Guru	
Invisible	
_UndefinedVisibility	

4.37.2.16 spinXMLValidation

enum `spinXMLValidation`

typedef describing the different validity checks which can be performed on an XML file

The enum values for a bitfield of lenght uint32_t

Enumerator

xvLoad	
xvCycles	Creates a dummy node map
xvSFNC	checks for write and dependency cycles (implies xvLoad)
xvDefault	checks for conformance with the standard feature naming convention (SFNC)
xvAll	checks performed if nothing else is said
_UndefinedEXMLValidation	all possible checks Object is not yet initialized

4.37.2.17 spinYesNo

```
enum spinYesNo
```

Defines the chices of a Yes/No alternative.


Enumerator

Yes	yes
No	no
_UndefinedYesNo	Object is not yet initialized.

4.38 SpinVideo Recording Access

The functions in this section provide access to video recording capabilities, which include opening, building, and closing video files.

Collaboration diagram for SpinVideo Recording Access:



Functions

- [SPINNAKERC_API spinVideoOpenUncompressed](#) ([spinVideo](#) *phSpinVideo, const char *pName, [spinAVIOption](#) option)
- [SPINNAKERC_API spinVideoOpenMJPEG](#) ([spinVideo](#) *phSpinVideo, const char *pName, [spinMJPEGOption](#) option)
- [SPINNAKERC_API spinVideoOpenH264](#) ([spinVideo](#) *phSpinVideo, const char *pName, [spinH264Option](#) option)
- [SPINNAKERC_API spinVideoAppend](#) ([spinVideo](#) hSpinVideo, [spinImage](#) hImage)
- [SPINNAKERC_API spinVideoSetMaximumFileSize](#) ([spinVideo](#) hSpinVideo, unsigned int size)
Set the maximum file size (in megabytes) of a AVI/MP4 file.
- [SPINNAKERC_API spinVideoClose](#) ([spinVideo](#) hSpinVideo)

4.38.1 Detailed Description

The functions in this section provide access to video recording capabilities, which include opening, building, and closing video files.

4.38.2 Function Documentation

4.38.2.1 spinVideoAppend()

```

SPINNAKERC_API spinVideoAppend (
    spinVideo hSpinVideo,
    spinImage hImage )
  
```

4.38.2.2 spinVideoClose()

```
SPINNAKERC_API spinVideoClose (
    spinVideo hSpinVideo )
```

4.38.2.3 spinVideoOpenH264()

```
SPINNAKERC_API spinVideoOpenH264 (
    spinVideo * phSpinVideo,
    const char * pName,
    spinH264Option option )
```

4.38.2.4 spinVideoOpenMJPG()

```
SPINNAKERC_API spinVideoOpenMJPG (
    spinVideo * phSpinVideo,
    const char * pName,
    spinMJPGOption option )
```

4.38.2.5 spinVideoOpenUncompressed()

```
SPINNAKERC_API spinVideoOpenUncompressed (
    spinVideo * phSpinVideo,
    const char * pName,
    spinAVIOption option )
```

4.38.2.6 spinVideoSetMaximumFileSize()

```
SPINNAKERC_API spinVideoSetMaximumFileSize (
    spinVideo hSpinVideo,
    unsigned int size )
```

Set the maximum file size (in megabytes) of a AVI/MP4 file.

A new AVI/MP4 file is created automatically when file size limit is reached. Setting a maximum size of 0 indicates no limit on file size.

Parameters


<i>hSpinVideo</i>	The spin video recorder to append the image to
<i>size</i>	The maximum video file size in MB.

Returns

spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

4.39 Transport Layer Enumerations

Collaboration diagram for Transport Layer Enumerations:



Enumerations

- enum `spinTLStreamTypeEnums` {
`StreamType_GigEVision`,
`StreamType_CameraLink`,
`StreamType_CameraLinkHS`,
`StreamType_CoaXPress`,
`StreamType_USB3Vision`,
`StreamType_Custom`,
`NUMSTREAMTYPE` }

The enumeration definitions for transport layer nodes.

- enum `spinTLStreamBufferCountModeEnums` {
`StreamBufferCountMode_Manual`,
`StreamBufferCountMode_Auto`,
`NUMSTREAMBUFFERCOUNTMODE` }
- enum `spinTLStreamBufferHandlingModeEnums` {
`StreamBufferHandlingMode_OldestFirst`,
`StreamBufferHandlingMode_OldestFirstOverwrite`,
`StreamBufferHandlingMode_NewestOnly`,
`StreamBufferHandlingMode_NewestFirst`,
`NUMSTREAMBUFFERHANDLINGMODE` }
- enum `spinTLDeviceTypeEnums` {
`DeviceType_GigEVision`,
`DeviceType_CameraLink`,
`DeviceType_CameraLinkHS`,
`DeviceType_CoaXPress`,
`DeviceType_USB3Vision`,
`DeviceType_Custom`,
`NUMDEVICETYPE` }
- enum `spinTLDeviceAccessStatusEnums` {
`DeviceAccessStatus_Unknown`,
`DeviceAccessStatus_ReadWrite`,
`DeviceAccessStatus_ReadOnly`,
`DeviceAccessStatus_NoAccess`,
`DeviceAccessStatus_Busy`,
`DeviceAccessStatus_OpenReadWrite`,
`DeviceAccessStatus_OpenReadOnly`,
`NUMDEVICEACCESSSTATUS` }
- enum `spinTLGevCCPEnums` {
`GevCCP_EnumEntry_GevCCP_OpenAccess`,
`GevCCP_EnumEntry_GevCCP_ExclusiveAccess`,
`GevCCP_EnumEntry_GevCCP_ControlAccess`,
`NUMGEVCCP` }

- enum `spinTLGUIXMLLocationEnums` {
`GUIXMLLocation_Device`,
`GUIXMLLocation_Host`,
`NUMGUIXMLLOCATION` }
- enum `spinTLGenlCamXMLLocationEnums` {
`GenlCamXMLLocation_Device`,
`GenlCamXMLLocation_Host`,
`NUMGENICAMXMLLOCATION` }
- enum `spinTLDeviceEndiannessMechanismEnums` {
`DeviceEndiannessMechanism_Legacy`,
`DeviceEndiannessMechanism_Standard`,
`NUMDEVICEENDIANESSMECHANISM` }
- enum `spinTLDeviceCurrentSpeedEnums` {
`DeviceCurrentSpeed_UnknownSpeed`,
`DeviceCurrentSpeed_LowSpeed`,
`DeviceCurrentSpeed_FullSpeed`,
`DeviceCurrentSpeed_HighSpeed`,
`DeviceCurrentSpeed_SuperSpeed`,
`NUMDEVICECURRENTSPEED` }
- enum `spinTLInterfaceTypeEnums` {
`InterfaceType_GigEVision`,
`InterfaceType_CameraLink`,
`InterfaceType_CameraLinkHS`,
`InterfaceType_CoaXPress`,
`InterfaceType_USB3Vision`,
`InterfaceType_Custom`,
`NUMINTERFACETYPE` }
- enum `spinTLPOEStatusEnums` {
`POEStatus_NotSupported`,
`POEStatus_PowerOff`,
`POEStatus_PowerOn`,
`NUMPOESTATUS` }
- enum `spinTLFilterDriverStatusEnums` {
`FilterDriverStatus_NotSupported`,
`FilterDriverStatus_Disabled`,
`FilterDriverStatus_Enabled`,
`NUMFILTERDRIVERSTATUS` }
- enum `spinTLTLTypeEnums` {
`TLType_GigEVision`,
`TLType_CameraLink`,
`TLType_CameraLinkHS`,
`TLType_CoaXPress`,
`TLType_USB3Vision`,
`TLType_Mixed`,
`TLType_Custom`,
`NUMTLTYPE` }

4.39.1 Detailed Description

4.39.2 Enumeration Type Documentation

4.39.2.1 spinTLDeviceAccessStatusEnums

enum `spinTLDeviceAccessStatusEnums`

< Gets the access status the transport layer Producer has on the device.

Enumerator

DeviceAccessStatus_Unknown	Not known to producer.
DeviceAccessStatus_ReadWrite	Full access
DeviceAccessStatus_ReadOnly	Read-only access
DeviceAccessStatus_NoAccess	Not available to connect
DeviceAccessStatus_Busy	The device is already opened by another entity
DeviceAccessStatus_OpenReadWrite	Open in Read/Write mode by this GenTL host
DeviceAccessStatus_OpenReadOnly	Open in Read access mode by this GenTL host
NUMDEVICEACCESSSTATUS	

4.39.2.2 spinTLDeviceCurrentSpeedEnums

enum `spinTLDeviceCurrentSpeedEnums`

< The USB Speed that the device is currently operating at.

Enumerator

DeviceCurrentSpeed_UnknownSpeed	Unknown-Speed.
DeviceCurrentSpeed_LowSpeed	Low-Speed.
DeviceCurrentSpeed_FullSpeed	Full-Speed.
DeviceCurrentSpeed_HighSpeed	High-Speed.
DeviceCurrentSpeed_SuperSpeed	Super-Speed.
NUMDEVICECURRENTSPEED	

4.39.2.3 spinTLDeviceEndiannessMechanismEnums

enum `spinTLDeviceEndiannessMechanismEnums`

< Identifies the endianness handling mode.

Enumerator

DeviceEndiannessMechanism_Legacy	Handling the device endianness according to GenICam Schema 1.0
DeviceEndiannessMechanism_Standard	Handling the device endianness according to GenICam Schema 1.1 and later
NUMDEVICEENDIANESSMECHANISM	

4.39.2.4 spinTLDeviceTypeEnums

```
enum spinTLDeviceTypeEnums
```

< Transport layer type of the device.

Enumerator

DeviceType_GigEVision	GigE Vision
DeviceType_CameraLink	Camera Link
DeviceType_CameraLinkHS	Camera Link High Speed
DeviceType_CoaXPress	CoaXPress
DeviceType_USB3Vision	USB3 Vision
DeviceType_Custom	Custom transport layer
NUMDEVICETYPE	

4.39.2.5 spinTLFilterDriverStatusEnums

```
enum spinTLFilterDriverStatusEnums
```

< Reports whether FLIR Light Weight Filter Driver is enabled or not.

Enumerator

FilterDriverStatus_NotSupported	Not Supported
FilterDriverStatus_Disabled	FLIR Light Weight Filter Driver is disabled
FilterDriverStatus_Enabled	FLIR Light Weight Filter Driver is enabled
NUMFILTERDRIVERSTATUS	

4.39.2.6 spinTLGenICamXMLLocationEnums

```
enum spinTLGenICamXMLLocationEnums
```

< Sets the location to load GenICam XML.

Enumerator

GenICamXMLLocation_Device	Load GenICam XML from device
GenICamXMLLocation_Host	Load GenICam XML from host
NUMGENICAMXMLLOCATION	

4.39.2.7 spinTLGevCCPEnums

enum `spinTLGevCCPEnums`

< Controls the device access privilege of an application.

Enumerator

GevCCP_EnumEntry_GevCCP_OpenAccess	Open access privilege.
GevCCP_EnumEntry_GevCCP_ExclusiveAccess	Exclusive access privilege.
GevCCP_EnumEntry_GevCCP_ControlAccess	Control access privilege.
NUMGEVCCP	

4.39.2.8 spinTLGUIXMLLocationEnums

enum `spinTLGUIXMLLocationEnums`

< Sets the location to load GUI XML.

Enumerator

GUIXMLLocation_Device	Load XML from device
GUIXMLLocation_Host	Load XML from host
NUMGUIXMLLOCATION	

4.39.2.9 spinTLInterfaceTypeEnums

enum `spinTLInterfaceTypeEnums`

< Transport layer type of the interface.

Enumerator

InterfaceType_GigEVision	GigE Vision
InterfaceType_CameraLink	Camera Link
InterfaceType_CameraLinkHS	Camera Link High Speed
InterfaceType_CoaXPress	CoaXPress
InterfaceType_USB3Vision	USB3 Vision
InterfaceType_Custom	Custom transport layer
NUMINTERFACETYPE	

4.39.2.10 spinTLPOEStatusEnums

```
enum spinTLPOEStatusEnums
```

< Reports and controls the interface's power over Ethernet status.

Enumerator

POEStatus_NotSupported	Not Supported
POEStatus_PowerOff	Power is Off
POEStatus_PowerOn	Power is On
NUMPOESTATUS	

4.39.2.11 spinTLStreamBufferCountModeEnums

```
enum spinTLStreamBufferCountModeEnums
```

< Controls access to setting the number of buffers used for the stream.

Enumerator

StreamBufferCountMode_Manual	The number of buffers used for the stream are set by the user.
StreamBufferCountMode_Auto	DEPRECATED. The number of buffers used for the stream is automatically calculated based on the device frame rate.
NUMSTREAMBUFFERCOUNTMODE	

4.39.2.12 spinTLStreamBufferHandlingModeEnums

```
enum spinTLStreamBufferHandlingModeEnums
```

< Available buffer handling modes of this data stream:

Enumerator

StreamBufferHandlingMode_OldestFirst	The application always gets the buffer from the head of the output buffer queue (thus, the oldest available one). If the output buffer queue is empty, the application waits for a newly acquired buffer until the timeout expires.
StreamBufferHandlingMode_OldestFirstOverwrite	The application always gets the buffer from the head of the output buffer queue (thus, the oldest available one). If the output buffer queue is empty, the application waits for a newly acquired buffer until the timeout expires. If a new buffer arrives it will overwrite the existing buffer from the head of the queue (behaves like a circular buffer).

Enumerator

StreamBufferHandlingMode_NewestOnly	The application always gets the latest completed buffer (the newest one). If the Output Buffer Queue is empty, the application waits for a newly acquired buffer until the timeout expires. This buffer handling mode is typically used in a live display GUI where it is important that there is no lag between camera and display.
StreamBufferHandlingMode_NewestFirst	The application always gets the buffer from the tail of the output buffer queue (thus, the newest available one). If the output buffer queue is empty, the application waits for a newly acquired buffer until the timeout expires.
NUMSTREAMBUFFERHANDLINGMODE	

4.39.2.13 spinTLStreamTypeEnums

enum `spinTLStreamTypeEnums`

The enumeration definitions for transport layer nodes.

< Stream type of the device.

Enumerator

StreamType_GigEVision	GigE Vision
StreamType_CameraLink	Camera Link
StreamType_CameraLinkHS	Camera Link High Speed
StreamType_CoaXPress	CoaXPress
StreamType_USB3Vision	USB3 Vision
StreamType_Custom	Custom transport layer
NUMSTREAMTYPE	

4.39.2.14 spinTLTLTypeEnums

enum `spinTLTLTypeEnums`

< Transport layer type of the GenTL Producer implementation.

Enumerator


TLType_GigEVision	GigE Vision
TLType_CameraLink	Camera Link
TLType_CameraLinkHS	Camera Link High Speed
TLType_CoaXPress	CoaXPress

Enumerator

TLType_USB3Vision	USB3 Vision
TLType_Mixed	Different Interface modules of the GenTL Producer are of different types
TLType_Custom	Custom transport layer
NUMTLTYPE	

4.40 TLDevice Structures

Collaboration diagram for TLDevice Structures:




Data Structures

- struct [quickSpinTLDevice](#)

4.40.1 Detailed Description

4.41 TLInterface Structures

Collaboration diagram for TLInterface Structures:



Data Structures

- struct [quickSpinTLInterface](#)

4.41.1 Detailed Description

4.42 TLStream Structures

Collaboration diagram for TLStream Structures:



Data Structures

- struct [quickSpinTLStream](#)

4.42.1 Detailed Description

4.43 TLSystem Structures

Collaboration diagram for TLSystem Structures:



Data Structures

- struct [quickSpinTLSystem](#)

4.43.1 Detailed Description

Chapter 5

Data Structure Documentation

5.1 actionCommandResult Struct Reference

Action Command Result.

Data Fields

- unsigned int [DeviceAddress](#)
- [actionCommandStatus](#) Status

5.1.1 Detailed Description

Action Command Result.

5.1.2 Field Documentation

5.1.2.1 DeviceAddress

```
unsigned int DeviceAddress
```

5.1.2.2 Status

```
actionCommandStatus Status
```

The documentation for this struct was generated from the following file:

- include/spinc/[SpinnakerDefsC.h](#)

5.2 quickSpin Struct Reference

Data Fields

- quickSpinIntegerNode LUTIndex
- quickSpinBooleanNode LUTEnable
- quickSpinIntegerNode LUTValue
- quickSpinEnumerationNode LUTSelector
- quickSpinFloatNode ExposureTime
- quickSpinCommandNode AcquisitionStop
- quickSpinFloatNode AcquisitionResultingFrameRate
- quickSpinFloatNode AcquisitionLineRate
- quickSpinCommandNode AcquisitionStart
- quickSpinCommandNode TriggerSoftware
- quickSpinEnumerationNode ExposureMode
- quickSpinEnumerationNode AcquisitionMode
- quickSpinIntegerNode AcquisitionFrameCount
- quickSpinEnumerationNode TriggerSource
- quickSpinEnumerationNode TriggerActivation
- quickSpinEnumerationNode SensorShutterMode
- quickSpinFloatNode TriggerDelay
- quickSpinEnumerationNode TriggerMode
- quickSpinFloatNode AcquisitionFrameRate
- quickSpinEnumerationNode TriggerOverlap
- quickSpinEnumerationNode TriggerSelector
- quickSpinBooleanNode AcquisitionFrameRateEnable
- quickSpinEnumerationNode ExposureAuto
- quickSpinIntegerNode AcquisitionBurstFrameCount
- quickSpinIntegerNode EventTest
- quickSpinIntegerNode EventTestTimestamp
- quickSpinIntegerNode EventExposureEndFrameID
- quickSpinIntegerNode EventExposureEnd
- quickSpinIntegerNode EventExposureEndTimestamp
- quickSpinIntegerNode EventError
- quickSpinIntegerNode EventErrorTimestamp
- quickSpinIntegerNode EventErrorCode
- quickSpinIntegerNode EventErrorFrameID
- quickSpinEnumerationNode EventSelector
- quickSpinBooleanNode EventSerialReceiveOverflow
- quickSpinIntegerNode EventSerialPortReceive
- quickSpinIntegerNode EventSerialPortReceiveTimestamp
- quickSpinStringNode EventSerialData
- quickSpinIntegerNode EventSerialDataLength
- quickSpinEnumerationNode EventNotification
- quickSpinIntegerNode LogicBlockLUTRowIndex
- quickSpinEnumerationNode LogicBlockSelector
- quickSpinEnumerationNode LogicBlockLUTInputActivation
- quickSpinEnumerationNode LogicBlockLUTInputSelector
- quickSpinEnumerationNode LogicBlockLUTInputSource
- quickSpinBooleanNode LogicBlockLUTOutputValue
- quickSpinIntegerNode LogicBlockLUTOutputValueAll
- quickSpinEnumerationNode LogicBlockLUTSelector
- quickSpinFloatNode ColorTransformationValue
- quickSpinBooleanNode ColorTransformationEnable

- [quickSpinEnumerationNode ColorTransformationSelector](#)
- [quickSpinEnumerationNode RgbTransformLightSource](#)
- [quickSpinFloatNode Saturation](#)
- [quickSpinBooleanNode SaturationEnable](#)
- [quickSpinEnumerationNode ColorTransformationValueSelector](#)
- [quickSpinIntegerNode TimestampLatchValue](#)
- [quickSpinCommandNode TimestampReset](#)
- [quickSpinStringNode DeviceUserID](#)
- [quickSpinFloatNode DeviceTemperature](#)
- [quickSpinIntegerNode MaxDeviceResetTime](#)
- [quickSpinIntegerNode DeviceTLVersionMinor](#)
- [quickSpinStringNode DeviceSerialNumber](#)
- [quickSpinStringNode DeviceVendorName](#)
- [quickSpinEnumerationNode DeviceRegistersEndianness](#)
- [quickSpinStringNode DeviceManufacturerInfo](#)
- [quickSpinIntegerNode DeviceLinkSpeed](#)
- [quickSpinIntegerNode LinkUptime](#)
- [quickSpinIntegerNode DeviceEventChannelCount](#)
- [quickSpinCommandNode TimestampLatch](#)
- [quickSpinEnumerationNode DeviceScanType](#)
- [quickSpinCommandNode DeviceReset](#)
- [quickSpinEnumerationNode DeviceCharacterSet](#)
- [quickSpinIntegerNode DeviceLinkThroughputLimit](#)
- [quickSpinStringNode DeviceFirmwareVersion](#)
- [quickSpinIntegerNode DeviceStreamChannelCount](#)
- [quickSpinEnumerationNode DeviceTLType](#)
- [quickSpinStringNode DeviceVersion](#)
- [quickSpinEnumerationNode DevicePowerSupplySelector](#)
- [quickSpinStringNode SensorDescription](#)
- [quickSpinStringNode DeviceModelName](#)
- [quickSpinIntegerNode DeviceTLVersionMajor](#)
- [quickSpinEnumerationNode DeviceTemperatureSelector](#)
- [quickSpinIntegerNode EnumerationCount](#)
- [quickSpinFloatNode PowerSupplyCurrent](#)
- [quickSpinStringNode DeviceID](#)
- [quickSpinIntegerNode DeviceUptime](#)
- [quickSpinIntegerNode DeviceLinkCurrentThroughput](#)
- [quickSpinIntegerNode DeviceMaxThroughput](#)
- [quickSpinCommandNode FactoryReset](#)
- [quickSpinFloatNode PowerSupplyVoltage](#)
- [quickSpinEnumerationNode DeviceIndicatorMode](#)
- [quickSpinFloatNode DeviceLinkBandwidthReserve](#)
- [quickSpinIntegerNode AasRoiOffsetY](#)
- [quickSpinIntegerNode AasRoiOffsetX](#)
- [quickSpinEnumerationNode AutoExposureControlPriority](#)
- [quickSpinFloatNode BalanceWhiteAutoLowerLimit](#)
- [quickSpinFloatNode BalanceWhiteAutoDamping](#)
- [quickSpinIntegerNode AasRoiHeight](#)
- [quickSpinFloatNode AutoExposureGreyValueUpperLimit](#)
- [quickSpinFloatNode AutoExposureTargetGreyValue](#)
- [quickSpinFloatNode AutoExposureGainLowerLimit](#)
- [quickSpinFloatNode AutoExposureGreyValueLowerLimit](#)
- [quickSpinEnumerationNode AutoExposureMeteringMode](#)
- [quickSpinFloatNode AutoExposureExposureTimeUpperLimit](#)
- [quickSpinFloatNode AutoExposureGainUpperLimit](#)

- [quickSpinFloatNode AutoExposureControlLoopDamping](#)
- [quickSpinFloatNode AutoExposureEVCompensation](#)
- [quickSpinFloatNode AutoExposureExposureTimeLowerLimit](#)
- [quickSpinEnumerationNode BalanceWhiteAutoProfile](#)
- [quickSpinEnumerationNode AutoAlgorithmSelector](#)
- [quickSpinEnumerationNode AutoExposureTargetGreyValueAuto](#)
- [quickSpinBooleanNode AasRoiEnable](#)
- [quickSpinEnumerationNode AutoExposureLightingMode](#)
- [quickSpinIntegerNode AasRoiWidth](#)
- [quickSpinFloatNode BalanceWhiteAutoUpperLimit](#)
- [quickSpinIntegerNode LinkErrorCount](#)
- [quickSpinBooleanNode GevCurrentIPConfigurationDHCP](#)
- [quickSpinIntegerNode GevInterfaceSelector](#)
- [quickSpinIntegerNode GevSCPD](#)
- [quickSpinIntegerNode GevTimestampTickFrequency](#)
- [quickSpinIntegerNode GevSCPSPacketSize](#)
- [quickSpinIntegerNode GevCurrentDefaultGateway](#)
- [quickSpinBooleanNode GevSCCFGUnconditionalStreaming](#)
- [quickSpinIntegerNode GevMCTT](#)
- [quickSpinBooleanNode GevSCPSDoNotFragment](#)
- [quickSpinIntegerNode GevCurrentSubnetMask](#)
- [quickSpinIntegerNode GevStreamChannelSelector](#)
- [quickSpinIntegerNode GevCurrentIPAddress](#)
- [quickSpinIntegerNode GevMCSP](#)
- [quickSpinIntegerNode GevGVCPPendingTimeout](#)
- [quickSpinEnumerationNode GevIEEE1588Status](#)
- [quickSpinStringNode GevFirstURL](#)
- [quickSpinIntegerNode GevMACAddress](#)
- [quickSpinIntegerNode GevPersistentSubnetMask](#)
- [quickSpinIntegerNode GevMCPHostPort](#)
- [quickSpinIntegerNode GevSCPHostPort](#)
- [quickSpinBooleanNode GevGVCPPendingAck](#)
- [quickSpinIntegerNode GevSCPInterfaceIndex](#)
- [quickSpinBooleanNode GevSupportedOption](#)
- [quickSpinEnumerationNode GevIEEE1588Mode](#)
- [quickSpinBooleanNode GevCurrentIPConfigurationLLA](#)
- [quickSpinIntegerNode GevSCSP](#)
- [quickSpinBooleanNode GevIEEE1588](#)
- [quickSpinBooleanNode GevSCCFGExtendedChunkData](#)
- [quickSpinIntegerNode GevPersistentIPAddress](#)
- [quickSpinBooleanNode GevCurrentIPConfigurationPersistentIP](#)
- [quickSpinEnumerationNode GevIEEE1588ClockAccuracy](#)
- [quickSpinIntegerNode GevHeartbeatTimeout](#)
- [quickSpinIntegerNode GevPersistentDefaultGateway](#)
- [quickSpinEnumerationNode GevCCP](#)
- [quickSpinIntegerNode GevMCDA](#)
- [quickSpinIntegerNode GevSCDA](#)
- [quickSpinIntegerNode GevSCPDirection](#)
- [quickSpinBooleanNode GevSCPSFireTestPacket](#)
- [quickSpinStringNode GevSecondURL](#)
- [quickSpinEnumerationNode GevSupportedOptionSelector](#)
- [quickSpinBooleanNode GevGVCPHeartbeatDisable](#)
- [quickSpinIntegerNode GevMCRC](#)
- [quickSpinBooleanNode GevSCPSBigEndian](#)
- [quickSpinIntegerNode GevNumberOfInterfaces](#)

- quickSpinIntegerNode TLParamsLocked
- quickSpinIntegerNode PayloadSize
- quickSpinIntegerNode PacketResendRequestCount
- quickSpinBooleanNode SharpeningEnable
- quickSpinEnumerationNode BlackLevelSelector
- quickSpinBooleanNode GammaEnable
- quickSpinBooleanNode SharpeningAuto
- quickSpinBooleanNode BlackLevelClampingEnable
- quickSpinFloatNode BalanceRatio
- quickSpinEnumerationNode BalanceWhiteAuto
- quickSpinFloatNode SharpeningThreshold
- quickSpinEnumerationNode GainAuto
- quickSpinFloatNode Sharpening
- quickSpinFloatNode Gain
- quickSpinEnumerationNode BalanceRatioSelector
- quickSpinEnumerationNode GainSelector
- quickSpinFloatNode BlackLevel
- quickSpinIntegerNode BlackLevelRaw
- quickSpinFloatNode Gamma
- quickSpinIntegerNode DefectTableIndex
- quickSpinCommandNode DefectTableFactoryRestore
- quickSpinIntegerNode DefectTableCoordinateY
- quickSpinCommandNode DefectTableSave
- quickSpinEnumerationNode DefectCorrectionMode
- quickSpinIntegerNode DefectTableCoordinateX
- quickSpinIntegerNode DefectTablePixelCount
- quickSpinBooleanNode DefectCorrectStaticEnable
- quickSpinCommandNode DefectTableApply
- quickSpinBooleanNode UserSetFeatureEnable
- quickSpinCommandNode UserSetSave
- quickSpinEnumerationNode UserSetSelector
- quickSpinCommandNode UserSetLoad
- quickSpinEnumerationNode UserSetDefault
- quickSpinEnumerationNode SerialPortBaudRate
- quickSpinIntegerNode SerialPortDataBits
- quickSpinEnumerationNode SerialPortParity
- quickSpinIntegerNode SerialTransmitQueueMaxCharacterCount
- quickSpinIntegerNode SerialReceiveQueueCurrentCharacterCount
- quickSpinEnumerationNode SerialPortSelector
- quickSpinEnumerationNode SerialPortStopBits
- quickSpinCommandNode SerialReceiveQueueClear
- quickSpinIntegerNode SerialReceiveFramingErrorCount
- quickSpinIntegerNode SerialTransmitQueueCurrentCharacterCount
- quickSpinIntegerNode SerialReceiveParityErrorCount
- quickSpinEnumerationNode SerialPortSource
- quickSpinIntegerNode SerialReceiveQueueMaxCharacterCount
- quickSpinIntegerNode SequencerSetStart
- quickSpinEnumerationNode SequencerMode
- quickSpinEnumerationNode SequencerConfigurationValid
- quickSpinEnumerationNode SequencerSetValid
- quickSpinIntegerNode SequencerSetSelector
- quickSpinEnumerationNode SequencerTriggerActivation
- quickSpinEnumerationNode SequencerConfigurationMode
- quickSpinCommandNode SequencerSetSave
- quickSpinEnumerationNode SequencerTriggerSource

- [quickSpinIntegerNode SequencerSetActive](#)
- [quickSpinIntegerNode SequencerSetNext](#)
- [quickSpinCommandNode SequencerSetLoad](#)
- [quickSpinIntegerNode SequencerPathSelector](#)
- [quickSpinBooleanNode SequencerFeatureEnable](#)
- [quickSpinIntegerNode TransferBlockCount](#)
- [quickSpinCommandNode TransferStart](#)
- [quickSpinIntegerNode TransferQueueMaxBlockCount](#)
- [quickSpinIntegerNode TransferQueueCurrentBlockCount](#)
- [quickSpinEnumerationNode TransferQueueMode](#)
- [quickSpinEnumerationNode TransferOperationMode](#)
- [quickSpinCommandNode TransferStop](#)
- [quickSpinIntegerNode TransferQueueOverflowCount](#)
- [quickSpinEnumerationNode TransferControlMode](#)
- [quickSpinFloatNode ChunkBlackLevel](#)
- [quickSpinIntegerNode ChunkFrameID](#)
- [quickSpinStringNode ChunkSerialData](#)
- [quickSpinFloatNode ChunkExposureTime](#)
- [quickSpinBooleanNode ChunkSerialReceiveOverflow](#)
- [quickSpinIntegerNode ChunkTimestamp](#)
- [quickSpinBooleanNode ChunkModeActive](#)
- [quickSpinIntegerNode ChunkExposureEndLineStatusAll](#)
- [quickSpinEnumerationNode ChunkGainSelector](#)
- [quickSpinEnumerationNode ChunkSelector](#)
- [quickSpinEnumerationNode ChunkBlackLevelSelector](#)
- [quickSpinIntegerNode ChunkWidth](#)
- [quickSpinIntegerNode ChunkImage](#)
- [quickSpinIntegerNode ChunkHeight](#)
- [quickSpinEnumerationNode ChunkPixelFormat](#)
- [quickSpinFloatNode ChunkGain](#)
- [quickSpinIntegerNode ChunkSequencerSetActive](#)
- [quickSpinIntegerNode ChunkCRC](#)
- [quickSpinIntegerNode ChunkOffsetX](#)
- [quickSpinIntegerNode ChunkOffsetY](#)
- [quickSpinBooleanNode ChunkEnable](#)
- [quickSpinIntegerNode ChunkSerialDataLength](#)
- [quickSpinIntegerNode FileAccessOffset](#)
- [quickSpinIntegerNode FileAccessLength](#)
- [quickSpinEnumerationNode FileOperationStatus](#)
- [quickSpinCommandNode FileOperationExecute](#)
- [quickSpinEnumerationNode FileOpenMode](#)
- [quickSpinIntegerNode FileOperationResult](#)
- [quickSpinEnumerationNode FileOperationSelector](#)
- [quickSpinEnumerationNode FileSelector](#)
- [quickSpinIntegerNode FileSize](#)
- [quickSpinEnumerationNode BinningSelector](#)
- [quickSpinIntegerNode PixelDynamicRangeMin](#)
- [quickSpinIntegerNode PixelDynamicRangeMax](#)
- [quickSpinIntegerNode OffsetY](#)
- [quickSpinIntegerNode BinningHorizontal](#)
- [quickSpinIntegerNode Width](#)
- [quickSpinEnumerationNode TestPatternGeneratorSelector](#)
- [quickSpinFloatNode CompressionRatio](#)
- [quickSpinBooleanNode ReverseX](#)
- [quickSpinBooleanNode ReverseY](#)

- [quickSpinEnumerationNode TestPattern](#)
- [quickSpinEnumerationNode PixelColorFilter](#)
- [quickSpinIntegerNode WidthMax](#)
- [quickSpinEnumerationNode AdcBitDepth](#)
- [quickSpinIntegerNode BinningVertical](#)
- [quickSpinEnumerationNode DecimationHorizontalMode](#)
- [quickSpinEnumerationNode BinningVerticalMode](#)
- [quickSpinIntegerNode OffsetX](#)
- [quickSpinIntegerNode HeightMax](#)
- [quickSpinIntegerNode DecimationHorizontal](#)
- [quickSpinEnumerationNode PixelSize](#)
- [quickSpinIntegerNode SensorHeight](#)
- [quickSpinEnumerationNode DecimationSelector](#)
- [quickSpinBooleanNode IspEnable](#)
- [quickSpinBooleanNode AdaptiveCompressionEnable](#)
- [quickSpinEnumerationNode ImageCompressionMode](#)
- [quickSpinIntegerNode DecimationVertical](#)
- [quickSpinIntegerNode Height](#)
- [quickSpinEnumerationNode BinningHorizontalMode](#)
- [quickSpinEnumerationNode PixelFormat](#)
- [quickSpinIntegerNode SensorWidth](#)
- [quickSpinEnumerationNode DecimationVerticalMode](#)
- [quickSpinCommandNode TestEventGenerate](#)
- [quickSpinCommandNode TriggerEventTest](#)
- [quickSpinIntegerNode GuiXmlManifestAddress](#)
- [quickSpinIntegerNode Test0001](#)
- [quickSpinBooleanNode V3_3Enable](#)
- [quickSpinEnumerationNode LineMode](#)
- [quickSpinEnumerationNode LineSource](#)
- [quickSpinEnumerationNode LineInputFilterSelector](#)
- [quickSpinBooleanNode UserOutputValue](#)
- [quickSpinIntegerNode UserOutputValueAll](#)
- [quickSpinEnumerationNode UserOutputSelector](#)
- [quickSpinBooleanNode LineStatus](#)
- [quickSpinEnumerationNode LineFormat](#)
- [quickSpinIntegerNode LineStatusAll](#)
- [quickSpinEnumerationNode LineSelector](#)
- [quickSpinEnumerationNode ExposureActiveMode](#)
- [quickSpinBooleanNode LineInverter](#)
- [quickSpinFloatNode LineFilterWidth](#)
- [quickSpinEnumerationNode CounterTriggerActivation](#)
- [quickSpinIntegerNode CounterValue](#)
- [quickSpinEnumerationNode CounterSelector](#)
- [quickSpinIntegerNode CounterValueAtReset](#)
- [quickSpinEnumerationNode CounterStatus](#)
- [quickSpinEnumerationNode CounterTriggerSource](#)
- [quickSpinIntegerNode CounterDelay](#)
- [quickSpinEnumerationNode CounterResetSource](#)
- [quickSpinEnumerationNode CounterEventSource](#)
- [quickSpinEnumerationNode CounterEventActivation](#)
- [quickSpinIntegerNode CounterDuration](#)
- [quickSpinEnumerationNode CounterResetActivation](#)
- [quickSpinEnumerationNode DeviceType](#)
- [quickSpinStringNode DeviceFamilyName](#)
- [quickSpinIntegerNode DeviceSFNCVersionMajor](#)

- [quickSpinIntegerNode DeviceSFNCVersionMinor](#)
- [quickSpinIntegerNode DeviceSFNCVersionSubMinor](#)
- [quickSpinIntegerNode DeviceManifestEntrySelector](#)
- [quickSpinIntegerNode DeviceManifestXMLMajorVersion](#)
- [quickSpinIntegerNode DeviceManifestXMLMinorVersion](#)
- [quickSpinIntegerNode DeviceManifestXMLSubMinorVersion](#)
- [quickSpinIntegerNode DeviceManifestSchemaMajorVersion](#)
- [quickSpinIntegerNode DeviceManifestSchemaMinorVersion](#)
- [quickSpinStringNode DeviceManifestPrimaryURL](#)
- [quickSpinStringNode DeviceManifestSecondaryURL](#)
- [quickSpinIntegerNode DeviceTLVersionSubMinor](#)
- [quickSpinIntegerNode DeviceGenCPVersionMajor](#)
- [quickSpinIntegerNode DeviceGenCPVersionMinor](#)
- [quickSpinIntegerNode DeviceConnectionSelector](#)
- [quickSpinIntegerNode DeviceConnectionSpeed](#)
- [quickSpinEnumerationNode DeviceConnectionStatus](#)
- [quickSpinIntegerNode DeviceLinkSelector](#)
- [quickSpinEnumerationNode DeviceLinkThroughputLimitMode](#)
- [quickSpinIntegerNode DeviceLinkConnectionCount](#)
- [quickSpinEnumerationNode DeviceLinkHeartbeatMode](#)
- [quickSpinFloatNode DeviceLinkHeartbeatTimeout](#)
- [quickSpinFloatNode DeviceLinkCommandTimeout](#)
- [quickSpinIntegerNode DeviceStreamChannelSelector](#)
- [quickSpinEnumerationNode DeviceStreamChannelType](#)
- [quickSpinIntegerNode DeviceStreamChannelLink](#)
- [quickSpinEnumerationNode DeviceStreamChannelEndianness](#)
- [quickSpinIntegerNode DeviceStreamChannelPacketSize](#)
- [quickSpinCommandNode DeviceFeaturePersistenceStart](#)
- [quickSpinCommandNode DeviceFeaturePersistenceEnd](#)
- [quickSpinCommandNode DeviceRegistersStreamingStart](#)
- [quickSpinCommandNode DeviceRegistersStreamingEnd](#)
- [quickSpinCommandNode DeviceRegistersCheck](#)
- [quickSpinBooleanNode DeviceRegistersValid](#)
- [quickSpinEnumerationNode DeviceClockSelector](#)
- [quickSpinFloatNode DeviceClockFrequency](#)
- [quickSpinEnumerationNode DeviceSerialPortSelector](#)
- [quickSpinEnumerationNode DeviceSerialPortBaudRate](#)
- [quickSpinIntegerNode Timestamp](#)
- [quickSpinEnumerationNode SensorTaps](#)
- [quickSpinEnumerationNode SensorDigitizationTaps](#)
- [quickSpinEnumerationNode RegionSelector](#)
- [quickSpinEnumerationNode RegionMode](#)
- [quickSpinEnumerationNode RegionDestination](#)
- [quickSpinEnumerationNode ImageComponentSelector](#)
- [quickSpinBooleanNode ImageComponentEnable](#)
- [quickSpinIntegerNode LinePitch](#)
- [quickSpinEnumerationNode PixelFormatInfoSelector](#)
- [quickSpinIntegerNode PixelFormatInfoID](#)
- [quickSpinEnumerationNode Deinterlacing](#)
- [quickSpinEnumerationNode ImageCompressionRateOption](#)
- [quickSpinIntegerNode ImageCompressionQuality](#)
- [quickSpinFloatNode ImageCompressionBitrate](#)
- [quickSpinEnumerationNode ImageCompressionJPEGFormatOption](#)
- [quickSpinCommandNode AcquisitionAbort](#)
- [quickSpinCommandNode AcquisitionArm](#)

- [quickSpinEnumerationNode AcquisitionStatusSelector](#)
- [quickSpinBooleanNode AcquisitionStatus](#)
- [quickSpinIntegerNode TriggerDivider](#)
- [quickSpinIntegerNode TriggerMultiplier](#)
- [quickSpinEnumerationNode ExposureTimeMode](#)
- [quickSpinEnumerationNode ExposureTimeSelector](#)
- [quickSpinEnumerationNode GainAutoBalance](#)
- [quickSpinEnumerationNode BlackLevelAuto](#)
- [quickSpinEnumerationNode BlackLevelAutoBalance](#)
- [quickSpinEnumerationNode WhiteClipSelector](#)
- [quickSpinFloatNode WhiteClip](#)
- [quickSpinRegisterNode LUTValueAll](#)
- [quickSpinIntegerNode UserOutputValueAllMask](#)
- [quickSpinCommandNode CounterReset](#)
- [quickSpinEnumerationNode TimerSelector](#)
- [quickSpinFloatNode TimerDuration](#)
- [quickSpinFloatNode TimerDelay](#)
- [quickSpinCommandNode TimerReset](#)
- [quickSpinFloatNode TimerValue](#)
- [quickSpinEnumerationNode TimerStatus](#)
- [quickSpinEnumerationNode TimerTriggerSource](#)
- [quickSpinEnumerationNode TimerTriggerActivation](#)
- [quickSpinEnumerationNode EncoderSelector](#)
- [quickSpinEnumerationNode EncoderSourceA](#)
- [quickSpinEnumerationNode EncoderSourceB](#)
- [quickSpinEnumerationNode EncoderMode](#)
- [quickSpinIntegerNode EncoderDivider](#)
- [quickSpinEnumerationNode EncoderOutputMode](#)
- [quickSpinEnumerationNode EncoderStatus](#)
- [quickSpinFloatNode EncoderTimeout](#)
- [quickSpinEnumerationNode EncoderResetSource](#)
- [quickSpinEnumerationNode EncoderResetActivation](#)
- [quickSpinCommandNode EncoderReset](#)
- [quickSpinIntegerNode EncoderValue](#)
- [quickSpinIntegerNode EncoderValueAtReset](#)
- [quickSpinEnumerationNode SoftwareSignalSelector](#)
- [quickSpinCommandNode SoftwareSignalPulse](#)
- [quickSpinEnumerationNode ActionUnconditionalMode](#)
- [quickSpinIntegerNode ActionDeviceKey](#)
- [quickSpinIntegerNode ActionQueueSize](#)
- [quickSpinIntegerNode ActionSelector](#)
- [quickSpinIntegerNode ActionGroupMask](#)
- [quickSpinIntegerNode ActionGroupKey](#)
- [quickSpinIntegerNode EventAcquisitionTrigger](#)
- [quickSpinIntegerNode EventAcquisitionTriggerTimestamp](#)
- [quickSpinIntegerNode EventAcquisitionTriggerFrameID](#)
- [quickSpinIntegerNode EventAcquisitionStart](#)
- [quickSpinIntegerNode EventAcquisitionStartTimestamp](#)
- [quickSpinIntegerNode EventAcquisitionStartFrameID](#)
- [quickSpinIntegerNode EventAcquisitionEnd](#)
- [quickSpinIntegerNode EventAcquisitionEndTimestamp](#)
- [quickSpinIntegerNode EventAcquisitionEndFrameID](#)
- [quickSpinIntegerNode EventAcquisitionTransferStart](#)
- [quickSpinIntegerNode EventAcquisitionTransferStartTimestamp](#)
- [quickSpinIntegerNode EventAcquisitionTransferStartFrameID](#)

- [quickSpinIntegerNode EventAcquisitionTransferEnd](#)
- [quickSpinIntegerNode EventAcquisitionTransferEndTimestamp](#)
- [quickSpinIntegerNode EventAcquisitionTransferEndFrameID](#)
- [quickSpinIntegerNode EventAcquisitionError](#)
- [quickSpinIntegerNode EventAcquisitionErrorTimestamp](#)
- [quickSpinIntegerNode EventAcquisitionErrorFrameID](#)
- [quickSpinIntegerNode EventFrameTrigger](#)
- [quickSpinIntegerNode EventFrameTriggerTimestamp](#)
- [quickSpinIntegerNode EventFrameTriggerFrameID](#)
- [quickSpinIntegerNode EventFrameStart](#)
- [quickSpinIntegerNode EventFrameStartTimestamp](#)
- [quickSpinIntegerNode EventFrameStartFrameID](#)
- [quickSpinIntegerNode EventFrameEnd](#)
- [quickSpinIntegerNode EventFrameEndTimestamp](#)
- [quickSpinIntegerNode EventFrameEndFrameID](#)
- [quickSpinIntegerNode EventFrameBurstStart](#)
- [quickSpinIntegerNode EventFrameBurstStartTimestamp](#)
- [quickSpinIntegerNode EventFrameBurstStartFrameID](#)
- [quickSpinIntegerNode EventFrameBurstEnd](#)
- [quickSpinIntegerNode EventFrameBurstEndTimestamp](#)
- [quickSpinIntegerNode EventFrameBurstEndFrameID](#)
- [quickSpinIntegerNode EventFrameTransferStart](#)
- [quickSpinIntegerNode EventFrameTransferStartTimestamp](#)
- [quickSpinIntegerNode EventFrameTransferStartFrameID](#)
- [quickSpinIntegerNode EventFrameTransferEnd](#)
- [quickSpinIntegerNode EventFrameTransferEndTimestamp](#)
- [quickSpinIntegerNode EventFrameTransferEndFrameID](#)
- [quickSpinIntegerNode EventExposureStart](#)
- [quickSpinIntegerNode EventExposureStartTimestamp](#)
- [quickSpinIntegerNode EventExposureStartFrameID](#)
- [quickSpinIntegerNode EventStream0TransferStart](#)
- [quickSpinIntegerNode EventStream0TransferStartTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferStartFrameID](#)
- [quickSpinIntegerNode EventStream0TransferEnd](#)
- [quickSpinIntegerNode EventStream0TransferEndTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferEndFrameID](#)
- [quickSpinIntegerNode EventStream0TransferPause](#)
- [quickSpinIntegerNode EventStream0TransferPauseTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferPauseFrameID](#)
- [quickSpinIntegerNode EventStream0TransferResume](#)
- [quickSpinIntegerNode EventStream0TransferResumeTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferResumeFrameID](#)
- [quickSpinIntegerNode EventStream0TransferBlockStart](#)
- [quickSpinIntegerNode EventStream0TransferBlockStartTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferBlockStartFrameID](#)
- [quickSpinIntegerNode EventStream0TransferBlockEnd](#)
- [quickSpinIntegerNode EventStream0TransferBlockEndTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferBlockEndFrameID](#)
- [quickSpinIntegerNode EventStream0TransferBlockTrigger](#)
- [quickSpinIntegerNode EventStream0TransferBlockTriggerTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferBlockTriggerFrameID](#)
- [quickSpinIntegerNode EventStream0TransferBurstStart](#)
- [quickSpinIntegerNode EventStream0TransferBurstStartTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferBurstStartFrameID](#)
- [quickSpinIntegerNode EventStream0TransferBurstEnd](#)

- [quickSpinIntegerNode EventStream0TransferBurstEndTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferBurstEndFrameID](#)
- [quickSpinIntegerNode EventStream0TransferOverflow](#)
- [quickSpinIntegerNode EventStream0TransferOverflowTimestamp](#)
- [quickSpinIntegerNode EventStream0TransferOverflowFrameID](#)
- [quickSpinIntegerNode EventSequencerSetChange](#)
- [quickSpinIntegerNode EventSequencerSetChangeTimestamp](#)
- [quickSpinIntegerNode EventSequencerSetChangeFrameID](#)
- [quickSpinIntegerNode EventCounter0Start](#)
- [quickSpinIntegerNode EventCounter0StartTimestamp](#)
- [quickSpinIntegerNode EventCounter0StartFrameID](#)
- [quickSpinIntegerNode EventCounter1Start](#)
- [quickSpinIntegerNode EventCounter1StartTimestamp](#)
- [quickSpinIntegerNode EventCounter1StartFrameID](#)
- [quickSpinIntegerNode EventCounter0End](#)
- [quickSpinIntegerNode EventCounter0EndTimestamp](#)
- [quickSpinIntegerNode EventCounter0EndFrameID](#)
- [quickSpinIntegerNode EventCounter1End](#)
- [quickSpinIntegerNode EventCounter1EndTimestamp](#)
- [quickSpinIntegerNode EventCounter1EndFrameID](#)
- [quickSpinIntegerNode EventTimer0Start](#)
- [quickSpinIntegerNode EventTimer0StartTimestamp](#)
- [quickSpinIntegerNode EventTimer0StartFrameID](#)
- [quickSpinIntegerNode EventTimer1Start](#)
- [quickSpinIntegerNode EventTimer1StartTimestamp](#)
- [quickSpinIntegerNode EventTimer1StartFrameID](#)
- [quickSpinIntegerNode EventTimer0End](#)
- [quickSpinIntegerNode EventTimer0EndTimestamp](#)
- [quickSpinIntegerNode EventTimer0EndFrameID](#)
- [quickSpinIntegerNode EventTimer1End](#)
- [quickSpinIntegerNode EventTimer1EndTimestamp](#)
- [quickSpinIntegerNode EventTimer1EndFrameID](#)
- [quickSpinIntegerNode EventEncoder0Stopped](#)
- [quickSpinIntegerNode EventEncoder0StoppedTimestamp](#)
- [quickSpinIntegerNode EventEncoder0StoppedFrameID](#)
- [quickSpinIntegerNode EventEncoder1Stopped](#)
- [quickSpinIntegerNode EventEncoder1StoppedTimestamp](#)
- [quickSpinIntegerNode EventEncoder1StoppedFrameID](#)
- [quickSpinIntegerNode EventEncoder0Restarted](#)
- [quickSpinIntegerNode EventEncoder0RestartedTimestamp](#)
- [quickSpinIntegerNode EventEncoder0RestartedFrameID](#)
- [quickSpinIntegerNode EventEncoder1Restarted](#)
- [quickSpinIntegerNode EventEncoder1RestartedTimestamp](#)
- [quickSpinIntegerNode EventEncoder1RestartedFrameID](#)
- [quickSpinIntegerNode EventLine0RisingEdge](#)
- [quickSpinIntegerNode EventLine0RisingEdgeTimestamp](#)
- [quickSpinIntegerNode EventLine0RisingEdgeFrameID](#)
- [quickSpinIntegerNode EventLine1RisingEdge](#)
- [quickSpinIntegerNode EventLine1RisingEdgeTimestamp](#)
- [quickSpinIntegerNode EventLine1RisingEdgeFrameID](#)
- [quickSpinIntegerNode EventLine0FallingEdge](#)
- [quickSpinIntegerNode EventLine0FallingEdgeTimestamp](#)
- [quickSpinIntegerNode EventLine0FallingEdgeFrameID](#)
- [quickSpinIntegerNode EventLine1FallingEdge](#)
- [quickSpinIntegerNode EventLine1FallingEdgeTimestamp](#)

- [quickSpinIntegerNode EventLine1FallingEdgeFrameID](#)
- [quickSpinIntegerNode EventLine0AnyEdge](#)
- [quickSpinIntegerNode EventLine0AnyEdgeTimestamp](#)
- [quickSpinIntegerNode EventLine0AnyEdgeFrameID](#)
- [quickSpinIntegerNode EventLine1AnyEdge](#)
- [quickSpinIntegerNode EventLine1AnyEdgeTimestamp](#)
- [quickSpinIntegerNode EventLine1AnyEdgeFrameID](#)
- [quickSpinIntegerNode EventLinkTrigger0](#)
- [quickSpinIntegerNode EventLinkTrigger0Timestamp](#)
- [quickSpinIntegerNode EventLinkTrigger0FrameID](#)
- [quickSpinIntegerNode EventLinkTrigger1](#)
- [quickSpinIntegerNode EventLinkTrigger1Timestamp](#)
- [quickSpinIntegerNode EventLinkTrigger1FrameID](#)
- [quickSpinIntegerNode EventActionLate](#)
- [quickSpinIntegerNode EventActionLateTimestamp](#)
- [quickSpinIntegerNode EventActionLateFrameID](#)
- [quickSpinIntegerNode EventLinkSpeedChange](#)
- [quickSpinIntegerNode EventLinkSpeedChangeTimestamp](#)
- [quickSpinIntegerNode EventLinkSpeedChangeFrameID](#)
- [quickSpinRegisterNode FileAccessBuffer](#)
- [quickSpinIntegerNode SourceCount](#)
- [quickSpinEnumerationNode SourceSelector](#)
- [quickSpinEnumerationNode TransferSelector](#)
- [quickSpinIntegerNode TransferBurstCount](#)
- [quickSpinCommandNode TransferAbort](#)
- [quickSpinCommandNode TransferPause](#)
- [quickSpinCommandNode TransferResume](#)
- [quickSpinEnumerationNode TransferTriggerSelector](#)
- [quickSpinEnumerationNode TransferTriggerMode](#)
- [quickSpinEnumerationNode TransferTriggerSource](#)
- [quickSpinEnumerationNode TransferTriggerActivation](#)
- [quickSpinEnumerationNode TransferStatusSelector](#)
- [quickSpinBooleanNode TransferStatus](#)
- [quickSpinEnumerationNode TransferComponentSelector](#)
- [quickSpinIntegerNode TransferStreamChannel](#)
- [quickSpinEnumerationNode Scan3dDistanceUnit](#)
- [quickSpinEnumerationNode Scan3dCoordinateSystem](#)
- [quickSpinEnumerationNode Scan3dOutputMode](#)
- [quickSpinEnumerationNode Scan3dCoordinateSystemReference](#)
- [quickSpinEnumerationNode Scan3dCoordinateSelector](#)
- [quickSpinFloatNode Scan3dCoordinateScale](#)
- [quickSpinFloatNode Scan3dCoordinateOffset](#)
- [quickSpinBooleanNode Scan3dInvalidDataFlag](#)
- [quickSpinFloatNode Scan3dInvalidDataValue](#)
- [quickSpinFloatNode Scan3dAxisMin](#)
- [quickSpinFloatNode Scan3dAxisMax](#)
- [quickSpinEnumerationNode Scan3dCoordinateTransformSelector](#)
- [quickSpinFloatNode Scan3dTransformValue](#)
- [quickSpinEnumerationNode Scan3dCoordinateReferenceSelector](#)
- [quickSpinFloatNode Scan3dCoordinateReferenceValue](#)
- [quickSpinIntegerNode ChunkPartSelector](#)
- [quickSpinEnumerationNode ChunkImageComponent](#)
- [quickSpinIntegerNode ChunkPixelDynamicRangeMin](#)
- [quickSpinIntegerNode ChunkPixelDynamicRangeMax](#)
- [quickSpinIntegerNode ChunkTimestampLatchValue](#)

- [quickSpinIntegerNode ChunkLineStatusAll](#)
- [quickSpinEnumerationNode ChunkCounterSelector](#)
- [quickSpinIntegerNode ChunkCounterValue](#)
- [quickSpinEnumerationNode ChunkTimerSelector](#)
- [quickSpinFloatNode ChunkTimerValue](#)
- [quickSpinEnumerationNode ChunkEncoderSelector](#)
- [quickSpinIntegerNode ChunkScanLineSelector](#)
- [quickSpinIntegerNode ChunkEncoderValue](#)
- [quickSpinEnumerationNode ChunkEncoderStatus](#)
- [quickSpinEnumerationNode ChunkExposureTimeSelector](#)
- [quickSpinIntegerNode ChunkLinePitch](#)
- [quickSpinEnumerationNode ChunkSourceID](#)
- [quickSpinEnumerationNode ChunkRegionID](#)
- [quickSpinIntegerNode ChunkTransferBlockID](#)
- [quickSpinEnumerationNode ChunkTransferStreamID](#)
- [quickSpinIntegerNode ChunkTransferQueueCurrentBlockCount](#)
- [quickSpinIntegerNode ChunkStreamChannelID](#)
- [quickSpinEnumerationNode ChunkScan3dDistanceUnit](#)
- [quickSpinEnumerationNode ChunkScan3dOutputMode](#)
- [quickSpinEnumerationNode ChunkScan3dCoordinateSystem](#)
- [quickSpinEnumerationNode ChunkScan3dCoordinateSystemReference](#)
- [quickSpinEnumerationNode ChunkScan3dCoordinateSelector](#)
- [quickSpinFloatNode ChunkScan3dCoordinateScale](#)
- [quickSpinFloatNode ChunkScan3dCoordinateOffset](#)
- [quickSpinBooleanNode ChunkScan3dInvalidDataFlag](#)
- [quickSpinFloatNode ChunkScan3dInvalidDataValue](#)
- [quickSpinFloatNode ChunkScan3dAxisMin](#)
- [quickSpinFloatNode ChunkScan3dAxisMax](#)
- [quickSpinEnumerationNode ChunkScan3dCoordinateTransformSelector](#)
- [quickSpinFloatNode ChunkScan3dTransformValue](#)
- [quickSpinEnumerationNode ChunkScan3dCoordinateReferenceSelector](#)
- [quickSpinFloatNode ChunkScan3dCoordinateReferenceValue](#)
- [quickSpinIntegerNode TestPendingAck](#)
- [quickSpinEnumerationNode DeviceTapGeometry](#)
- [quickSpinEnumerationNode GevPhysicalLinkConfiguration](#)
- [quickSpinEnumerationNode GevCurrentPhysicalLinkConfiguration](#)
- [quickSpinIntegerNode GevActiveLinkCount](#)
- [quickSpinBooleanNode GevPAUSEFrameReception](#)
- [quickSpinBooleanNode GevPAUSEFrameTransmission](#)
- [quickSpinEnumerationNode GevIPConfigurationStatus](#)
- [quickSpinIntegerNode GevDiscoveryAckDelay](#)
- [quickSpinEnumerationNode GevGVCPExtendedStatusCodesSelector](#)
- [quickSpinBooleanNode GevGVCPExtendedStatusCodes](#)
- [quickSpinIntegerNode GevPrimaryApplicationSwitchoverKey](#)
- [quickSpinEnumerationNode GevGVSPExtendedIDMode](#)
- [quickSpinIntegerNode GevPrimaryApplicationSocket](#)
- [quickSpinIntegerNode GevPrimaryApplicationIPAddress](#)
- [quickSpinBooleanNode GevSCCFGPacketResendDestination](#)
- [quickSpinBooleanNode GevSCCFGAllInTransmission](#)
- [quickSpinIntegerNode GevSCZoneCount](#)
- [quickSpinIntegerNode GevSCZoneDirectionAll](#)
- [quickSpinBooleanNode GevSCZoneConfigurationLock](#)
- [quickSpinIntegerNode aPAUSEMACCtrlFramesTransmitted](#)
- [quickSpinIntegerNode aPAUSEMACCtrlFramesReceived](#)
- [quickSpinEnumerationNode CIConfiguration](#)

- [quickSpinEnumerationNode](#) CTimeSlotsCount
- [quickSpinEnumerationNode](#) CxpLinkConfigurationStatus
- [quickSpinEnumerationNode](#) CxpLinkConfigurationPreferred
- [quickSpinEnumerationNode](#) CxpLinkConfiguration
- [quickSpinIntegerNode](#) CxpConnectionSelector
- [quickSpinEnumerationNode](#) CxpConnectionTestMode
- [quickSpinIntegerNode](#) CxpConnectionTestErrorCount
- [quickSpinIntegerNode](#) CxpConnectionTestPacketCount
- [quickSpinCommandNode](#) CxpPoCxpAuto
- [quickSpinCommandNode](#) CxpPoCxpTurnOff
- [quickSpinCommandNode](#) CxpPoCxpTripReset
- [quickSpinEnumerationNode](#) CxpPoCxpStatus
- [quickSpinIntegerNode](#) ChunkInferenceFrameld
- [quickSpinIntegerNode](#) ChunkInferenceResult
- [quickSpinFloatNode](#) ChunkInferenceConfidence
- [quickSpinRegisterNode](#) ChunkInferenceBoundingBoxResult

5.2.1 Field Documentation

5.2.1.1 AasRoiEnable

[quickSpinBooleanNode](#) AasRoiEnable

5.2.1.2 AasRoiHeight

[quickSpinIntegerNode](#) AasRoiHeight

5.2.1.3 AasRoiOffsetX

[quickSpinIntegerNode](#) AasRoiOffsetX

5.2.1.4 AasRoiOffsetY

[quickSpinIntegerNode](#) AasRoiOffsetY

5.2.1.5 AasRoiWidth

`quickSpinIntegerNode` AasRoiWidth

5.2.1.6 AcquisitionAbort

`quickSpinCommandNode` AcquisitionAbort

5.2.1.7 AcquisitionArm

`quickSpinCommandNode` AcquisitionArm

5.2.1.8 AcquisitionBurstFrameCount

`quickSpinIntegerNode` AcquisitionBurstFrameCount

5.2.1.9 AcquisitionFrameCount

`quickSpinIntegerNode` AcquisitionFrameCount

5.2.1.10 AcquisitionFrameRate

`quickSpinFloatNode` AcquisitionFrameRate

5.2.1.11 AcquisitionFrameRateEnable

`quickSpinBooleanNode` AcquisitionFrameRateEnable

5.2.1.12 AcquisitionLineRate

`quickSpinFloatNode` AcquisitionLineRate

5.2.1.13 AcquisitionMode

[quickSpinEnumerationNode](#) AcquisitionMode

5.2.1.14 AcquisitionResultingFrameRate

[quickSpinFloatNode](#) AcquisitionResultingFrameRate

5.2.1.15 AcquisitionStart

[quickSpinCommandNode](#) AcquisitionStart

5.2.1.16 AcquisitionStatus

[quickSpinBooleanNode](#) AcquisitionStatus

5.2.1.17 AcquisitionStatusSelector

[quickSpinEnumerationNode](#) AcquisitionStatusSelector

5.2.1.18 AcquisitionStop

[quickSpinCommandNode](#) AcquisitionStop

5.2.1.19 ActionDeviceKey

[quickSpinIntegerNode](#) ActionDeviceKey

5.2.1.20 ActionGroupKey

[quickSpinIntegerNode](#) ActionGroupKey

5.2.1.21 ActionGroupMask

`quickSpinIntegerNode` ActionGroupMask

5.2.1.22 ActionQueueSize

`quickSpinIntegerNode` ActionQueueSize

5.2.1.23 ActionSelector

`quickSpinIntegerNode` ActionSelector

5.2.1.24 ActionUnconditionalMode

`quickSpinEnumerationNode` ActionUnconditionalMode

5.2.1.25 AdaptiveCompressionEnable

`quickSpinBooleanNode` AdaptiveCompressionEnable

5.2.1.26 AdcBitDepth

`quickSpinEnumerationNode` AdcBitDepth

5.2.1.27 aPAUSEMACCtrlFramesReceived

`quickSpinIntegerNode` aPAUSEMACCtrlFramesReceived

5.2.1.28 aPAUSEMACCtrlFramesTransmitted

`quickSpinIntegerNode` aPAUSEMACCtrlFramesTransmitted

5.2.1.29 AutoAlgorithmSelector

`quickSpinEnumerationNode` AutoAlgorithmSelector

5.2.1.30 AutoExposureControlLoopDamping

`quickSpinFloatNode` AutoExposureControlLoopDamping

5.2.1.31 AutoExposureControlPriority

`quickSpinEnumerationNode` AutoExposureControlPriority

5.2.1.32 AutoExposureEVCompensation

`quickSpinFloatNode` AutoExposureEVCompensation

5.2.1.33 AutoExposureExposureTimeLowerLimit

`quickSpinFloatNode` AutoExposureExposureTimeLowerLimit

5.2.1.34 AutoExposureExposureTimeUpperLimit

`quickSpinFloatNode` AutoExposureExposureTimeUpperLimit

5.2.1.35 AutoExposureGainLowerLimit

`quickSpinFloatNode` AutoExposureGainLowerLimit

5.2.1.36 AutoExposureGainUpperLimit

`quickSpinFloatNode` AutoExposureGainUpperLimit

5.2.1.37 AutoExposureGreyValueLowerLimit

`quickSpinFloatNode` AutoExposureGreyValueLowerLimit

5.2.1.38 AutoExposureGreyValueUpperLimit

`quickSpinFloatNode` AutoExposureGreyValueUpperLimit

5.2.1.39 AutoExposureLightingMode

`quickSpinEnumerationNode` AutoExposureLightingMode

5.2.1.40 AutoExposureMeteringMode

`quickSpinEnumerationNode` AutoExposureMeteringMode

5.2.1.41 AutoExposureTargetGreyValue

`quickSpinFloatNode` AutoExposureTargetGreyValue

5.2.1.42 AutoExposureTargetGreyValueAuto

`quickSpinEnumerationNode` AutoExposureTargetGreyValueAuto

5.2.1.43 BalanceRatio

`quickSpinFloatNode` BalanceRatio

5.2.1.44 BalanceRatioSelector

`quickSpinEnumerationNode` BalanceRatioSelector

5.2.1.45 BalanceWhiteAuto

[quickSpinEnumerationNode](#) BalanceWhiteAuto

5.2.1.46 BalanceWhiteAutoDamping

[quickSpinFloatNode](#) BalanceWhiteAutoDamping

5.2.1.47 BalanceWhiteAutoLowerLimit

[quickSpinFloatNode](#) BalanceWhiteAutoLowerLimit

5.2.1.48 BalanceWhiteAutoProfile

[quickSpinEnumerationNode](#) BalanceWhiteAutoProfile

5.2.1.49 BalanceWhiteAutoUpperLimit

[quickSpinFloatNode](#) BalanceWhiteAutoUpperLimit

5.2.1.50 BinningHorizontal

[quickSpinIntegerNode](#) BinningHorizontal

5.2.1.51 BinningHorizontalMode

[quickSpinEnumerationNode](#) BinningHorizontalMode

5.2.1.52 BinningSelector

[quickSpinEnumerationNode](#) BinningSelector

5.2.1.53 BinningVertical

`quickSpinIntegerNode` BinningVertical

5.2.1.54 BinningVerticalMode

`quickSpinEnumerationNode` BinningVerticalMode

5.2.1.55 BlackLevel

`quickSpinFloatNode` BlackLevel

5.2.1.56 BlackLevelAuto

`quickSpinEnumerationNode` BlackLevelAuto

5.2.1.57 BlackLevelAutoBalance

`quickSpinEnumerationNode` BlackLevelAutoBalance

5.2.1.58 BlackLevelClampingEnable

`quickSpinBooleanNode` BlackLevelClampingEnable

5.2.1.59 BlackLevelRaw

`quickSpinIntegerNode` BlackLevelRaw

5.2.1.60 BlackLevelSelector

`quickSpinEnumerationNode` BlackLevelSelector

5.2.1.61 ChunkBlackLevel

[quickSpinFloatNode](#) ChunkBlackLevel

5.2.1.62 ChunkBlackLevelSelector

[quickSpinEnumerationNode](#) ChunkBlackLevelSelector

5.2.1.63 ChunkCounterSelector

[quickSpinEnumerationNode](#) ChunkCounterSelector

5.2.1.64 ChunkCounterValue

[quickSpinIntegerNode](#) ChunkCounterValue

5.2.1.65 ChunkCRC

[quickSpinIntegerNode](#) ChunkCRC

5.2.1.66 ChunkEnable

[quickSpinBooleanNode](#) ChunkEnable

5.2.1.67 ChunkEncoderSelector

[quickSpinEnumerationNode](#) ChunkEncoderSelector

5.2.1.68 ChunkEncoderStatus

[quickSpinEnumerationNode](#) ChunkEncoderStatus

5.2.1.69 ChunkEncoderValue

`quickSpinIntegerNode` ChunkEncoderValue

5.2.1.70 ChunkExposureEndLineStatusAll

`quickSpinIntegerNode` ChunkExposureEndLineStatusAll

5.2.1.71 ChunkExposureTime

`quickSpinFloatNode` ChunkExposureTime

5.2.1.72 ChunkExposureTimeSelector

`quickSpinEnumerationNode` ChunkExposureTimeSelector

5.2.1.73 ChunkFrameID

`quickSpinIntegerNode` ChunkFrameID

5.2.1.74 ChunkGain

`quickSpinFloatNode` ChunkGain

5.2.1.75 ChunkGainSelector

`quickSpinEnumerationNode` ChunkGainSelector

5.2.1.76 ChunkHeight

`quickSpinIntegerNode` ChunkHeight

5.2.1.77 ChunkImage

[quickSpinIntegerNode](#) ChunkImage

5.2.1.78 ChunkImageComponent

[quickSpinEnumerationNode](#) ChunkImageComponent

5.2.1.79 ChunkInferenceBoundingBoxResult

[quickSpinRegisterNode](#) ChunkInferenceBoundingBoxResult

5.2.1.80 ChunkInferenceConfidence

[quickSpinFloatNode](#) ChunkInferenceConfidence

5.2.1.81 ChunkInferenceFrameId

[quickSpinIntegerNode](#) ChunkInferenceFrameId

5.2.1.82 ChunkInferenceResult

[quickSpinIntegerNode](#) ChunkInferenceResult

5.2.1.83 ChunkLinePitch

[quickSpinIntegerNode](#) ChunkLinePitch

5.2.1.84 ChunkLineStatusAll

[quickSpinIntegerNode](#) ChunkLineStatusAll

5.2.1.85 ChunkModeActive

[quickSpinBooleanNode](#) ChunkModeActive

5.2.1.86 ChunkOffsetX

[quickSpinIntegerNode](#) ChunkOffsetX

5.2.1.87 ChunkOffsetY

[quickSpinIntegerNode](#) ChunkOffsetY

5.2.1.88 ChunkPartSelector

[quickSpinIntegerNode](#) ChunkPartSelector

5.2.1.89 ChunkPixelDynamicRangeMax

[quickSpinIntegerNode](#) ChunkPixelDynamicRangeMax

5.2.1.90 ChunkPixelDynamicRangeMin

[quickSpinIntegerNode](#) ChunkPixelDynamicRangeMin

5.2.1.91 ChunkPixelFormat

[quickSpinEnumerationNode](#) ChunkPixelFormat

5.2.1.92 ChunkRegionID

[quickSpinEnumerationNode](#) ChunkRegionID

5.2.1.93 ChunkScan3dAxisMax

[quickSpinFloatNode](#) ChunkScan3dAxisMax

5.2.1.94 ChunkScan3dAxisMin

[quickSpinFloatNode](#) ChunkScan3dAxisMin

5.2.1.95 ChunkScan3dCoordinateOffset

[quickSpinFloatNode](#) ChunkScan3dCoordinateOffset

5.2.1.96 ChunkScan3dCoordinateReferenceSelector

[quickSpinEnumerationNode](#) ChunkScan3dCoordinateReferenceSelector

5.2.1.97 ChunkScan3dCoordinateReferenceValue

[quickSpinFloatNode](#) ChunkScan3dCoordinateReferenceValue

5.2.1.98 ChunkScan3dCoordinateScale

[quickSpinFloatNode](#) ChunkScan3dCoordinateScale

5.2.1.99 ChunkScan3dCoordinateSelector

[quickSpinEnumerationNode](#) ChunkScan3dCoordinateSelector

5.2.1.100 ChunkScan3dCoordinateSystem

[quickSpinEnumerationNode](#) ChunkScan3dCoordinateSystem

5.2.1.101 ChunkScan3dCoordinateSystemReference

`quickSpinEnumerationNode` ChunkScan3dCoordinateSystemReference

5.2.1.102 ChunkScan3dCoordinateTransformSelector

`quickSpinEnumerationNode` ChunkScan3dCoordinateTransformSelector

5.2.1.103 ChunkScan3dDistanceUnit

`quickSpinEnumerationNode` ChunkScan3dDistanceUnit

5.2.1.104 ChunkScan3dInvalidDataFlag

`quickSpinBooleanNode` ChunkScan3dInvalidDataFlag

5.2.1.105 ChunkScan3dInvalidDataValue

`quickSpinFloatNode` ChunkScan3dInvalidDataValue

5.2.1.106 ChunkScan3dOutputMode

`quickSpinEnumerationNode` ChunkScan3dOutputMode

5.2.1.107 ChunkScan3dTransformValue

`quickSpinFloatNode` ChunkScan3dTransformValue

5.2.1.108 ChunkScanLineSelector

`quickSpinIntegerNode` ChunkScanLineSelector

5.2.1.109 ChunkSelector

[quickSpinEnumerationNode](#) ChunkSelector

5.2.1.110 ChunkSequencerSetActive

[quickSpinIntegerNode](#) ChunkSequencerSetActive

5.2.1.111 ChunkSerialData

[quickSpinStringNode](#) ChunkSerialData

5.2.1.112 ChunkSerialDataLength

[quickSpinIntegerNode](#) ChunkSerialDataLength

5.2.1.113 ChunkSerialReceiveOverflow

[quickSpinBooleanNode](#) ChunkSerialReceiveOverflow

5.2.1.114 ChunkSourceID

[quickSpinEnumerationNode](#) ChunkSourceID

5.2.1.115 ChunkStreamChannelID

[quickSpinIntegerNode](#) ChunkStreamChannelID

5.2.1.116 ChunkTimerSelector

[quickSpinEnumerationNode](#) ChunkTimerSelector

5.2.1.117 ChunkTimerValue

[quickSpinFloatNode](#) ChunkTimerValue

5.2.1.118 ChunkTimestamp

[quickSpinIntegerNode](#) ChunkTimestamp

5.2.1.119 ChunkTimestampLatchValue

[quickSpinIntegerNode](#) ChunkTimestampLatchValue

5.2.1.120 ChunkTransferBlockID

[quickSpinIntegerNode](#) ChunkTransferBlockID

5.2.1.121 ChunkTransferQueueCurrentBlockCount

[quickSpinIntegerNode](#) ChunkTransferQueueCurrentBlockCount

5.2.1.122 ChunkTransferStreamID

[quickSpinEnumerationNode](#) ChunkTransferStreamID

5.2.1.123 ChunkWidth

[quickSpinIntegerNode](#) ChunkWidth

5.2.1.124 ClConfiguration

[quickSpinEnumerationNode](#) ClConfiguration

5.2.1.125 CTimeSlotsCount

[quickSpinEnumerationNode](#) CTimeSlotsCount

5.2.1.126 ColorTransformationEnable

[quickSpinBooleanNode](#) ColorTransformationEnable

5.2.1.127 ColorTransformationSelector

[quickSpinEnumerationNode](#) ColorTransformationSelector

5.2.1.128 ColorTransformationValue

[quickSpinFloatNode](#) ColorTransformationValue

5.2.1.129 ColorTransformationValueSelector

[quickSpinEnumerationNode](#) ColorTransformationValueSelector

5.2.1.130 CompressionRatio

[quickSpinFloatNode](#) CompressionRatio

5.2.1.131 CounterDelay

[quickSpinIntegerNode](#) CounterDelay

5.2.1.132 CounterDuration

[quickSpinIntegerNode](#) CounterDuration

5.2.1.133 CounterEventActivation

[quickSpinEnumerationNode](#) CounterEventActivation

5.2.1.134 CounterEventSource

[quickSpinEnumerationNode](#) CounterEventSource

5.2.1.135 CounterReset

[quickSpinCommandNode](#) CounterReset

5.2.1.136 CounterResetActivation

[quickSpinEnumerationNode](#) CounterResetActivation

5.2.1.137 CounterResetSource

[quickSpinEnumerationNode](#) CounterResetSource

5.2.1.138 CounterSelector

[quickSpinEnumerationNode](#) CounterSelector

5.2.1.139 CounterStatus

[quickSpinEnumerationNode](#) CounterStatus

5.2.1.140 CounterTriggerActivation

[quickSpinEnumerationNode](#) CounterTriggerActivation

5.2.1.141 CounterTriggerSource

[quickSpinEnumerationNode](#) CounterTriggerSource

5.2.1.142 CounterValue

[quickSpinIntegerNode](#) CounterValue

5.2.1.143 CounterValueAtReset

[quickSpinIntegerNode](#) CounterValueAtReset

5.2.1.144 CxpConnectionSelector

[quickSpinIntegerNode](#) CxpConnectionSelector

5.2.1.145 CxpConnectionTestErrorCount

[quickSpinIntegerNode](#) CxpConnectionTestErrorCount

5.2.1.146 CxpConnectionTestMode

[quickSpinEnumerationNode](#) CxpConnectionTestMode

5.2.1.147 CxpConnectionTestPacketCount

[quickSpinIntegerNode](#) CxpConnectionTestPacketCount

5.2.1.148 CxpLinkConfiguration

[quickSpinEnumerationNode](#) CxpLinkConfiguration

5.2.1.149 CxpLinkConfigurationPreferred

[quickSpinEnumerationNode](#) CxpLinkConfigurationPreferred

5.2.1.150 CxpLinkConfigurationStatus

[quickSpinEnumerationNode](#) CxpLinkConfigurationStatus

5.2.1.151 CxpPoCxpAuto

[quickSpinCommandNode](#) CxpPoCxpAuto

5.2.1.152 CxpPoCxpStatus

[quickSpinEnumerationNode](#) CxpPoCxpStatus

5.2.1.153 CxpPoCxpTripReset

[quickSpinCommandNode](#) CxpPoCxpTripReset

5.2.1.154 CxpPoCxpTurnOff

[quickSpinCommandNode](#) CxpPoCxpTurnOff

5.2.1.155 DecimationHorizontal

[quickSpinIntegerNode](#) DecimationHorizontal

5.2.1.156 DecimationHorizontalMode

[quickSpinEnumerationNode](#) DecimationHorizontalMode

5.2.1.157 DecimationSelector

[quickSpinEnumerationNode](#) DecimationSelector

5.2.1.158 DecimationVertical

[quickSpinIntegerNode](#) DecimationVertical

5.2.1.159 DecimationVerticalMode

[quickSpinEnumerationNode](#) DecimationVerticalMode

5.2.1.160 DefectCorrectionMode

[quickSpinEnumerationNode](#) DefectCorrectionMode

5.2.1.161 DefectCorrectStaticEnable

[quickSpinBooleanNode](#) DefectCorrectStaticEnable

5.2.1.162 DefectTableApply

[quickSpinCommandNode](#) DefectTableApply

5.2.1.163 DefectTableCoordinateX

[quickSpinIntegerNode](#) DefectTableCoordinateX

5.2.1.164 DefectTableCoordinateY

[quickSpinIntegerNode](#) DefectTableCoordinateY

5.2.1.165 DefectTableFactoryRestore

[quickSpinCommandNode](#) DefectTableFactoryRestore

5.2.1.166 DefectTableIndex

[quickSpinIntegerNode](#) DefectTableIndex

5.2.1.167 DefectTablePixelCount

[quickSpinIntegerNode](#) DefectTablePixelCount

5.2.1.168 DefectTableSave

[quickSpinCommandNode](#) DefectTableSave

5.2.1.169 Deinterlacing

[quickSpinEnumerationNode](#) Deinterlacing

5.2.1.170 DeviceCharacterSet

[quickSpinEnumerationNode](#) DeviceCharacterSet

5.2.1.171 DeviceClockFrequency

[quickSpinFloatNode](#) DeviceClockFrequency

5.2.1.172 DeviceClockSelector

[quickSpinEnumerationNode](#) DeviceClockSelector

5.2.1.173 DeviceConnectionSelector

[quickSpinIntegerNode](#) DeviceConnectionSelector

5.2.1.174 DeviceConnectionSpeed

[quickSpinIntegerNode](#) DeviceConnectionSpeed

5.2.1.175 DeviceConnectionStatus

[quickSpinEnumerationNode](#) DeviceConnectionStatus

5.2.1.176 DeviceEventChannelCount

[quickSpinIntegerNode](#) DeviceEventChannelCount

5.2.1.177 DeviceFamilyName

[quickSpinStringNode](#) DeviceFamilyName

5.2.1.178 DeviceFeaturePersistenceEnd

[quickSpinCommandNode](#) DeviceFeaturePersistenceEnd

5.2.1.179 DeviceFeaturePersistenceStart

[quickSpinCommandNode](#) DeviceFeaturePersistenceStart

5.2.1.180 DeviceFirmwareVersion

[quickSpinStringNode](#) DeviceFirmwareVersion

5.2.1.181 DeviceGenCPVersionMajor

[quickSpinIntegerNode](#) DeviceGenCPVersionMajor

5.2.1.182 DeviceGenCPVersionMinor

[quickSpinIntegerNode](#) DeviceGenCPVersionMinor

5.2.1.183 DeviceID

[quickSpinStringNode](#) DeviceID

5.2.1.184 DeviceIndicatorMode

[quickSpinEnumerationNode](#) DeviceIndicatorMode

5.2.1.185 DeviceLinkBandwidthReserve

[quickSpinFloatNode](#) DeviceLinkBandwidthReserve

5.2.1.186 DeviceLinkCommandTimeout

[quickSpinFloatNode](#) DeviceLinkCommandTimeout

5.2.1.187 DeviceLinkConnectionCount

[quickSpinIntegerNode](#) DeviceLinkConnectionCount

5.2.1.188 DeviceLinkCurrentThroughput

[quickSpinIntegerNode](#) DeviceLinkCurrentThroughput

5.2.1.189 DeviceLinkHeartbeatMode

[quickSpinEnumerationNode](#) DeviceLinkHeartbeatMode

5.2.1.190 DeviceLinkHeartbeatTimeout

[quickSpinFloatNode](#) DeviceLinkHeartbeatTimeout

5.2.1.191 DeviceLinkSelector

[quickSpinIntegerNode](#) DeviceLinkSelector

5.2.1.192 DeviceLinkSpeed

[quickSpinIntegerNode](#) DeviceLinkSpeed

5.2.1.193 DeviceLinkThroughputLimit

[quickSpinIntegerNode](#) DeviceLinkThroughputLimit

5.2.1.194 DeviceLinkThroughputLimitMode

[quickSpinEnumerationNode](#) DeviceLinkThroughputLimitMode

5.2.1.195 DeviceManifestEntrySelector

[quickSpinIntegerNode](#) DeviceManifestEntrySelector

5.2.1.196 DeviceManifestPrimaryURL

[quickSpinStringNode](#) DeviceManifestPrimaryURL

5.2.1.197 DeviceManifestSchemaMajorVersion

[quickSpinIntegerNode](#) DeviceManifestSchemaMajorVersion

5.2.1.198 DeviceManifestSchemaMinorVersion

[quickSpinIntegerNode](#) DeviceManifestSchemaMinorVersion

5.2.1.199 DeviceManifestSecondaryURL

[quickSpinStringNode](#) DeviceManifestSecondaryURL

5.2.1.200 DeviceManifestXMLMajorVersion

[quickSpinIntegerNode](#) DeviceManifestXMLMajorVersion

5.2.1.201 DeviceManifestXMLMinorVersion

[quickSpinIntegerNode](#) DeviceManifestXMLMinorVersion

5.2.1.202 DeviceManifestXMLSubMinorVersion

[quickSpinIntegerNode](#) DeviceManifestXMLSubMinorVersion

5.2.1.203 DeviceManufacturerInfo

[quickSpinStringNode](#) DeviceManufacturerInfo

5.2.1.204 DeviceMaxThroughput

[quickSpinIntegerNode](#) DeviceMaxThroughput

5.2.1.205 DeviceModelName

[quickSpinStringNode](#) DeviceModelName

5.2.1.206 DevicePowerSupplySelector

[quickSpinEnumerationNode](#) DevicePowerSupplySelector

5.2.1.207 DeviceRegistersCheck

[quickSpinCommandNode](#) DeviceRegistersCheck

5.2.1.208 DeviceRegistersEndianness

[quickSpinEnumerationNode](#) DeviceRegistersEndianness

5.2.1.209 DeviceRegistersStreamingEnd

[quickSpinCommandNode](#) DeviceRegistersStreamingEnd

5.2.1.210 DeviceRegistersStreamingStart

[quickSpinCommandNode](#) DeviceRegistersStreamingStart

5.2.1.211 DeviceRegistersValid

[quickSpinBooleanNode](#) DeviceRegistersValid

5.2.1.212 DeviceReset

[quickSpinCommandNode](#) DeviceReset

5.2.1.213 DeviceScanType

[quickSpinEnumerationNode](#) DeviceScanType

5.2.1.214 DeviceSerialNumber

[quickSpinStringNode](#) DeviceSerialNumber

5.2.1.215 DeviceSerialPortBaudRate

[quickSpinEnumerationNode](#) DeviceSerialPortBaudRate

5.2.1.216 DeviceSerialPortSelector

[quickSpinEnumerationNode](#) DeviceSerialPortSelector

5.2.1.217 DeviceSFNCVersionMajor

[quickSpinIntegerNode](#) DeviceSFNCVersionMajor

5.2.1.218 DeviceSFNCVersionMinor

[quickSpinIntegerNode](#) DeviceSFNCVersionMinor

5.2.1.219 DeviceSFNCVersionSubMinor

[quickSpinIntegerNode](#) DeviceSFNCVersionSubMinor

5.2.1.220 DeviceStreamChannelCount

[quickSpinIntegerNode](#) DeviceStreamChannelCount

5.2.1.221 DeviceStreamChannelEndianness

[quickSpinEnumerationNode](#) DeviceStreamChannelEndianness

5.2.1.222 DeviceStreamChannelLink

[quickSpinIntegerNode](#) DeviceStreamChannelLink

5.2.1.223 DeviceStreamChannelPacketSize

[quickSpinIntegerNode](#) DeviceStreamChannelPacketSize

5.2.1.224 DeviceStreamChannelSelector

[quickSpinIntegerNode](#) DeviceStreamChannelSelector

5.2.1.225 DeviceStreamChannelType

[quickSpinEnumerationNode](#) DeviceStreamChannelType

5.2.1.226 DeviceTapGeometry

[quickSpinEnumerationNode](#) DeviceTapGeometry

5.2.1.227 DeviceTemperature

[quickSpinFloatNode](#) DeviceTemperature

5.2.1.228 DeviceTemperatureSelector

[quickSpinEnumerationNode](#) DeviceTemperatureSelector

5.2.1.229 DeviceTLType

[quickSpinEnumerationNode](#) DeviceTLType

5.2.1.230 DeviceTLVersionMajor

[quickSpinIntegerNode](#) DeviceTLVersionMajor

5.2.1.231 DeviceTLVersionMinor

[quickSpinIntegerNode](#) DeviceTLVersionMinor

5.2.1.232 DeviceTLVersionSubMinor

[quickSpinIntegerNode](#) DeviceTLVersionSubMinor

5.2.1.233 DeviceType

[quickSpinEnumerationNode](#) DeviceType

5.2.1.234 DeviceUptime

[quickSpinIntegerNode](#) DeviceUptime

5.2.1.235 DeviceUserID

[quickSpinStringNode](#) DeviceUserID

5.2.1.236 DeviceVendorName

[quickSpinStringNode](#) DeviceVendorName

5.2.1.237 DeviceVersion

[quickSpinStringNode](#) DeviceVersion

5.2.1.238 EncoderDivider

[quickSpinIntegerNode](#) EncoderDivider

5.2.1.239 EncoderMode

[quickSpinEnumerationNode](#) EncoderMode

5.2.1.240 EncoderOutputMode

[quickSpinEnumerationNode](#) EncoderOutputMode

5.2.1.241 EncoderReset

[quickSpinCommandNode](#) EncoderReset

5.2.1.242 EncoderResetActivation

[quickSpinEnumerationNode](#) EncoderResetActivation

5.2.1.243 EncoderResetSource

[quickSpinEnumerationNode](#) EncoderResetSource

5.2.1.244 EncoderSelector

[quickSpinEnumerationNode](#) EncoderSelector

5.2.1.245 EncoderSourceA

[quickSpinEnumerationNode](#) EncoderSourceA

5.2.1.246 EncoderSourceB

[quickSpinEnumerationNode](#) EncoderSourceB

5.2.1.247 EncoderStatus

[quickSpinEnumerationNode](#) EncoderStatus

5.2.1.248 EncoderTimeout

[quickSpinFloatNode](#) EncoderTimeout

5.2.1.249 EncoderValue

[quickSpinIntegerNode](#) EncoderValue

5.2.1.250 EncoderValueAtReset

[quickSpinIntegerNode](#) EncoderValueAtReset

5.2.1.251 EnumerationCount

[quickSpinIntegerNode](#) EnumerationCount

5.2.1.252 EventAcquisitionEnd

[quickSpinIntegerNode](#) EventAcquisitionEnd

5.2.1.253 EventAcquisitionEndFrameID

`quickSpinIntegerNode` EventAcquisitionEndFrameID

5.2.1.254 EventAcquisitionEndTimestamp

`quickSpinIntegerNode` EventAcquisitionEndTimestamp

5.2.1.255 EventAcquisitionError

`quickSpinIntegerNode` EventAcquisitionError

5.2.1.256 EventAcquisitionErrorFrameID

`quickSpinIntegerNode` EventAcquisitionErrorFrameID

5.2.1.257 EventAcquisitionErrorTimestamp

`quickSpinIntegerNode` EventAcquisitionErrorTimestamp

5.2.1.258 EventAcquisitionStart

`quickSpinIntegerNode` EventAcquisitionStart

5.2.1.259 EventAcquisitionStartFrameID

`quickSpinIntegerNode` EventAcquisitionStartFrameID

5.2.1.260 EventAcquisitionStartTimestamp

`quickSpinIntegerNode` EventAcquisitionStartTimestamp

5.2.1.261 EventAcquisitionTransferEnd

`quickSpinIntegerNode` EventAcquisitionTransferEnd

5.2.1.262 EventAcquisitionTransferEndFrameID

`quickSpinIntegerNode` EventAcquisitionTransferEndFrameID

5.2.1.263 EventAcquisitionTransferEndTimestamp

`quickSpinIntegerNode` EventAcquisitionTransferEndTimestamp

5.2.1.264 EventAcquisitionTransferStart

`quickSpinIntegerNode` EventAcquisitionTransferStart

5.2.1.265 EventAcquisitionTransferStartFrameID

`quickSpinIntegerNode` EventAcquisitionTransferStartFrameID

5.2.1.266 EventAcquisitionTransferStartTimestamp

`quickSpinIntegerNode` EventAcquisitionTransferStartTimestamp

5.2.1.267 EventAcquisitionTrigger

`quickSpinIntegerNode` EventAcquisitionTrigger

5.2.1.268 EventAcquisitionTriggerFrameID

`quickSpinIntegerNode` EventAcquisitionTriggerFrameID

5.2.1.269 EventAcquisitionTriggerTimestamp

[quickSpinIntegerNode](#) EventAcquisitionTriggerTimestamp

5.2.1.270 EventActionLate

[quickSpinIntegerNode](#) EventActionLate

5.2.1.271 EventActionLateFrameID

[quickSpinIntegerNode](#) EventActionLateFrameID

5.2.1.272 EventActionLateTimestamp

[quickSpinIntegerNode](#) EventActionLateTimestamp

5.2.1.273 EventCounter0End

[quickSpinIntegerNode](#) EventCounter0End

5.2.1.274 EventCounter0EndFrameID

[quickSpinIntegerNode](#) EventCounter0EndFrameID

5.2.1.275 EventCounter0EndTimestamp

[quickSpinIntegerNode](#) EventCounter0EndTimestamp

5.2.1.276 EventCounter0Start

[quickSpinIntegerNode](#) EventCounter0Start

5.2.1.277 EventCounter0StartFrameID

[quickSpinIntegerNode](#) EventCounter0StartFrameID

5.2.1.278 EventCounter0StartTimestamp

[quickSpinIntegerNode](#) EventCounter0StartTimestamp

5.2.1.279 EventCounter1End

[quickSpinIntegerNode](#) EventCounter1End

5.2.1.280 EventCounter1EndFrameID

[quickSpinIntegerNode](#) EventCounter1EndFrameID

5.2.1.281 EventCounter1EndTimestamp

[quickSpinIntegerNode](#) EventCounter1EndTimestamp

5.2.1.282 EventCounter1Start

[quickSpinIntegerNode](#) EventCounter1Start

5.2.1.283 EventCounter1StartFrameID

[quickSpinIntegerNode](#) EventCounter1StartFrameID

5.2.1.284 EventCounter1StartTimestamp

[quickSpinIntegerNode](#) EventCounter1StartTimestamp

5.2.1.285 EventEncoder0Restarted

[quickSpinIntegerNode](#) EventEncoder0Restarted

5.2.1.286 EventEncoder0RestartedFrameID

[quickSpinIntegerNode](#) EventEncoder0RestartedFrameID

5.2.1.287 EventEncoder0RestartedTimestamp

[quickSpinIntegerNode](#) EventEncoder0RestartedTimestamp

5.2.1.288 EventEncoder0Stopped

[quickSpinIntegerNode](#) EventEncoder0Stopped

5.2.1.289 EventEncoder0StoppedFrameID

[quickSpinIntegerNode](#) EventEncoder0StoppedFrameID

5.2.1.290 EventEncoder0StoppedTimestamp

[quickSpinIntegerNode](#) EventEncoder0StoppedTimestamp

5.2.1.291 EventEncoder1Restarted

[quickSpinIntegerNode](#) EventEncoder1Restarted

5.2.1.292 EventEncoder1RestartedFrameID

[quickSpinIntegerNode](#) EventEncoder1RestartedFrameID

5.2.1.293 EventEncoder1RestartedTimestamp

[quickSpinIntegerNode](#) EventEncoder1RestartedTimestamp

5.2.1.294 EventEncoder1Stopped

[quickSpinIntegerNode](#) EventEncoder1Stopped

5.2.1.295 EventEncoder1StoppedFrameID

[quickSpinIntegerNode](#) EventEncoder1StoppedFrameID

5.2.1.296 EventEncoder1StoppedTimestamp

[quickSpinIntegerNode](#) EventEncoder1StoppedTimestamp

5.2.1.297 EventError

[quickSpinIntegerNode](#) EventError

5.2.1.298 EventErrorCode

[quickSpinIntegerNode](#) EventErrorCode

5.2.1.299 EventErrorFrameID

[quickSpinIntegerNode](#) EventErrorFrameID

5.2.1.300 EventErrorTimestamp

[quickSpinIntegerNode](#) EventErrorTimestamp

5.2.1.301 EventExposureEnd

[quickSpinIntegerNode](#) EventExposureEnd

5.2.1.302 EventExposureEndFrameID

[quickSpinIntegerNode](#) EventExposureEndFrameID

5.2.1.303 EventExposureEndTimestamp

[quickSpinIntegerNode](#) EventExposureEndTimestamp

5.2.1.304 EventExposureStart

[quickSpinIntegerNode](#) EventExposureStart

5.2.1.305 EventExposureStartFrameID

[quickSpinIntegerNode](#) EventExposureStartFrameID

5.2.1.306 EventExposureStartTimestamp

[quickSpinIntegerNode](#) EventExposureStartTimestamp

5.2.1.307 EventFrameBurstEnd

[quickSpinIntegerNode](#) EventFrameBurstEnd

5.2.1.308 EventFrameBurstEndFrameID

[quickSpinIntegerNode](#) EventFrameBurstEndFrameID

5.2.1.309 EventFrameBurstEndTimestamp

[quickSpinIntegerNode](#) EventFrameBurstEndTimestamp

5.2.1.310 EventFrameBurstStart

[quickSpinIntegerNode](#) EventFrameBurstStart

5.2.1.311 EventFrameBurstStartFrameID

[quickSpinIntegerNode](#) EventFrameBurstStartFrameID

5.2.1.312 EventFrameBurstStartTimestamp

[quickSpinIntegerNode](#) EventFrameBurstStartTimestamp

5.2.1.313 EventFrameEnd

[quickSpinIntegerNode](#) EventFrameEnd

5.2.1.314 EventFrameEndFrameID

[quickSpinIntegerNode](#) EventFrameEndFrameID

5.2.1.315 EventFrameEndTimestamp

[quickSpinIntegerNode](#) EventFrameEndTimestamp

5.2.1.316 EventFrameStart

[quickSpinIntegerNode](#) EventFrameStart

5.2.1.317 EventFrameStartFrameID

`quickSpinIntegerNode` EventFrameStartFrameID

5.2.1.318 EventFrameStartTimestamp

`quickSpinIntegerNode` EventFrameStartTimestamp

5.2.1.319 EventFrameTransferEnd

`quickSpinIntegerNode` EventFrameTransferEnd

5.2.1.320 EventFrameTransferEndFrameID

`quickSpinIntegerNode` EventFrameTransferEndFrameID

5.2.1.321 EventFrameTransferEndTimestamp

`quickSpinIntegerNode` EventFrameTransferEndTimestamp

5.2.1.322 EventFrameTransferStart

`quickSpinIntegerNode` EventFrameTransferStart

5.2.1.323 EventFrameTransferStartFrameID

`quickSpinIntegerNode` EventFrameTransferStartFrameID

5.2.1.324 EventFrameTransferStartTimestamp

`quickSpinIntegerNode` EventFrameTransferStartTimestamp

5.2.1.325 EventFrameTrigger

[quickSpinIntegerNode](#) EventFrameTrigger

5.2.1.326 EventFrameTriggerFrameID

[quickSpinIntegerNode](#) EventFrameTriggerFrameID

5.2.1.327 EventFrameTriggerTimestamp

[quickSpinIntegerNode](#) EventFrameTriggerTimestamp

5.2.1.328 EventLine0AnyEdge

[quickSpinIntegerNode](#) EventLine0AnyEdge

5.2.1.329 EventLine0AnyEdgeFrameID

[quickSpinIntegerNode](#) EventLine0AnyEdgeFrameID

5.2.1.330 EventLine0AnyEdgeTimestamp

[quickSpinIntegerNode](#) EventLine0AnyEdgeTimestamp

5.2.1.331 EventLine0FallingEdge

[quickSpinIntegerNode](#) EventLine0FallingEdge

5.2.1.332 EventLine0FallingEdgeFrameID

[quickSpinIntegerNode](#) EventLine0FallingEdgeFrameID

5.2.1.333 EventLine0FallingEdgeTimestamp

`quickSpinIntegerNode` EventLine0FallingEdgeTimestamp

5.2.1.334 EventLine0RisingEdge

`quickSpinIntegerNode` EventLine0RisingEdge

5.2.1.335 EventLine0RisingEdgeFrameID

`quickSpinIntegerNode` EventLine0RisingEdgeFrameID

5.2.1.336 EventLine0RisingEdgeTimestamp

`quickSpinIntegerNode` EventLine0RisingEdgeTimestamp

5.2.1.337 EventLine1AnyEdge

`quickSpinIntegerNode` EventLine1AnyEdge

5.2.1.338 EventLine1AnyEdgeFrameID

`quickSpinIntegerNode` EventLine1AnyEdgeFrameID

5.2.1.339 EventLine1AnyEdgeTimestamp

`quickSpinIntegerNode` EventLine1AnyEdgeTimestamp

5.2.1.340 EventLine1FallingEdge

`quickSpinIntegerNode` EventLine1FallingEdge

5.2.1.341 EventLine1FallingEdgeFrameID

`quickSpinIntegerNode` EventLine1FallingEdgeFrameID

5.2.1.342 EventLine1FallingEdgeTimestamp

`quickSpinIntegerNode` EventLine1FallingEdgeTimestamp

5.2.1.343 EventLine1RisingEdge

`quickSpinIntegerNode` EventLine1RisingEdge

5.2.1.344 EventLine1RisingEdgeFrameID

`quickSpinIntegerNode` EventLine1RisingEdgeFrameID

5.2.1.345 EventLine1RisingEdgeTimestamp

`quickSpinIntegerNode` EventLine1RisingEdgeTimestamp

5.2.1.346 EventLinkSpeedChange

`quickSpinIntegerNode` EventLinkSpeedChange

5.2.1.347 EventLinkSpeedChangeFrameID

`quickSpinIntegerNode` EventLinkSpeedChangeFrameID

5.2.1.348 EventLinkSpeedChangeTimestamp

`quickSpinIntegerNode` EventLinkSpeedChangeTimestamp

5.2.1.349 EventLinkTrigger0

[quickSpinIntegerNode](#) EventLinkTrigger0

5.2.1.350 EventLinkTrigger0FrameID

[quickSpinIntegerNode](#) EventLinkTrigger0FrameID

5.2.1.351 EventLinkTrigger0Timestamp

[quickSpinIntegerNode](#) EventLinkTrigger0Timestamp

5.2.1.352 EventLinkTrigger1

[quickSpinIntegerNode](#) EventLinkTrigger1

5.2.1.353 EventLinkTrigger1FrameID

[quickSpinIntegerNode](#) EventLinkTrigger1FrameID

5.2.1.354 EventLinkTrigger1Timestamp

[quickSpinIntegerNode](#) EventLinkTrigger1Timestamp

5.2.1.355 EventNotification

[quickSpinEnumerationNode](#) EventNotification

5.2.1.356 EventSelector

[quickSpinEnumerationNode](#) EventSelector

5.2.1.357 EventSequencerSetChange

[quickSpinIntegerNode](#) EventSequencerSetChange

5.2.1.358 EventSequencerSetChangeFrameID

[quickSpinIntegerNode](#) EventSequencerSetChangeFrameID

5.2.1.359 EventSequencerSetChangeTimestamp

[quickSpinIntegerNode](#) EventSequencerSetChangeTimestamp

5.2.1.360 EventSerialData

[quickSpinStringNode](#) EventSerialData

5.2.1.361 EventSerialDataLength

[quickSpinIntegerNode](#) EventSerialDataLength

5.2.1.362 EventSerialPortReceive

[quickSpinIntegerNode](#) EventSerialPortReceive

5.2.1.363 EventSerialPortReceiveTimestamp

[quickSpinIntegerNode](#) EventSerialPortReceiveTimestamp

5.2.1.364 EventSerialReceiveOverflow

[quickSpinBooleanNode](#) EventSerialReceiveOverflow

5.2.1.365 EventStream0TransferBlockEnd

[quickSpinIntegerNode](#) EventStream0TransferBlockEnd

5.2.1.366 EventStream0TransferBlockEndFrameID

[quickSpinIntegerNode](#) EventStream0TransferBlockEndFrameID

5.2.1.367 EventStream0TransferBlockEndTimestamp

[quickSpinIntegerNode](#) EventStream0TransferBlockEndTimestamp

5.2.1.368 EventStream0TransferBlockStart

[quickSpinIntegerNode](#) EventStream0TransferBlockStart

5.2.1.369 EventStream0TransferBlockStartFrameID

[quickSpinIntegerNode](#) EventStream0TransferBlockStartFrameID

5.2.1.370 EventStream0TransferBlockStartTimestamp

[quickSpinIntegerNode](#) EventStream0TransferBlockStartTimestamp

5.2.1.371 EventStream0TransferBlockTrigger

[quickSpinIntegerNode](#) EventStream0TransferBlockTrigger

5.2.1.372 EventStream0TransferBlockTriggerFrameID

[quickSpinIntegerNode](#) EventStream0TransferBlockTriggerFrameID

5.2.1.373 EventStream0TransferBlockTriggerTimestamp

`quickSpinIntegerNode` EventStream0TransferBlockTriggerTimestamp

5.2.1.374 EventStream0TransferBurstEnd

`quickSpinIntegerNode` EventStream0TransferBurstEnd

5.2.1.375 EventStream0TransferBurstEndFrameID

`quickSpinIntegerNode` EventStream0TransferBurstEndFrameID

5.2.1.376 EventStream0TransferBurstEndTimestamp

`quickSpinIntegerNode` EventStream0TransferBurstEndTimestamp

5.2.1.377 EventStream0TransferBurstStart

`quickSpinIntegerNode` EventStream0TransferBurstStart

5.2.1.378 EventStream0TransferBurstStartFrameID

`quickSpinIntegerNode` EventStream0TransferBurstStartFrameID

5.2.1.379 EventStream0TransferBurstStartTimestamp

`quickSpinIntegerNode` EventStream0TransferBurstStartTimestamp

5.2.1.380 EventStream0TransferEnd

`quickSpinIntegerNode` EventStream0TransferEnd

5.2.1.381 EventStream0TransferEndFrameID

`quickSpinIntegerNode` EventStream0TransferEndFrameID

5.2.1.382 EventStream0TransferEndTimestamp

`quickSpinIntegerNode` EventStream0TransferEndTimestamp

5.2.1.383 EventStream0TransferOverflow

`quickSpinIntegerNode` EventStream0TransferOverflow

5.2.1.384 EventStream0TransferOverflowFrameID

`quickSpinIntegerNode` EventStream0TransferOverflowFrameID

5.2.1.385 EventStream0TransferOverflowTimestamp

`quickSpinIntegerNode` EventStream0TransferOverflowTimestamp

5.2.1.386 EventStream0TransferPause

`quickSpinIntegerNode` EventStream0TransferPause

5.2.1.387 EventStream0TransferPauseFrameID

`quickSpinIntegerNode` EventStream0TransferPauseFrameID

5.2.1.388 EventStream0TransferPauseTimestamp

`quickSpinIntegerNode` EventStream0TransferPauseTimestamp

5.2.1.389 EventStream0TransferResume

[quickSpinIntegerNode](#) EventStream0TransferResume

5.2.1.390 EventStream0TransferResumeFrameID

[quickSpinIntegerNode](#) EventStream0TransferResumeFrameID

5.2.1.391 EventStream0TransferResumeTimestamp

[quickSpinIntegerNode](#) EventStream0TransferResumeTimestamp

5.2.1.392 EventStream0TransferStart

[quickSpinIntegerNode](#) EventStream0TransferStart

5.2.1.393 EventStream0TransferStartFrameID

[quickSpinIntegerNode](#) EventStream0TransferStartFrameID

5.2.1.394 EventStream0TransferStartTimestamp

[quickSpinIntegerNode](#) EventStream0TransferStartTimestamp

5.2.1.395 EventTest

[quickSpinIntegerNode](#) EventTest

5.2.1.396 EventTestTimestamp

[quickSpinIntegerNode](#) EventTestTimestamp

5.2.1.397 EventTimer0End

[quickSpinIntegerNode](#) EventTimer0End

5.2.1.398 EventTimer0EndFrameID

[quickSpinIntegerNode](#) EventTimer0EndFrameID

5.2.1.399 EventTimer0EndTimestamp

[quickSpinIntegerNode](#) EventTimer0EndTimestamp

5.2.1.400 EventTimer0Start

[quickSpinIntegerNode](#) EventTimer0Start

5.2.1.401 EventTimer0StartFrameID

[quickSpinIntegerNode](#) EventTimer0StartFrameID

5.2.1.402 EventTimer0StartTimestamp

[quickSpinIntegerNode](#) EventTimer0StartTimestamp

5.2.1.403 EventTimer1End

[quickSpinIntegerNode](#) EventTimer1End

5.2.1.404 EventTimer1EndFrameID

[quickSpinIntegerNode](#) EventTimer1EndFrameID

5.2.1.405 EventTimer1EndTimestamp

[quickSpinIntegerNode](#) EventTimer1EndTimestamp

5.2.1.406 EventTimer1Start

[quickSpinIntegerNode](#) EventTimer1Start

5.2.1.407 EventTimer1StartFrameID

[quickSpinIntegerNode](#) EventTimer1StartFrameID

5.2.1.408 EventTimer1StartTimestamp

[quickSpinIntegerNode](#) EventTimer1StartTimestamp

5.2.1.409 ExposureActiveMode

[quickSpinEnumerationNode](#) ExposureActiveMode

5.2.1.410 ExposureAuto

[quickSpinEnumerationNode](#) ExposureAuto

5.2.1.411 ExposureMode

[quickSpinEnumerationNode](#) ExposureMode

5.2.1.412 ExposureTime

[quickSpinFloatNode](#) ExposureTime

5.2.1.413 ExposureTimeMode

[quickSpinEnumerationNode](#) ExposureTimeMode

5.2.1.414 ExposureTimeSelector

[quickSpinEnumerationNode](#) ExposureTimeSelector

5.2.1.415 FactoryReset

[quickSpinCommandNode](#) FactoryReset

5.2.1.416 FileAccessBuffer

[quickSpinRegisterNode](#) FileAccessBuffer

5.2.1.417 FileAccessLength

[quickSpinIntegerNode](#) FileAccessLength

5.2.1.418 FileAccessOffset

[quickSpinIntegerNode](#) FileAccessOffset

5.2.1.419 FileOpenMode

[quickSpinEnumerationNode](#) FileOpenMode

5.2.1.420 FileOperationExecute

[quickSpinCommandNode](#) FileOperationExecute

5.2.1.421 FileOperationResult

`quickSpinIntegerNode` FileOperationResult

5.2.1.422 FileOperationSelector

`quickSpinEnumerationNode` FileOperationSelector

5.2.1.423 FileOperationStatus

`quickSpinEnumerationNode` FileOperationStatus

5.2.1.424 FileSelector

`quickSpinEnumerationNode` FileSelector

5.2.1.425 FileSize

`quickSpinIntegerNode` FileSize

5.2.1.426 Gain

`quickSpinFloatNode` Gain

5.2.1.427 GainAuto

`quickSpinEnumerationNode` GainAuto

5.2.1.428 GainAutoBalance

`quickSpinEnumerationNode` GainAutoBalance

5.2.1.429 GainSelector

[quickSpinEnumerationNode](#) GainSelector

5.2.1.430 Gamma

[quickSpinFloatNode](#) Gamma

5.2.1.431 GammaEnable

[quickSpinBooleanNode](#) GammaEnable

5.2.1.432 GevActiveLinkCount

[quickSpinIntegerNode](#) GevActiveLinkCount

5.2.1.433 GevCCP

[quickSpinEnumerationNode](#) GevCCP

5.2.1.434 GevCurrentDefaultGateway

[quickSpinIntegerNode](#) GevCurrentDefaultGateway

5.2.1.435 GevCurrentIPAddress

[quickSpinIntegerNode](#) GevCurrentIPAddress

5.2.1.436 GevCurrentIPConfigurationDHCP

[quickSpinBooleanNode](#) GevCurrentIPConfigurationDHCP

5.2.1.437 GevCurrentIPConfigurationLLA

`quickSpinBooleanNode` `GevCurrentIPConfigurationLLA`

5.2.1.438 GevCurrentIPConfigurationPersistentIP

`quickSpinBooleanNode` `GevCurrentIPConfigurationPersistentIP`

5.2.1.439 GevCurrentPhysicalLinkConfiguration

`quickSpinEnumerationNode` `GevCurrentPhysicalLinkConfiguration`

5.2.1.440 GevCurrentSubnetMask

`quickSpinIntegerNode` `GevCurrentSubnetMask`

5.2.1.441 GevDiscoveryAckDelay

`quickSpinIntegerNode` `GevDiscoveryAckDelay`

5.2.1.442 GevFirstURL

`quickSpinStringNode` `GevFirstURL`

5.2.1.443 GevGVCPEExtendedStatusCodes

`quickSpinBooleanNode` `GevGVCPEExtendedStatusCodes`

5.2.1.444 GevGVCPEExtendedStatusCodesSelector

`quickSpinEnumerationNode` `GevGVCPEExtendedStatusCodesSelector`

5.2.1.445 GevGVCPHeartbeatDisable

[quickSpinBooleanNode](#) GevGVCPHeartbeatDisable

5.2.1.446 GevGVCPPendingAck

[quickSpinBooleanNode](#) GevGVCPPendingAck

5.2.1.447 GevGVCPPendingTimeout

[quickSpinIntegerNode](#) GevGVCPPendingTimeout

5.2.1.448 GevGVSPExtendedIDMode

[quickSpinEnumerationNode](#) GevGVSPExtendedIDMode

5.2.1.449 GevHeartbeatTimeout

[quickSpinIntegerNode](#) GevHeartbeatTimeout

5.2.1.450 GevIEEE1588

[quickSpinBooleanNode](#) GevIEEE1588

5.2.1.451 GevIEEE1588ClockAccuracy

[quickSpinEnumerationNode](#) GevIEEE1588ClockAccuracy

5.2.1.452 GevIEEE1588Mode

[quickSpinEnumerationNode](#) GevIEEE1588Mode

5.2.1.453 GevIEEE1588Status

[quickSpinEnumerationNode](#) [GevIEEE1588Status](#)

5.2.1.454 GevInterfaceSelector

[quickSpinIntegerNode](#) [GevInterfaceSelector](#)

5.2.1.455 GevIPConfigurationStatus

[quickSpinEnumerationNode](#) [GevIPConfigurationStatus](#)

5.2.1.456 GevMACAddress

[quickSpinIntegerNode](#) [GevMACAddress](#)

5.2.1.457 GevMCDA

[quickSpinIntegerNode](#) [GevMCDA](#)

5.2.1.458 GevMCPHostPort

[quickSpinIntegerNode](#) [GevMCPHostPort](#)

5.2.1.459 GevMCRC

[quickSpinIntegerNode](#) [GevMCRC](#)

5.2.1.460 GevMCSP

[quickSpinIntegerNode](#) [GevMCSP](#)

5.2.1.461 GevMCTT

[quickSpinIntegerNode](#) GevMCTT

5.2.1.462 GevNumberOfInterfaces

[quickSpinIntegerNode](#) GevNumberOfInterfaces

5.2.1.463 GevPAUSEFrameReception

[quickSpinBooleanNode](#) GevPAUSEFrameReception

5.2.1.464 GevPAUSEFrameTransmission

[quickSpinBooleanNode](#) GevPAUSEFrameTransmission

5.2.1.465 GevPersistentDefaultGateway

[quickSpinIntegerNode](#) GevPersistentDefaultGateway

5.2.1.466 GevPersistentIPAddress

[quickSpinIntegerNode](#) GevPersistentIPAddress

5.2.1.467 GevPersistentSubnetMask

[quickSpinIntegerNode](#) GevPersistentSubnetMask

5.2.1.468 GevPhysicalLinkConfiguration

[quickSpinEnumerationNode](#) GevPhysicalLinkConfiguration

5.2.1.469 GevPrimaryApplicationIPAddress

[quickSpinIntegerNode](#) GevPrimaryApplicationIPAddress

5.2.1.470 GevPrimaryApplicationSocket

[quickSpinIntegerNode](#) GevPrimaryApplicationSocket

5.2.1.471 GevPrimaryApplicationSwitchoverKey

[quickSpinIntegerNode](#) GevPrimaryApplicationSwitchoverKey

5.2.1.472 GevSCCFGAllInTransmission

[quickSpinBooleanNode](#) GevSCCFGAllInTransmission

5.2.1.473 GevSCCFGExtendedChunkData

[quickSpinBooleanNode](#) GevSCCFGExtendedChunkData

5.2.1.474 GevSCCFGPacketResendDestination

[quickSpinBooleanNode](#) GevSCCFGPacketResendDestination

5.2.1.475 GevSCCFGUnconditionalStreaming

[quickSpinBooleanNode](#) GevSCCFGUnconditionalStreaming

5.2.1.476 GevSCDA

[quickSpinIntegerNode](#) GevSCDA

5.2.1.477 GevSCPD

[quickSpinIntegerNode](#) GevSCPD

5.2.1.478 GevSCPDirection

[quickSpinIntegerNode](#) GevSCPDirection

5.2.1.479 GevSCPHostPort

[quickSpinIntegerNode](#) GevSCPHostPort

5.2.1.480 GevSCPInterfaceIndex

[quickSpinIntegerNode](#) GevSCPInterfaceIndex

5.2.1.481 GevSCPSBigEndian

[quickSpinBooleanNode](#) GevSCPSBigEndian

5.2.1.482 GevSCPSDoNotFragment

[quickSpinBooleanNode](#) GevSCPSDoNotFragment

5.2.1.483 GevSCPSFireTestPacket

[quickSpinBooleanNode](#) GevSCPSFireTestPacket

5.2.1.484 GevSCPSPacketSize

[quickSpinIntegerNode](#) GevSCPSPacketSize

5.2.1.485 GevSCSP

[quickSpinIntegerNode](#) GevSCSP

5.2.1.486 GevSCZoneConfigurationLock

[quickSpinBooleanNode](#) GevSCZoneConfigurationLock

5.2.1.487 GevSCZoneCount

[quickSpinIntegerNode](#) GevSCZoneCount

5.2.1.488 GevSCZoneDirectionAll

[quickSpinIntegerNode](#) GevSCZoneDirectionAll

5.2.1.489 GevSecondURL

[quickSpinStringNode](#) GevSecondURL

5.2.1.490 GevStreamChannelSelector

[quickSpinIntegerNode](#) GevStreamChannelSelector

5.2.1.491 GevSupportedOption

[quickSpinBooleanNode](#) GevSupportedOption

5.2.1.492 GevSupportedOptionSelector

[quickSpinEnumerationNode](#) GevSupportedOptionSelector

5.2.1.493 GevTimestampTickFrequency

[quickSpinIntegerNode](#) GevTimestampTickFrequency

5.2.1.494 GuiXmlManifestAddress

[quickSpinIntegerNode](#) GuiXmlManifestAddress

5.2.1.495 Height

[quickSpinIntegerNode](#) Height

5.2.1.496 HeightMax

[quickSpinIntegerNode](#) HeightMax

5.2.1.497 ImageComponentEnable

[quickSpinBooleanNode](#) ImageComponentEnable

5.2.1.498 ImageComponentSelector

[quickSpinEnumerationNode](#) ImageComponentSelector

5.2.1.499 ImageCompressionBitrate

[quickSpinFloatNode](#) ImageCompressionBitrate

5.2.1.500 ImageCompressionJPEGFormatOption

[quickSpinEnumerationNode](#) ImageCompressionJPEGFormatOption

5.2.1.501 ImageCompressionMode

[quickSpinEnumerationNode](#) ImageCompressionMode

5.2.1.502 ImageCompressionQuality

[quickSpinIntegerNode](#) ImageCompressionQuality

5.2.1.503 ImageCompressionRateOption

[quickSpinEnumerationNode](#) ImageCompressionRateOption

5.2.1.504 IspEnable

[quickSpinBooleanNode](#) IspEnable

5.2.1.505 LineFilterWidth

[quickSpinFloatNode](#) LineFilterWidth

5.2.1.506 LineFormat

[quickSpinEnumerationNode](#) LineFormat

5.2.1.507 LineInputFilterSelector

[quickSpinEnumerationNode](#) LineInputFilterSelector

5.2.1.508 LineInverter

[quickSpinBooleanNode](#) LineInverter

5.2.1.509 LineMode

[quickSpinEnumerationNode](#) LineMode

5.2.1.510 LinePitch

[quickSpinIntegerNode](#) LinePitch

5.2.1.511 LineSelector

[quickSpinEnumerationNode](#) LineSelector

5.2.1.512 LineSource

[quickSpinEnumerationNode](#) LineSource

5.2.1.513 LineStatus

[quickSpinBooleanNode](#) LineStatus

5.2.1.514 LineStatusAll

[quickSpinIntegerNode](#) LineStatusAll

5.2.1.515 LinkErrorCount

[quickSpinIntegerNode](#) LinkErrorCount

5.2.1.516 LinkUptime

[quickSpinIntegerNode](#) LinkUptime

5.2.1.517 LogicBlockLUTInputActivation

[quickSpinEnumerationNode](#) LogicBlockLUTInputActivation

5.2.1.518 LogicBlockLUTInputSelector

[quickSpinEnumerationNode](#) LogicBlockLUTInputSelector

5.2.1.519 LogicBlockLUTInputSource

[quickSpinEnumerationNode](#) LogicBlockLUTInputSource

5.2.1.520 LogicBlockLUTOutputValue

[quickSpinBooleanNode](#) LogicBlockLUTOutputValue

5.2.1.521 LogicBlockLUTOutputValueAll

[quickSpinIntegerNode](#) LogicBlockLUTOutputValueAll

5.2.1.522 LogicBlockLUTRowIndex

[quickSpinIntegerNode](#) LogicBlockLUTRowIndex

5.2.1.523 LogicBlockLUTSelector

[quickSpinEnumerationNode](#) LogicBlockLUTSelector

5.2.1.524 LogicBlockSelector

[quickSpinEnumerationNode](#) LogicBlockSelector

5.2.1.525 LUTEnable

[quickSpinBooleanNode](#) LUTEnable

5.2.1.526 LUTIndex

[quickSpinIntegerNode](#) LUTIndex

5.2.1.527 LUTSelector

[quickSpinEnumerationNode](#) LUTSelector

5.2.1.528 LUTValue

[quickSpinIntegerNode](#) LUTValue

5.2.1.529 LUTValueAll

[quickSpinRegisterNode](#) LUTValueAll

5.2.1.530 MaxDeviceResetTime

[quickSpinIntegerNode](#) MaxDeviceResetTime

5.2.1.531 OffsetX

[quickSpinIntegerNode](#) OffsetX

5.2.1.532 OffsetY

[quickSpinIntegerNode](#) OffsetY

5.2.1.533 PacketResendRequestCount

[quickSpinIntegerNode](#) PacketResendRequestCount

5.2.1.534 PayloadSize

[quickSpinIntegerNode](#) PayloadSize

5.2.1.535 PixelColorFilter

[quickSpinEnumerationNode](#) PixelColorFilter

5.2.1.536 PixelDynamicRangeMax

[quickSpinIntegerNode](#) PixelDynamicRangeMax

5.2.1.537 PixelDynamicRangeMin

[quickSpinIntegerNode](#) PixelDynamicRangeMin

5.2.1.538 PixelFormat

[quickSpinEnumerationNode](#) PixelFormat

5.2.1.539 PixelFormatInfoID

[quickSpinIntegerNode](#) PixelFormatInfoID

5.2.1.540 PixelFormatInfoSelector

[quickSpinEnumerationNode](#) PixelFormatInfoSelector

5.2.1.541 PixelSize

[quickSpinEnumerationNode](#) PixelSize

5.2.1.542 PowerSupplyCurrent

[quickSpinFloatNode](#) PowerSupplyCurrent

5.2.1.543 PowerSupplyVoltage

[quickSpinFloatNode](#) PowerSupplyVoltage

5.2.1.544 RegionDestination

[quickSpinEnumerationNode](#) RegionDestination

5.2.1.545 RegionMode

[quickSpinEnumerationNode](#) RegionMode

5.2.1.546 RegionSelector

[quickSpinEnumerationNode](#) RegionSelector

5.2.1.547 ReverseX

[quickSpinBooleanNode](#) ReverseX

5.2.1.548 ReverseY

[quickSpinBooleanNode](#) ReverseY

5.2.1.549 RgbTransformLightSource

`quickSpinEnumerationNode` RgbTransformLightSource

5.2.1.550 Saturation

`quickSpinFloatNode` Saturation

5.2.1.551 SaturationEnable

`quickSpinBooleanNode` SaturationEnable

5.2.1.552 Scan3dAxisMax

`quickSpinFloatNode` Scan3dAxisMax

5.2.1.553 Scan3dAxisMin

`quickSpinFloatNode` Scan3dAxisMin

5.2.1.554 Scan3dCoordinateOffset

`quickSpinFloatNode` Scan3dCoordinateOffset

5.2.1.555 Scan3dCoordinateReferenceSelector

`quickSpinEnumerationNode` Scan3dCoordinateReferenceSelector

5.2.1.556 Scan3dCoordinateReferenceValue

`quickSpinFloatNode` Scan3dCoordinateReferenceValue

5.2.1.557 Scan3dCoordinateScale

`quickSpinFloatNode` Scan3dCoordinateScale

5.2.1.558 Scan3dCoordinateSelector

`quickSpinEnumerationNode` Scan3dCoordinateSelector

5.2.1.559 Scan3dCoordinateSystem

`quickSpinEnumerationNode` Scan3dCoordinateSystem

5.2.1.560 Scan3dCoordinateSystemReference

`quickSpinEnumerationNode` Scan3dCoordinateSystemReference

5.2.1.561 Scan3dCoordinateTransformSelector

`quickSpinEnumerationNode` Scan3dCoordinateTransformSelector

5.2.1.562 Scan3dDistanceUnit

`quickSpinEnumerationNode` Scan3dDistanceUnit

5.2.1.563 Scan3dInvalidDataFlag

`quickSpinBooleanNode` Scan3dInvalidDataFlag

5.2.1.564 Scan3dInvalidDataValue

`quickSpinFloatNode` Scan3dInvalidDataValue

5.2.1.565 Scan3dOutputMode

[quickSpinEnumerationNode](#) Scan3dOutputMode

5.2.1.566 Scan3dTransformValue

[quickSpinFloatNode](#) Scan3dTransformValue

5.2.1.567 SensorDescription

[quickSpinStringNode](#) SensorDescription

5.2.1.568 SensorDigitizationTaps

[quickSpinEnumerationNode](#) SensorDigitizationTaps

5.2.1.569 SensorHeight

[quickSpinIntegerNode](#) SensorHeight

5.2.1.570 SensorShutterMode

[quickSpinEnumerationNode](#) SensorShutterMode

5.2.1.571 SensorTaps

[quickSpinEnumerationNode](#) SensorTaps

5.2.1.572 SensorWidth

[quickSpinIntegerNode](#) SensorWidth

5.2.1.573 SequencerConfigurationMode

[quickSpinEnumerationNode](#) SequencerConfigurationMode

5.2.1.574 SequencerConfigurationValid

[quickSpinEnumerationNode](#) SequencerConfigurationValid

5.2.1.575 SequencerFeatureEnable

[quickSpinBooleanNode](#) SequencerFeatureEnable

5.2.1.576 SequencerMode

[quickSpinEnumerationNode](#) SequencerMode

5.2.1.577 SequencerPathSelector

[quickSpinIntegerNode](#) SequencerPathSelector

5.2.1.578 SequencerSetActive

[quickSpinIntegerNode](#) SequencerSetActive

5.2.1.579 SequencerSetLoad

[quickSpinCommandNode](#) SequencerSetLoad

5.2.1.580 SequencerSetNext

[quickSpinIntegerNode](#) SequencerSetNext

5.2.1.581 SequencerSetSave

[quickSpinCommandNode](#) SequencerSetSave

5.2.1.582 SequencerSetSelector

[quickSpinIntegerNode](#) SequencerSetSelector

5.2.1.583 SequencerSetStart

[quickSpinIntegerNode](#) SequencerSetStart

5.2.1.584 SequencerSetValid

[quickSpinEnumerationNode](#) SequencerSetValid

5.2.1.585 SequencerTriggerActivation

[quickSpinEnumerationNode](#) SequencerTriggerActivation

5.2.1.586 SequencerTriggerSource

[quickSpinEnumerationNode](#) SequencerTriggerSource

5.2.1.587 SerialPortBaudRate

[quickSpinEnumerationNode](#) SerialPortBaudRate

5.2.1.588 SerialPortDataBits

[quickSpinIntegerNode](#) SerialPortDataBits

5.2.1.589 SerialPortParity

[quickSpinEnumerationNode](#) SerialPortParity

5.2.1.590 SerialPortSelector

[quickSpinEnumerationNode](#) SerialPortSelector

5.2.1.591 SerialPortSource

[quickSpinEnumerationNode](#) SerialPortSource

5.2.1.592 SerialPortStopBits

[quickSpinEnumerationNode](#) SerialPortStopBits

5.2.1.593 SerialReceiveFramingErrorCount

[quickSpinIntegerNode](#) SerialReceiveFramingErrorCount

5.2.1.594 SerialReceiveParityErrorCount

[quickSpinIntegerNode](#) SerialReceiveParityErrorCount

5.2.1.595 SerialReceiveQueueClear

[quickSpinCommandNode](#) SerialReceiveQueueClear

5.2.1.596 SerialReceiveQueueCurrentCharacterCount

[quickSpinIntegerNode](#) SerialReceiveQueueCurrentCharacterCount

5.2.1.597 SerialReceiveQueueMaxCharacterCount

`quickSpinIntegerNode` SerialReceiveQueueMaxCharacterCount

5.2.1.598 SerialTransmitQueueCurrentCharacterCount

`quickSpinIntegerNode` SerialTransmitQueueCurrentCharacterCount

5.2.1.599 SerialTransmitQueueMaxCharacterCount

`quickSpinIntegerNode` SerialTransmitQueueMaxCharacterCount

5.2.1.600 Sharpening

`quickSpinFloatNode` Sharpening

5.2.1.601 SharpeningAuto

`quickSpinBooleanNode` SharpeningAuto

5.2.1.602 SharpeningEnable

`quickSpinBooleanNode` SharpeningEnable

5.2.1.603 SharpeningThreshold

`quickSpinFloatNode` SharpeningThreshold

5.2.1.604 SoftwareSignalPulse

`quickSpinCommandNode` SoftwareSignalPulse

5.2.1.605 SoftwareSignalSelector

`quickSpinEnumerationNode` SoftwareSignalSelector

5.2.1.606 SourceCount

`quickSpinIntegerNode` SourceCount

5.2.1.607 SourceSelector

`quickSpinEnumerationNode` SourceSelector

5.2.1.608 Test0001

`quickSpinIntegerNode` Test0001

5.2.1.609 TestEventGenerate

`quickSpinCommandNode` TestEventGenerate

5.2.1.610 TestPattern

`quickSpinEnumerationNode` TestPattern

5.2.1.611 TestPatternGeneratorSelector

`quickSpinEnumerationNode` TestPatternGeneratorSelector

5.2.1.612 TestPendingAck

`quickSpinIntegerNode` TestPendingAck

5.2.1.613 TimerDelay

`quickSpinFloatNode` TimerDelay

5.2.1.614 TimerDuration

`quickSpinFloatNode` TimerDuration

5.2.1.615 TimerReset

`quickSpinCommandNode` TimerReset

5.2.1.616 TimerSelector

`quickSpinEnumerationNode` TimerSelector

5.2.1.617 TimerStatus

`quickSpinEnumerationNode` TimerStatus

5.2.1.618 TimerTriggerActivation

`quickSpinEnumerationNode` TimerTriggerActivation

5.2.1.619 TimerTriggerSource

`quickSpinEnumerationNode` TimerTriggerSource

5.2.1.620 TimerValue

`quickSpinFloatNode` TimerValue

5.2.1.621 Timestamp

[quickSpinIntegerNode](#) Timestamp

5.2.1.622 TimestampLatch

[quickSpinCommandNode](#) TimestampLatch

5.2.1.623 TimestampLatchValue

[quickSpinIntegerNode](#) TimestampLatchValue

5.2.1.624 TimestampReset

[quickSpinCommandNode](#) TimestampReset

5.2.1.625 TLParamsLocked

[quickSpinIntegerNode](#) TLParamsLocked

5.2.1.626 TransferAbort

[quickSpinCommandNode](#) TransferAbort

5.2.1.627 TransferBlockCount

[quickSpinIntegerNode](#) TransferBlockCount

5.2.1.628 TransferBurstCount

[quickSpinIntegerNode](#) TransferBurstCount

5.2.1.629 TransferComponentSelector

[quickSpinEnumerationNode](#) TransferComponentSelector

5.2.1.630 TransferControlMode

[quickSpinEnumerationNode](#) TransferControlMode

5.2.1.631 TransferOperationMode

[quickSpinEnumerationNode](#) TransferOperationMode

5.2.1.632 TransferPause

[quickSpinCommandNode](#) TransferPause

5.2.1.633 TransferQueueCurrentBlockCount

[quickSpinIntegerNode](#) TransferQueueCurrentBlockCount

5.2.1.634 TransferQueueMaxBlockCount

[quickSpinIntegerNode](#) TransferQueueMaxBlockCount

5.2.1.635 TransferQueueMode

[quickSpinEnumerationNode](#) TransferQueueMode

5.2.1.636 TransferQueueOverflowCount

[quickSpinIntegerNode](#) TransferQueueOverflowCount

5.2.1.637 TransferResume

[quickSpinCommandNode](#) TransferResume

5.2.1.638 TransferSelector

[quickSpinEnumerationNode](#) TransferSelector

5.2.1.639 TransferStart

[quickSpinCommandNode](#) TransferStart

5.2.1.640 TransferStatus

[quickSpinBooleanNode](#) TransferStatus

5.2.1.641 TransferStatusSelector

[quickSpinEnumerationNode](#) TransferStatusSelector

5.2.1.642 TransferStop

[quickSpinCommandNode](#) TransferStop

5.2.1.643 TransferStreamChannel

[quickSpinIntegerNode](#) TransferStreamChannel

5.2.1.644 TransferTriggerActivation

[quickSpinEnumerationNode](#) TransferTriggerActivation

5.2.1.645 TransferTriggerMode

`quickSpinEnumerationNode` TransferTriggerMode

5.2.1.646 TransferTriggerSelector

`quickSpinEnumerationNode` TransferTriggerSelector

5.2.1.647 TransferTriggerSource

`quickSpinEnumerationNode` TransferTriggerSource

5.2.1.648 TriggerActivation

`quickSpinEnumerationNode` TriggerActivation

5.2.1.649 TriggerDelay

`quickSpinFloatNode` TriggerDelay

5.2.1.650 TriggerDivider

`quickSpinIntegerNode` TriggerDivider

5.2.1.651 TriggerEventTest

`quickSpinCommandNode` TriggerEventTest

5.2.1.652 TriggerMode

`quickSpinEnumerationNode` TriggerMode

5.2.1.653 TriggerMultiplier

`quickSpinIntegerNode` TriggerMultiplier

5.2.1.654 TriggerOverlap

`quickSpinEnumerationNode` TriggerOverlap

5.2.1.655 TriggerSelector

`quickSpinEnumerationNode` TriggerSelector

5.2.1.656 TriggerSoftware

`quickSpinCommandNode` TriggerSoftware

5.2.1.657 TriggerSource

`quickSpinEnumerationNode` TriggerSource

5.2.1.658 UserOutputSelector

`quickSpinEnumerationNode` UserOutputSelector

5.2.1.659 UserOutputValue

`quickSpinBooleanNode` UserOutputValue

5.2.1.660 UserOutputValueAll

`quickSpinIntegerNode` UserOutputValueAll

5.2.1.661 UserOutputValueAllMask

`quickSpinIntegerNode` UserOutputValueAllMask

5.2.1.662 UserSetDefault

`quickSpinEnumerationNode` UserSetDefault

5.2.1.663 UserSetFeatureEnable

`quickSpinBooleanNode` UserSetFeatureEnable

5.2.1.664 UserSetLoad

`quickSpinCommandNode` UserSetLoad

5.2.1.665 UserSetSave

`quickSpinCommandNode` UserSetSave

5.2.1.666 UserSetSelector

`quickSpinEnumerationNode` UserSetSelector

5.2.1.667 V3_3Enable

`quickSpinBooleanNode` V3_3Enable

5.2.1.668 WhiteClip

`quickSpinFloatNode` WhiteClip

5.2.1.669 WhiteClipSelector

[quickSpinEnumerationNode](#) [WhiteClipSelector](#)

5.2.1.670 Width

[quickSpinIntegerNode](#) [Width](#)

5.2.1.671 WidthMax

[quickSpinIntegerNode](#) [WidthMax](#)

The documentation for this struct was generated from the following file:

- [include/spinc/QuickSpinDefsC.h](#)

5.3 quickSpinTLDevice Struct Reference**Data Fields**

- [quickSpinStringNode](#) [DeviceID](#)
- [quickSpinStringNode](#) [DeviceSerialNumber](#)
- [quickSpinStringNode](#) [DeviceVendorName](#)
- [quickSpinStringNode](#) [DeviceModelName](#)
- [quickSpinEnumerationNode](#) [DeviceType](#)
- [quickSpinStringNode](#) [DeviceDisplayName](#)
- [quickSpinEnumerationNode](#) [DeviceAccessStatus](#)
- [quickSpinStringNode](#) [DeviceVersion](#)
- [quickSpinStringNode](#) [DeviceUserID](#)
- [quickSpinStringNode](#) [DeviceDriverVersion](#)
- [quickSpinBooleanNode](#) [DevicesUpdater](#)
- [quickSpinEnumerationNode](#) [GevCCP](#)
- [quickSpinEnumerationNode](#) [GUIXMLLocation](#)
- [quickSpinStringNode](#) [GUIXMLPath](#)
- [quickSpinEnumerationNode](#) [GenICamXMLLocation](#)
- [quickSpinStringNode](#) [GenICamXMLPath](#)
- [quickSpinIntegerNode](#) [GevDeviceIPAddress](#)
- [quickSpinIntegerNode](#) [GevDeviceSubnetMask](#)
- [quickSpinIntegerNode](#) [GevDeviceMACAddress](#)
- [quickSpinIntegerNode](#) [GevDeviceGateway](#)
- [quickSpinIntegerNode](#) [DeviceLinkSpeed](#)
- [quickSpinIntegerNode](#) [GevVersionMajor](#)
- [quickSpinIntegerNode](#) [GevVersionMinor](#)
- [quickSpinBooleanNode](#) [GevDeviceModelsBigEndian](#)
- [quickSpinIntegerNode](#) [GevDeviceReadAndWriteTimeout](#)

- [quickSpinIntegerNode](#) [GevDeviceMaximumRetryCount](#)
- [quickSpinIntegerNode](#) [GevDevicePort](#)
- [quickSpinCommandNode](#) [GevDeviceDiscoverMaximumPacketSize](#)
- [quickSpinIntegerNode](#) [GevDeviceMaximumPacketSize](#)
- [quickSpinBooleanNode](#) [GevDeviceIsWrongSubnet](#)
- [quickSpinCommandNode](#) [GevDeviceAutoForceIP](#)
- [quickSpinCommandNode](#) [GevDeviceForceIP](#)
- [quickSpinIntegerNode](#) [GevDeviceForceIPAddress](#)
- [quickSpinIntegerNode](#) [GevDeviceForceSubnetMask](#)
- [quickSpinIntegerNode](#) [GevDeviceForceGateway](#)
- [quickSpinBooleanNode](#) [DeviceMulticastMonitorMode](#)
- [quickSpinEnumerationNode](#) [DeviceEndiannessMechanism](#)
- [quickSpinStringNode](#) [DeviceInstanceId](#)
- [quickSpinStringNode](#) [DeviceLocation](#)
- [quickSpinEnumerationNode](#) [DeviceCurrentSpeed](#)
- [quickSpinBooleanNode](#) [DeviceU3VProtocol](#)

5.3.1 Field Documentation

5.3.1.1 DeviceAccessStatus

[quickSpinEnumerationNode](#) [DeviceAccessStatus](#)

5.3.1.2 DeviceCurrentSpeed

[quickSpinEnumerationNode](#) [DeviceCurrentSpeed](#)

5.3.1.3 DeviceDisplayName

[quickSpinStringNode](#) [DeviceDisplayName](#)

5.3.1.4 DeviceDriverVersion

[quickSpinStringNode](#) [DeviceDriverVersion](#)

5.3.1.5 DeviceEndiannessMechanism

[quickSpinEnumerationNode](#) DeviceEndiannessMechanism

5.3.1.6 DeviceID

[quickSpinStringNode](#) DeviceID

5.3.1.7 DeviceInstanceId

[quickSpinStringNode](#) DeviceInstanceId

5.3.1.8 DeviceIsUpdater

[quickSpinBooleanNode](#) DeviceIsUpdater

5.3.1.9 DeviceLinkSpeed

[quickSpinIntegerNode](#) DeviceLinkSpeed

5.3.1.10 DeviceLocation

[quickSpinStringNode](#) DeviceLocation

5.3.1.11 DeviceModelName

[quickSpinStringNode](#) DeviceModelName

5.3.1.12 DeviceMulticastMonitorMode

[quickSpinBooleanNode](#) DeviceMulticastMonitorMode

5.3.1.13 DeviceSerialNumber

[quickSpinStringNode](#) DeviceSerialNumber

5.3.1.14 DeviceType

[quickSpinEnumerationNode](#) DeviceType

5.3.1.15 DeviceU3VProtocol

[quickSpinBooleanNode](#) DeviceU3VProtocol

5.3.1.16 DeviceUserID

[quickSpinStringNode](#) DeviceUserID

5.3.1.17 DeviceVendorName

[quickSpinStringNode](#) DeviceVendorName

5.3.1.18 DeviceVersion

[quickSpinStringNode](#) DeviceVersion

5.3.1.19 GenICamXMLLocation

[quickSpinEnumerationNode](#) GenICamXMLLocation

5.3.1.20 GenICamXMLPath

[quickSpinStringNode](#) GenICamXMLPath

5.3.1.21 GevCCP

[quickSpinEnumerationNode](#) GevCCP

5.3.1.22 GevDeviceAutoForceIP

[quickSpinCommandNode](#) GevDeviceAutoForceIP

5.3.1.23 GevDeviceDiscoverMaximumPacketSize

[quickSpinCommandNode](#) GevDeviceDiscoverMaximumPacketSize

5.3.1.24 GevDeviceForceGateway

[quickSpinIntegerNode](#) GevDeviceForceGateway

5.3.1.25 GevDeviceForceIP

[quickSpinCommandNode](#) GevDeviceForceIP

5.3.1.26 GevDeviceForceIPAddress

[quickSpinIntegerNode](#) GevDeviceForceIPAddress

5.3.1.27 GevDeviceForceSubnetMask

[quickSpinIntegerNode](#) GevDeviceForceSubnetMask

5.3.1.28 GevDeviceGateway

[quickSpinIntegerNode](#) GevDeviceGateway

5.3.1.29 GevDeviceIPAddress

`quickSpinIntegerNode` GevDeviceIPAddress

5.3.1.30 GevDeviceIsWrongSubnet

`quickSpinBooleanNode` GevDeviceIsWrongSubnet

5.3.1.31 GevDeviceMACAddress

`quickSpinIntegerNode` GevDeviceMACAddress

5.3.1.32 GevDeviceMaximumPacketSize

`quickSpinIntegerNode` GevDeviceMaximumPacketSize

5.3.1.33 GevDeviceMaximumRetryCount

`quickSpinIntegerNode` GevDeviceMaximumRetryCount

5.3.1.34 GevDeviceModelsBigEndian

`quickSpinBooleanNode` GevDeviceModeIsBigEndian

5.3.1.35 GevDevicePort

`quickSpinIntegerNode` GevDevicePort

5.3.1.36 GevDeviceReadAndWriteTimeout

`quickSpinIntegerNode` GevDeviceReadAndWriteTimeout

5.3.1.37 `GevDeviceSubnetMask`

[quickSpinIntegerNode](#) `GevDeviceSubnetMask`

5.3.1.38 `GevVersionMajor`

[quickSpinIntegerNode](#) `GevVersionMajor`

5.3.1.39 `GevVersionMinor`

[quickSpinIntegerNode](#) `GevVersionMinor`

5.3.1.40 `GUIXMLLocation`

[quickSpinEnumerationNode](#) `GUIXMLLocation`

5.3.1.41 `GUIXMLPath`

[quickSpinStringNode](#) `GUIXMLPath`

The documentation for this struct was generated from the following file:

- [include/spinc/TransportLayerDeviceC.h](#)

5.4 `quickSpinTLInterface` Struct Reference

Data Fields

- [quickSpinStringNode](#) `InterfaceID`
- [quickSpinStringNode](#) `InterfaceDisplayName`
- [quickSpinEnumerationNode](#) `InterfaceType`
- [quickSpinIntegerNode](#) `GevInterfaceGatewaySelector`
- [quickSpinIntegerNode](#) `GevInterfaceGateway`
- [quickSpinIntegerNode](#) `GevInterfaceMACAddress`
- [quickSpinIntegerNode](#) `GevInterfaceSubnetSelector`
- [quickSpinIntegerNode](#) `GevInterfaceSubnetIPAddress`
- [quickSpinIntegerNode](#) `GevInterfaceSubnetMask`
- [quickSpinIntegerNode](#) `GevInterfaceTransmitLinkSpeed`
- [quickSpinIntegerNode](#) `GevInterfaceReceiveLinkSpeed`

- [quickSpinIntegerNode](#) [GevInterfaceMTU](#)
- [quickSpinEnumerationNode](#) [POEStatus](#)
- [quickSpinEnumerationNode](#) [FilterDriverStatus](#)
- [quickSpinIntegerNode](#) [GevActionDeviceKey](#)
- [quickSpinIntegerNode](#) [GevActionGroupKey](#)
- [quickSpinIntegerNode](#) [GevActionGroupMask](#)
- [quickSpinIntegerNode](#) [GevActionTime](#)
- [quickSpinCommandNode](#) [ActionCommand](#)
- [quickSpinStringNode](#) [DeviceUnlock](#)
- [quickSpinCommandNode](#) [DeviceUpdateList](#)
- [quickSpinIntegerNode](#) [DeviceCount](#)
- [quickSpinIntegerNode](#) [DeviceSelector](#)
- [quickSpinStringNode](#) [DeviceID](#)
- [quickSpinStringNode](#) [DeviceVendorName](#)
- [quickSpinStringNode](#) [DeviceModelName](#)
- [quickSpinStringNode](#) [DeviceSerialNumber](#)
- [quickSpinEnumerationNode](#) [DeviceAccessStatus](#)
- [quickSpinIntegerNode](#) [GevDeviceIPAddress](#)
- [quickSpinIntegerNode](#) [GevDeviceSubnetMask](#)
- [quickSpinIntegerNode](#) [GevDeviceGateway](#)
- [quickSpinIntegerNode](#) [GevDeviceMACAddress](#)
- [quickSpinIntegerNode](#) [IncompatibleDeviceCount](#)
- [quickSpinIntegerNode](#) [IncompatibleDeviceSelector](#)
- [quickSpinStringNode](#) [IncompatibleDeviceID](#)
- [quickSpinStringNode](#) [IncompatibleDeviceVendorName](#)
- [quickSpinStringNode](#) [IncompatibleDeviceModelName](#)
- [quickSpinIntegerNode](#) [IncompatibleGevDeviceIPAddress](#)
- [quickSpinIntegerNode](#) [IncompatibleGevDeviceSubnetMask](#)
- [quickSpinIntegerNode](#) [IncompatibleGevDeviceMACAddress](#)
- [quickSpinCommandNode](#) [GevDeviceForceIP](#)
- [quickSpinIntegerNode](#) [GevDeviceForceIPAddress](#)
- [quickSpinIntegerNode](#) [GevDeviceForceSubnetMask](#)
- [quickSpinIntegerNode](#) [GevDeviceForceGateway](#)
- [quickSpinCommandNode](#) [GevDeviceAutoForceIP](#)
- [quickSpinStringNode](#) [HostAdapterName](#)
- [quickSpinStringNode](#) [HostAdapterVendor](#)
- [quickSpinStringNode](#) [HostAdapterDriverVersion](#)

5.4.1 Field Documentation

5.4.1.1 ActionCommand

[quickSpinCommandNode](#) [ActionCommand](#)

5.4.1.2 DeviceAccessStatus

[quickSpinEnumerationNode](#) [DeviceAccessStatus](#)

5.4.1.3 DeviceCount

[quickSpinIntegerNode](#) DeviceCount

5.4.1.4 DeviceID

[quickSpinStringNode](#) DeviceID

5.4.1.5 DeviceModelName

[quickSpinStringNode](#) DeviceModelName

5.4.1.6 DeviceSelector

[quickSpinIntegerNode](#) DeviceSelector

5.4.1.7 DeviceSerialNumber

[quickSpinStringNode](#) DeviceSerialNumber

5.4.1.8 DeviceUnlock

[quickSpinStringNode](#) DeviceUnlock

5.4.1.9 DeviceUpdateList

[quickSpinCommandNode](#) DeviceUpdateList

5.4.1.10 DeviceVendorName

[quickSpinStringNode](#) DeviceVendorName

5.4.1.11 FilterDriverStatus

[quickSpinEnumerationNode](#) FilterDriverStatus

5.4.1.12 GevActionDeviceKey

[quickSpinIntegerNode](#) GevActionDeviceKey

5.4.1.13 GevActionGroupKey

[quickSpinIntegerNode](#) GevActionGroupKey

5.4.1.14 GevActionGroupMask

[quickSpinIntegerNode](#) GevActionGroupMask

5.4.1.15 GevActionTime

[quickSpinIntegerNode](#) GevActionTime

5.4.1.16 GevDeviceAutoForceIP

[quickSpinCommandNode](#) GevDeviceAutoForceIP

5.4.1.17 GevDeviceForceGateway

[quickSpinIntegerNode](#) GevDeviceForceGateway

5.4.1.18 GevDeviceForceIP

[quickSpinCommandNode](#) GevDeviceForceIP

5.4.1.19 GevDeviceForceIPAddress

`quickSpinIntegerNode` GevDeviceForceIPAddress

5.4.1.20 GevDeviceForceSubnetMask

`quickSpinIntegerNode` GevDeviceForceSubnetMask

5.4.1.21 GevDeviceGateway

`quickSpinIntegerNode` GevDeviceGateway

5.4.1.22 GevDeviceIPAddress

`quickSpinIntegerNode` GevDeviceIPAddress

5.4.1.23 GevDeviceMACAddress

`quickSpinIntegerNode` GevDeviceMACAddress

5.4.1.24 GevDeviceSubnetMask

`quickSpinIntegerNode` GevDeviceSubnetMask

5.4.1.25 GevInterfaceGateway

`quickSpinIntegerNode` GevInterfaceGateway

5.4.1.26 GevInterfaceGatewaySelector

`quickSpinIntegerNode` GevInterfaceGatewaySelector

5.4.1.27 `GevInterfaceMACAddress`

`quickSpinIntegerNode` `GevInterfaceMACAddress`

5.4.1.28 `GevInterfaceMTU`

`quickSpinIntegerNode` `GevInterfaceMTU`

5.4.1.29 `GevInterfaceReceiveLinkSpeed`

`quickSpinIntegerNode` `GevInterfaceReceiveLinkSpeed`

5.4.1.30 `GevInterfaceSubnetIPAddress`

`quickSpinIntegerNode` `GevInterfaceSubnetIPAddress`

5.4.1.31 `GevInterfaceSubnetMask`

`quickSpinIntegerNode` `GevInterfaceSubnetMask`

5.4.1.32 `GevInterfaceSubnetSelector`

`quickSpinIntegerNode` `GevInterfaceSubnetSelector`

5.4.1.33 `GevInterfaceTransmitLinkSpeed`

`quickSpinIntegerNode` `GevInterfaceTransmitLinkSpeed`

5.4.1.34 `HostAdapterDriverVersion`

`quickSpinStringNode` `HostAdapterDriverVersion`

5.4.1.35 HostAdapterName

`quickSpinStringNode` HostAdapterName

5.4.1.36 HostAdapterVendor

`quickSpinStringNode` HostAdapterVendor

5.4.1.37 IncompatibleDeviceCount

`quickSpinIntegerNode` IncompatibleDeviceCount

5.4.1.38 IncompatibleDeviceID

`quickSpinStringNode` IncompatibleDeviceID

5.4.1.39 IncompatibleDeviceModelName

`quickSpinStringNode` IncompatibleDeviceModelName

5.4.1.40 IncompatibleDeviceSelector

`quickSpinIntegerNode` IncompatibleDeviceSelector

5.4.1.41 IncompatibleDeviceVendorName

`quickSpinStringNode` IncompatibleDeviceVendorName

5.4.1.42 IncompatibleGevDeviceIPAddress

`quickSpinIntegerNode` IncompatibleGevDeviceIPAddress

5.4.1.43 IncompatibleGevDeviceMACAddress

`quickSpinIntegerNode` IncompatibleGevDeviceMACAddress

5.4.1.44 IncompatibleGevDeviceSubnetMask

`quickSpinIntegerNode` IncompatibleGevDeviceSubnetMask

5.4.1.45 InterfaceDisplayName

`quickSpinStringNode` InterfaceDisplayName

5.4.1.46 InterfaceID

`quickSpinStringNode` InterfaceID

5.4.1.47 InterfaceType

`quickSpinEnumerationNode` InterfaceType

5.4.1.48 POEStatus

`quickSpinEnumerationNode` POEStatus

The documentation for this struct was generated from the following file:

- `include/spinc/TransportLayerInterfaceC.h`

5.5 quickSpinTLStream Struct Reference

Data Fields

- [quickSpinStringNode](#) StreamID
- [quickSpinEnumerationNode](#) StreamType
- [quickSpinIntegerNode](#) StreamBufferCountManual
- [quickSpinIntegerNode](#) StreamBufferCountResult
- [quickSpinIntegerNode](#) StreamBufferCountMax
- [quickSpinEnumerationNode](#) StreamBufferCountMode
- [quickSpinEnumerationNode](#) StreamBufferHandlingMode
- [quickSpinIntegerNode](#) StreamAnnounceBufferMinimum
- [quickSpinIntegerNode](#) StreamAnnouncedBufferCount
- [quickSpinIntegerNode](#) StreamStartedFrameCount
- [quickSpinIntegerNode](#) StreamDeliveredFrameCount
- [quickSpinIntegerNode](#) StreamLostFrameCount
- [quickSpinIntegerNode](#) StreamInputBufferCount
- [quickSpinIntegerNode](#) StreamOutputBufferCount
- [quickSpinBooleanNode](#) StreamCRCCheckEnable
- [quickSpinBooleanNode](#) GevPacketResendMode
- [quickSpinIntegerNode](#) GevMaximumNumberResendRequests
- [quickSpinIntegerNode](#) GevPacketResendTimeout
- [quickSpinBooleanNode](#) StreamIsGrabbing
- [quickSpinIntegerNode](#) StreamChunkCountMaximum
- [quickSpinIntegerNode](#) StreamBufferAlignment
- [quickSpinIntegerNode](#) GevTotalPacketCount
- [quickSpinIntegerNode](#) GevFailedPacketCount
- [quickSpinIntegerNode](#) GevResendPacketCount
- [quickSpinIntegerNode](#) StreamFailedBufferCount
- [quickSpinIntegerNode](#) GevResendRequestCount
- [quickSpinIntegerNode](#) StreamBlockTransferSize

5.5.1 Field Documentation

5.5.1.1 GevFailedPacketCount

[quickSpinIntegerNode](#) GevFailedPacketCount

5.5.1.2 GevMaximumNumberResendRequests

[quickSpinIntegerNode](#) GevMaximumNumberResendRequests

5.5.1.3 GevPacketResendMode

[quickSpinBooleanNode](#) GevPacketResendMode

5.5.1.4 GevPacketResendTimeout

[quickSpinIntegerNode](#) GevPacketResendTimeout

5.5.1.5 GevResendPacketCount

[quickSpinIntegerNode](#) GevResendPacketCount

5.5.1.6 GevResendRequestCount

[quickSpinIntegerNode](#) GevResendRequestCount

5.5.1.7 GevTotalPacketCount

[quickSpinIntegerNode](#) GevTotalPacketCount

5.5.1.8 StreamAnnounceBufferMinimum

[quickSpinIntegerNode](#) StreamAnnounceBufferMinimum

5.5.1.9 StreamAnnouncedBufferCount

[quickSpinIntegerNode](#) StreamAnnouncedBufferCount

5.5.1.10 StreamBlockTransferSize

[quickSpinIntegerNode](#) StreamBlockTransferSize

5.5.1.11 StreamBufferAlignment

[quickSpinIntegerNode](#) StreamBufferAlignment

5.5.1.12 StreamBufferCountManual

[quickSpinIntegerNode](#) StreamBufferCountManual

5.5.1.13 StreamBufferCountMax

[quickSpinIntegerNode](#) StreamBufferCountMax

5.5.1.14 StreamBufferCountMode

[quickSpinEnumerationNode](#) StreamBufferCountMode

5.5.1.15 StreamBufferCountResult

[quickSpinIntegerNode](#) StreamBufferCountResult

5.5.1.16 StreamBufferHandlingMode

[quickSpinEnumerationNode](#) StreamBufferHandlingMode

5.5.1.17 StreamChunkCountMaximum

[quickSpinIntegerNode](#) StreamChunkCountMaximum

5.5.1.18 StreamCRCCheckEnable

[quickSpinBooleanNode](#) StreamCRCCheckEnable

5.5.1.19 StreamDeliveredFrameCount

`quickSpinIntegerNode` StreamDeliveredFrameCount

5.5.1.20 StreamFailedBufferCount

`quickSpinIntegerNode` StreamFailedBufferCount

5.5.1.21 StreamID

`quickSpinStringNode` StreamID

5.5.1.22 StreamInputBufferCount

`quickSpinIntegerNode` StreamInputBufferCount

5.5.1.23 StreamIsGrabbing

`quickSpinBooleanNode` StreamIsGrabbing

5.5.1.24 StreamLostFrameCount

`quickSpinIntegerNode` StreamLostFrameCount

5.5.1.25 StreamOutputBufferCount

`quickSpinIntegerNode` StreamOutputBufferCount

5.5.1.26 StreamStartedFrameCount

`quickSpinIntegerNode` StreamStartedFrameCount

5.5.1.27 StreamType

`quickSpinEnumerationNode` StreamType

The documentation for this struct was generated from the following file:

- `include/spinc/TransportLayerStreamC.h`

5.6 quickSpinTLSystem Struct Reference

Data Fields

- `quickSpinBooleanNode` EnumerateGEVInterfaces
- `quickSpinStringNode` TLID
- `quickSpinStringNode` TLVendorName
- `quickSpinStringNode` TLModelName
- `quickSpinStringNode` TLVersion
- `quickSpinStringNode` TLFileName
- `quickSpinStringNode` TLDisplayName
- `quickSpinStringNode` TLPath
- `quickSpinEnumerationNode` TLType
- `quickSpinIntegerNode` GenTLVersionMajor
- `quickSpinIntegerNode` GenTLVersionMinor
- `quickSpinIntegerNode` GenTLSFNCVersionMajor
- `quickSpinIntegerNode` GenTLSFNCVersionMinor
- `quickSpinIntegerNode` GenTLSFNCVersionSubMinor
- `quickSpinIntegerNode` GevVersionMajor
- `quickSpinIntegerNode` GevVersionMinor
- `quickSpinCommandNode` InterfaceUpdateList
- `quickSpinIntegerNode` InterfaceSelector
- `quickSpinStringNode` InterfaceID
- `quickSpinStringNode` InterfaceDisplayName
- `quickSpinIntegerNode` GevInterfaceMACAddress
- `quickSpinIntegerNode` GevInterfaceDefaultIPAddress
- `quickSpinIntegerNode` GevInterfaceDefaultSubnetMask
- `quickSpinIntegerNode` GevInterfaceDefaultGateway

5.6.1 Field Documentation

5.6.1.1 EnumerateGEVInterfaces

`quickSpinBooleanNode` EnumerateGEVInterfaces

5.6.1.2 GenTLNFNCVersionMajor

`quickSpinIntegerNode` GenTLNFNCVersionMajor

5.6.1.3 GenTLNFNCVersionMinor

`quickSpinIntegerNode` GenTLNFNCVersionMinor

5.6.1.4 GenTLNFNCVersionSubMinor

`quickSpinIntegerNode` GenTLNFNCVersionSubMinor

5.6.1.5 GenTLVersionMajor

`quickSpinIntegerNode` GenTLVersionMajor

5.6.1.6 GenTLVersionMinor

`quickSpinIntegerNode` GenTLVersionMinor

5.6.1.7 GevInterfaceDefaultGateway

`quickSpinIntegerNode` GevInterfaceDefaultGateway

5.6.1.8 GevInterfaceDefaultIPAddress

`quickSpinIntegerNode` GevInterfaceDefaultIPAddress

5.6.1.9 GevInterfaceDefaultSubnetMask

`quickSpinIntegerNode` GevInterfaceDefaultSubnetMask

5.6.1.10 **GevInterfaceMACAddress**

[quickSpinIntegerNode](#) `GevInterfaceMACAddress`

5.6.1.11 **GevVersionMajor**

[quickSpinIntegerNode](#) `GevVersionMajor`

5.6.1.12 **GevVersionMinor**

[quickSpinIntegerNode](#) `GevVersionMinor`

5.6.1.13 **InterfaceDisplayName**

[quickSpinStringNode](#) `InterfaceDisplayName`

5.6.1.14 **InterfaceID**

[quickSpinStringNode](#) `InterfaceID`

5.6.1.15 **InterfaceSelector**

[quickSpinIntegerNode](#) `InterfaceSelector`

5.6.1.16 **InterfaceUpdateList**

[quickSpinCommandNode](#) `InterfaceUpdateList`

5.6.1.17 **TLDisplayName**

[quickSpinStringNode](#) `TLDisplayName`

5.6.1.18 TLFileName

[quickSpinStringNode](#) TLFileName

5.6.1.19 TLID

[quickSpinStringNode](#) TLID

5.6.1.20 TLModelName

[quickSpinStringNode](#) TLModelName

5.6.1.21 TLPath

[quickSpinStringNode](#) TLPath

5.6.1.22 TLType

[quickSpinEnumerationNode](#) TLType

5.6.1.23 TLVendorName

[quickSpinStringNode](#) TLVendorName

5.6.1.24 TLVersion

[quickSpinStringNode](#) TLVersion

The documentation for this struct was generated from the following file:

- [include/spinc/TransportLayerSystemC.h](#)

5.7 spinAVIOption Struct Reference

Options for saving uncompressed videos.

Data Fields

- float [frameRate](#)
Frame rate of the stream.
- unsigned int [reserved](#) [256]
Reserved for future use.

5.7.1 Detailed Description

Options for saving uncompressed videos.

Used in saving AVI videos with a call to `spinAVIRecorderOpenUncompressed()`.

5.7.2 Field Documentation

5.7.2.1 frameRate

```
float frameRate
```

Frame rate of the stream.

5.7.2.2 reserved

```
unsigned int reserved[256]
```

Reserved for future use.

The documentation for this struct was generated from the following file:

- `include/spinc/SpinnakerDefsC.h`

5.8 spinBMPOption Struct Reference

Options for saving BMP images.

Data Fields

- [bool8_t indexedColor_8bit](#)
- unsigned int [reserved](#) [16]

Reserved for future use.

5.8.1 Detailed Description

Options for saving BMP images.

Used in saving PPM images with a call to [spinImageSaveBmp\(\)](#).

5.8.2 Field Documentation

5.8.2.1 indexedColor_8bit

[bool8_t](#) indexedColor_8bit

5.8.2.2 reserved

unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

- include/spinc/[SpinnakerDefsC.h](#)

5.9 spinChunkData Struct Reference

The type of information that can be obtained from image chunk data.

Data Fields

- double [m_blackLevel](#)
- int64_t [m_frameID](#)
- double [m_exposureTime](#)
- int64_t [m_timestamp](#)
- int64_t [m_exposureEndLineStatusAll](#)
- int64_t [m_width](#)
- int64_t [m_image](#)
- int64_t [m_height](#)
- double [m_gain](#)
- int64_t [m_sequencerSetActive](#)
- int64_t [m_cRC](#)
- int64_t [m_offsetX](#)
- int64_t [m_offsetY](#)
- int64_t [m_serialDataLength](#)
- int64_t [m_partSelector](#)
- int64_t [m_pixelDynamicRangeMin](#)
- int64_t [m_pixelDynamicRangeMax](#)
- int64_t [m_timestampLatchValue](#)
- int64_t [m_lineStatusAll](#)
- int64_t [m_counterValue](#)
- double [m_timerValue](#)
- int64_t [m_scanLineSelector](#)
- int64_t [m_encoderValue](#)
- int64_t [m_linePitch](#)
- int64_t [m_transferBlockID](#)
- int64_t [m_transferQueueCurrentBlockCount](#)
- int64_t [m_streamChannelID](#)
- double [m_scan3dCoordinateScale](#)
- double [m_scan3dCoordinateOffset](#)
- double [m_scan3dInvalidDataValue](#)
- double [m_scan3dAxisMin](#)
- double [m_scan3dAxisMax](#)
- double [m_scan3dTransformValue](#)
- double [m_scan3dCoordinateReferenceValue](#)
- int64_t [m_inferenceFrameId](#)
- int64_t [m_inferenceResult](#)
- double [m_inferenceConfidence](#)

5.9.1 Detailed Description

The type of information that can be obtained from image chunk data.

5.9.2 Field Documentation

5.9.2.1 [m_blackLevel](#)

double [m_blackLevel](#)

5.9.2.2 m_counterValue

int64_t m_counterValue

5.9.2.3 m_cRC

int64_t m_cRC

5.9.2.4 m_encoderValue

int64_t m_encoderValue

5.9.2.5 m_exposureEndLineStyleAll

int64_t m_exposureEndLineStyleAll

5.9.2.6 m_exposureTime

double m_exposureTime

5.9.2.7 m_frameID

int64_t m_frameID

5.9.2.8 m_gain

double m_gain

5.9.2.9 m_height

int64_t m_height

5.9.2.10 m_image

```
int64_t m_image
```

5.9.2.11 m_inferenceConfidence

```
double m_inferenceConfidence
```

5.9.2.12 m_inferenceFrameId

```
int64_t m_inferenceFrameId
```

5.9.2.13 m_inferenceResult

```
int64_t m_inferenceResult
```

5.9.2.14 m_linePitch

```
int64_t m_linePitch
```

5.9.2.15 m_lineStatusAll

```
int64_t m_lineStatusAll
```

5.9.2.16 m_offsetX

```
int64_t m_offsetX
```

5.9.2.17 m_offsetY

```
int64_t m_offsetY
```

5.9.2.18 m_partSelector

```
int64_t m_partSelector
```

5.9.2.19 m_pixelDynamicRangeMax

```
int64_t m_pixelDynamicRangeMax
```

5.9.2.20 m_pixelDynamicRangeMin

```
int64_t m_pixelDynamicRangeMin
```

5.9.2.21 m_scan3dAxisMax

```
double m_scan3dAxisMax
```

5.9.2.22 m_scan3dAxisMin

```
double m_scan3dAxisMin
```

5.9.2.23 m_scan3dCoordinateOffset

```
double m_scan3dCoordinateOffset
```

5.9.2.24 m_scan3dCoordinateReferenceValue

```
double m_scan3dCoordinateReferenceValue
```

5.9.2.25 m_scan3dCoordinateScale

```
double m_scan3dCoordinateScale
```

5.9.2.26 m_scan3dInvalidDataValue

```
double m_scan3dInvalidDataValue
```

5.9.2.27 m_scan3dTransformValue

```
double m_scan3dTransformValue
```

5.9.2.28 m_scanLineSelector

```
int64_t m_scanLineSelector
```

5.9.2.29 m_sequencerSetActive

```
int64_t m_sequencerSetActive
```

5.9.2.30 m_serialDataLength

```
int64_t m_serialDataLength
```

5.9.2.31 m_streamChannelID

```
int64_t m_streamChannelID
```

5.9.2.32 m_timerValue

```
double m_timerValue
```

5.9.2.33 m_timestamp

```
int64_t m_timestamp
```


5.9.2.34 m_timestampLatchValue

int64_t m_timestampLatchValue

5.9.2.35 m_transferBlockID

int64_t m_transferBlockID

5.9.2.36 m_transferQueueCurrentBlockCount

int64_t m_transferQueueCurrentBlockCount

5.9.2.37 m_width

int64_t m_width

The documentation for this struct was generated from the following file:

- include/spinc/[ChunkDataDefC.h](#)

5.10 spinH264Option Struct Reference

Options for saving H264 videos.

Data Fields

- float [frameRate](#)
Frame rate of the stream.
- unsigned int [width](#)
Width of source image.
- unsigned int [height](#)
Height of source image.
- unsigned int [bitrate](#)
Bitrate to encode at.
- unsigned int [reserved](#) [256]
Reserved for future use.

5.10.1 Detailed Description

Options for saving H264 videos.

Used in saving H264 videos with a call to `spinAVIRecorderOpenH264()`.

5.10.2 Field Documentation

5.10.2.1 bitrate

```
unsigned int bitrate
```

Bitrate to encode at.

5.10.2.2 frameRate

```
float frameRate
```

Frame rate of the stream.

5.10.2.3 height

```
unsigned int height
```

Height of source image.

5.10.2.4 reserved

```
unsigned int reserved[256]
```

Reserved for future use.

5.10.2.5 width

```
unsigned int width
```

Width of source image.

The documentation for this struct was generated from the following file:

- `include/spinc/SpinnakerDefsC.h`

5.11 spinJPEGOption Struct Reference

Options for saving JPEG images.

Data Fields

- `bool8_t progressive`
Whether to save as a progressive JPEG file.
- unsigned int `quality`
JPEG image quality in range (0-100).
- unsigned int `reserved` [16]
Reserved for future use.

5.11.1 Detailed Description

Options for saving JPEG images.

Used in saving PPM images with a call to `spinImageSaveJpeg()`.

5.11.2 Field Documentation

5.11.2.1 progressive

`bool8_t progressive`

Whether to save as a progressive JPEG file.

5.11.2.2 quality

`unsigned int quality`

JPEG image quality in range (0-100).

- 100 - Superb quality.
- 75 - Good quality.
- 50 - Normal quality.
- 10 - Poor quality.

5.11.2.3 reserved

```
unsigned int reserved[16]
```

Reserved for future use.

The documentation for this struct was generated from the following file:

- include/spinc/[SpinnakerDefsC.h](#)

5.12 spinJPG2Option Struct Reference

Options for saving JPEG 2000 images.

Data Fields

- unsigned int [quality](#)
JPEG saving quality in range (1-512).
- unsigned int [reserved](#) [16]
Reserved for future use.

5.12.1 Detailed Description

Options for saving JPEG 2000 images.

Used in saving PPM images with a call to [spinImageSaveJpg2\(\)](#).

5.12.2 Field Documentation

5.12.2.1 quality

```
unsigned int quality
```

JPEG saving quality in range (1-512).

5.12.2.2 reserved

```
unsigned int reserved[16]
```

Reserved for future use.

The documentation for this struct was generated from the following file:

- include/spinc/[SpinnakerDefsC.h](#)

5.13 spinLibraryVersion Struct Reference

Provides easier access to the current version of Spinnaker.

Data Fields

- unsigned int [major](#)
Major version of the library.
- unsigned int [minor](#)
Minor version of the library.
- unsigned int [type](#)
Version type of the library.
- unsigned int [build](#)
Build number of the library.

5.13.1 Detailed Description

Provides easier access to the current version of Spinnaker.

5.13.2 Field Documentation

5.13.2.1 build

```
unsigned int build
```

Build number of the library.

5.13.2.2 major

```
unsigned int major
```

Major version of the library.

5.13.2.3 minor

```
unsigned int minor
```

Minor version of the library.

5.13.2.4 type

`unsigned int type`

Version type of the library.

The documentation for this struct was generated from the following file:

- `include/spinc/SpinnakerDefsC.h`

5.14 spinMJPGOption Struct Reference

Options for saving MJPG videos.

Data Fields

- float `frameRate`
Frame rate of the stream.
- unsigned int `quality`
Image quality (1-100)
- unsigned int `reserved` [256]

5.14.1 Detailed Description

Options for saving MJPG videos.

Used in saving MJPG videos with a call to `spinAVIRecorderOpenMJPG()`.

5.14.2 Field Documentation

5.14.2.1 frameRate

`float frameRate`

Frame rate of the stream.

5.14.2.2 quality

`unsigned int quality`

Image quality (1-100)

5.14.2.3 reserved

```
unsigned int reserved[256]
```

The documentation for this struct was generated from the following file:

- [include/spinc/SpinnakerDefsC.h](#)

5.15 spinPGMOption Struct Reference

Options for saving PGM images.

Data Fields

- [bool8_t binaryFile](#)
Whether to save the PPM as a binary file.
- unsigned int [reserved](#) [16]
Reserved for future use.

5.15.1 Detailed Description

Options for saving PGM images.

5.15.2 Field Documentation

5.15.2.1 binaryFile

```
bool8_t binaryFile
```

Whether to save the PPM as a binary file.

5.15.2.2 reserved

```
unsigned int reserved[16]
```

Reserved for future use.

The documentation for this struct was generated from the following file:

- [include/spinc/SpinnakerDefsC.h](#)

5.16 spinPNGOption Struct Reference

Options for saving PNG images.

Data Fields

- [bool8_t interlaced](#)
Whether to save the PNG as interlaced.
- unsigned int [compressionLevel](#)
Compression level (0-9).
- unsigned int [reserved](#) [16]
Reserved for future use.

5.16.1 Detailed Description

Options for saving PNG images.

Used in saving PNG images with a call to [spinImageSavePng\(\)](#).

5.16.2 Field Documentation

5.16.2.1 compressionLevel

```
unsigned int compressionLevel
```

Compression level (0-9).

0 is no compression, 9 is best compression.

5.16.2.2 interlaced

```
bool8_t interlaced
```

Whether to save the PNG as interlaced.

5.16.2.3 reserved

```
unsigned int reserved[16]
```

Reserved for future use.

The documentation for this struct was generated from the following file:

- include/spinc/[SpinnakerDefsC.h](#)

5.17 spinPPMOption Struct Reference

Options for saving PPM images.

Data Fields

- `bool8_t binaryFile`
Whether to save the PPM as a binary file.
- unsigned int `reserved` [16]
Reserved for future use.

5.17.1 Detailed Description

Options for saving PPM images.

Used in saving PPM images with a call to `spinImageSavePpm()`.

5.17.2 Field Documentation

5.17.2.1 binaryFile

`bool8_t binaryFile`

Whether to save the PPM as a binary file.

5.17.2.2 reserved

`unsigned int reserved[16]`

Reserved for future use.

The documentation for this struct was generated from the following file:

- `include/spinc/SpinnakerDefsC.h`

5.18 spinTIFFOption Struct Reference

Options for saving TIFF images.

Data Fields

- [spinCompressionMethod](#) *compression*
Compression method to use for encoding TIFF images.
- unsigned int [reserved](#) [16]
Reserved for future use.

5.18.1 Detailed Description

Options for saving TIFF images.

Used in saving PPM images with a call to [spinImageSaveTiff\(\)](#).

5.18.2 Field Documentation

5.18.2.1 [compression](#)

[spinCompressionMethod](#) *compression*

Compression method to use for encoding TIFF images.

5.18.2.2 [reserved](#)

```
unsigned int reserved[16]
```

Reserved for future use.

The documentation for this struct was generated from the following file:


- include/spinc/[SpinnakerDefsC.h](#)

Chapter 6

File Documentation

6.1 include/spinc/CameraDefsC.h File Reference

This graph shows which files directly or indirectly include this file:



Enumerations

- enum `spinLUTSelectorEnums` {
 `LUTSelector_LUT1`,
 `NUM_LUTSELECTOR` }

The enum definitions for camera nodes.

- enum `spinExposureModeEnums` {
 `ExposureMode_Timed`,
 `ExposureMode_TriggerWidth`,
 `NUM_EXPOSUREMODE` }
- enum `spinAcquisitionModeEnums` {
 `AcquisitionMode_Continuous`,
 `AcquisitionMode_SingleFrame`,
 `AcquisitionMode_MultiFrame`,
 `NUM_ACQUISITIONMODE` }

- enum `spinTriggerSourceEnums` {
 `TriggerSource_Software`,
 `TriggerSource_Line0`,
 `TriggerSource_Line1`,
 `TriggerSource_Line2`,
 `TriggerSource_Line3`,
 `TriggerSource_UserOutput0`,
 `TriggerSource_UserOutput1`,
 `TriggerSource_UserOutput2`,
 `TriggerSource_UserOutput3`,
 `TriggerSource_Counter0Start`,
 `TriggerSource_Counter1Start`,
 `TriggerSource_Counter0End`,
 `TriggerSource_Counter1End`,
 `TriggerSource_LogicBlock0`,
 `TriggerSource_LogicBlock1`,
 `TriggerSource_Action0`,
 `NUM_TRIGGERSOURCE` }
- enum `spinTriggerActivationEnums` {
 `TriggerActivation_LevelLow`,
 `TriggerActivation_LevelHigh`,
 `TriggerActivation_FallingEdge`,
 `TriggerActivation_RisingEdge`,
 `TriggerActivation_AnyEdge`,
 `NUM_TRIGGERACTIVATION` }
- enum `spinSensorShutterModeEnums` {
 `SensorShutterMode_Global`,
 `SensorShutterMode_Rolling`,
 `SensorShutterMode_GlobalReset`,
 `NUM_SENSORSHUTTERMODE` }
- enum `spinTriggerModeEnums` {
 `TriggerMode_Off`,
 `TriggerMode_On`,
 `NUM_TRIGGERMODE` }
- enum `spinTriggerOverlapEnums` {
 `TriggerOverlap_Off`,
 `TriggerOverlap_ReadOut`,
 `TriggerOverlap_PreviousFrame`,
 `NUM_TRIGGEROVERLAP` }
- enum `spinTriggerSelectorEnums` {
 `TriggerSelector_AcquisitionStart`,
 `TriggerSelector_FrameStart`,
 `TriggerSelector_FrameBurstStart`,
 `NUM_TRIGGERSELECTOR` }
- enum `spinExposureAutoEnums` {
 `ExposureAuto_Off`,
 `ExposureAuto_Once`,
 `ExposureAuto_Continuous`,
 `NUM_EXPOSUREAUTO` }
- enum `spinEventSelectorEnums` {
 `EventSelector_Error`,
 `EventSelector_ExposureEnd`,
 `EventSelector_SerialPortReceive`,
 `NUM_EVENTSELECTOR` }
- enum `spinEventNotificationEnums` {
 `EventNotification_On`,
 `EventNotification_Off`,
 `NUM_EVENTNOTIFICATION` }

- enum `spinLogicBlockSelectorEnums` {
 `LogicBlockSelector_LogicBlock0`,
 `LogicBlockSelector_LogicBlock1`,
 `NUM_LOGICBLOCKSELECTOR` }
- enum `spinLogicBlockLUTInputActivationEnums` {
 `LogicBlockLUTInputActivation_LevelLow`,
 `LogicBlockLUTInputActivation_LevelHigh`,
 `LogicBlockLUTInputActivation_FallingEdge`,
 `LogicBlockLUTInputActivation_RisingEdge`,
 `LogicBlockLUTInputActivation_AnyEdge`,
 `NUM_LOGICBLOCKLUTINPUTACTIVATION` }
- enum `spinLogicBlockLUTInputSelectorEnums` {
 `LogicBlockLUTInputSelector_Input0`,
 `LogicBlockLUTInputSelector_Input1`,
 `LogicBlockLUTInputSelector_Input2`,
 `LogicBlockLUTInputSelector_Input3`,
 `NUM_LOGICBLOCKLUTINPUTSELECTOR` }
- enum `spinLogicBlockLUTInputSourceEnums` {
 `LogicBlockLUTInputSource_Zero`,
 `LogicBlockLUTInputSource_Line0`,
 `LogicBlockLUTInputSource_Line1`,
 `LogicBlockLUTInputSource_Line2`,
 `LogicBlockLUTInputSource_Line3`,
 `LogicBlockLUTInputSource_UserOutput0`,
 `LogicBlockLUTInputSource_UserOutput1`,
 `LogicBlockLUTInputSource_UserOutput2`,
 `LogicBlockLUTInputSource_UserOutput3`,
 `LogicBlockLUTInputSource_Counter0Start`,
 `LogicBlockLUTInputSource_Counter1Start`,
 `LogicBlockLUTInputSource_Counter0End`,
 `LogicBlockLUTInputSource_Counter1End`,
 `LogicBlockLUTInputSource_LogicBlock0`,
 `LogicBlockLUTInputSource_LogicBlock1`,
 `LogicBlockLUTInputSource_ExposureStart`,
 `LogicBlockLUTInputSource_ExposureEnd`,
 `LogicBlockLUTInputSource_FrameTriggerWait`,
 `LogicBlockLUTInputSource_AcquisitionActive`,
 `NUM_LOGICBLOCKLUTINPUTSOURCE` }
- enum `spinLogicBlockLUTSelectorEnums` {
 `LogicBlockLUTSelector_Value`,
 `LogicBlockLUTSelector_Enable`,
 `NUM_LOGICBLOCKLUTSELECTOR` }
- enum `spinColorTransformationSelectorEnums` {
 `ColorTransformationSelector_RGBtoRGB`,
 `ColorTransformationSelector_RGBtoYUV`,
 `NUM_COLORTRANSFORMATIONSELECTOR` }
- enum `spinRgbTransformLightSourceEnums` {
 `RgbTransformLightSource_General`,
 `RgbTransformLightSource_Tungsten2800K`,
 `RgbTransformLightSource_WarmFluorescent3000K`,
 `RgbTransformLightSource_CoolFluorescent4000K`,
 `RgbTransformLightSource_Daylight5000K`,
 `RgbTransformLightSource_Cloudy6500K`,
 `RgbTransformLightSource_Shade8000K`,
 `RgbTransformLightSource_Custom`,
 `NUM_RGBTRANSFORMLIGHTSOURCE` }
- enum `spinColorTransformationValueSelectorEnums` {
 `ColorTransformationValueSelector_Gain00`,

```

ColorTransformationValueSelector_Gain01,
ColorTransformationValueSelector_Gain02,
ColorTransformationValueSelector_Gain10,
ColorTransformationValueSelector_Gain11,
ColorTransformationValueSelector_Gain12,
ColorTransformationValueSelector_Gain20,
ColorTransformationValueSelector_Gain21,
ColorTransformationValueSelector_Gain22,
ColorTransformationValueSelector_Offset0,
ColorTransformationValueSelector_Offset1,
ColorTransformationValueSelector_Offset2,
NUM_COLORTRANSFORMATIONVALUESELECTOR }

• enum spinDeviceRegistersEndiannessEnums {
    DeviceRegistersEndianness_Little,
    DeviceRegistersEndianness_Big,
    NUM_DEVICEREGISTERSENDIANNES }

• enum spinDeviceScanTypeEnums {
    DeviceScanType_Areascan,
    NUM_DEVICESCANTYPE }

• enum spinDeviceCharacterSetEnums {
    DeviceCharacterSet_UTF8,
    DeviceCharacterSet_ASCII,
    NUM_DEVICECHARACTERSET }

• enum spinDeviceTLTypeEnums {
    DeviceTLType_GigEVision,
    DeviceTLType_CameraLink,
    DeviceTLType_CameraLinkHS,
    DeviceTLType_CoaXPress,
    DeviceTLType_USB3Vision,
    DeviceTLType_Custom,
    NUM_DEVICETLTYPE }

• enum spinDevicePowerSupplySelectorEnums {
    DevicePowerSupplySelector_External,
    NUM_DEVICEPOWERSUPPLYSELECTOR }

• enum spinDeviceTemperatureSelectorEnums {
    DeviceTemperatureSelector_Sensor,
    NUM_DEVICETEMPERATURESELECTOR }

• enum spinDeviceIndicatorModeEnums {
    DeviceIndicatorMode_Inactive,
    DeviceIndicatorMode_Active,
    DeviceIndicatorMode_ErrorStatus,
    NUM_DEVICEINDICATORMODE }

• enum spinAutoExposureControlPriorityEnums {
    AutoExposureControlPriority_Gain,
    AutoExposureControlPriority_ExposureTime,
    NUM_AUTOEXPOSURECONTROLPRIORITY }

• enum spinAutoExposureMeteringModeEnums {
    AutoExposureMeteringMode_Average,
    AutoExposureMeteringMode_Spot,
    AutoExposureMeteringMode_Partial,
    AutoExposureMeteringMode_CenterWeighted,
    AutoExposureMeteringMode_HistogramPeak,
    NUM_AUTOEXPOSUREMETERINGMODE }

• enum spinBalanceWhiteAutoProfileEnums {
    BalanceWhiteAutoProfile_Indoor,
    BalanceWhiteAutoProfile_Outdoor,
    NUM_BALANCEWHITEAUTOPROFILE }

```

- enum `spinAutoAlgorithmSelectorEnums` {
`AutoAlgorithmSelector_Awb,`
`AutoAlgorithmSelector_Ae,`
`NUM_AUTOALGORITHMSELECTOR` }
- enum `spinAutoExposureTargetGreyValueAutoEnums` {
`AutoExposureTargetGreyValueAuto_Off,`
`AutoExposureTargetGreyValueAuto_Continuous,`
`NUM_AUTOEXPOSURETARGETGREYVALUEAUTO` }
- enum `spinAutoExposureLightingModeEnums` {
`AutoExposureLightingMode_AutoDetect,`
`AutoExposureLightingMode_Backlight,`
`AutoExposureLightingMode_Frontlight,`
`AutoExposureLightingMode_Normal,`
`NUM_AUTOEXPOSURELIGHTINGMODE` }
- enum `spinGevIEEE1588StatusEnums` {
`GevIEEE1588Status_Initializing,`
`GevIEEE1588Status_Faulty,`
`GevIEEE1588Status_Disabled,`
`GevIEEE1588Status_Listening,`
`GevIEEE1588Status_PreMaster,`
`GevIEEE1588Status_Master,`
`GevIEEE1588Status_Passive,`
`GevIEEE1588Status_Uncalibrated,`
`GevIEEE1588Status_Slave,`
`NUM_GEVIEEE1588STATUS` }
- enum `spinGevIEEE1588ModeEnums` {
`GevIEEE1588Mode_Auto,`
`GevIEEE1588Mode_SlaveOnly,`
`NUM_GEVIEEE1588MODE` }
- enum `spinGevIEEE1588ClockAccuracyEnums` {
`GevIEEE1588ClockAccuracy_Unknown,`
`NUM_GEVIEEE1588CLOCKACCURACY` }
- enum `spinGevCCPEnums` {
`GevCCP_OpenAccess,`
`GevCCP_ExclusiveAccess,`
`GevCCP_ControlAccess,`
`NUM_GEVCCP` }
- enum `spinGevSupportedOptionSelectorEnums` {
`GevSupportedOptionSelector_UserDefinedName,`
`GevSupportedOptionSelector_SerialNumber,`
`GevSupportedOptionSelector_HeartbeatDisable,`
`GevSupportedOptionSelector_LinkSpeed,`
`GevSupportedOptionSelector_CCPApplicationSocket,`
`GevSupportedOptionSelector_ManifestTable,`
`GevSupportedOptionSelector_TestData,`
`GevSupportedOptionSelector_DiscoveryAckDelay,`
`GevSupportedOptionSelector_DiscoveryAckDelayWritable,`
`GevSupportedOptionSelector_ExtendedStatusCodes,`
`GevSupportedOptionSelector_Action,`
`GevSupportedOptionSelector_PendingAck,`
`GevSupportedOptionSelector_EventData,`
`GevSupportedOptionSelector_Event,`
`GevSupportedOptionSelector_PacketResend,`
`GevSupportedOptionSelector_WriteMem,`
`GevSupportedOptionSelector_CommandsConcatenation,`
`GevSupportedOptionSelector_IPConfigurationLLA,`
`GevSupportedOptionSelector_IPConfigurationDHCP,`
`GevSupportedOptionSelector_IPConfigurationPersistentIP,`

```
GevSupportedOptionSelector_StreamChannelSourceSocket,  
GevSupportedOptionSelector_MessageChannelSourceSocket,  
NUM_GEVSUPPORTEDOPTIONSELECTOR }  
  
• enum spinBlackLevelSelectorEnums {  
    BlackLevelSelector_All,  
    BlackLevelSelector_Analog,  
    BlackLevelSelector_Digital,  
    NUM_BLACKLEVELSELECTOR }  
  
• enum spinBalanceWhiteAutoEnums {  
    BalanceWhiteAuto_Off,  
    BalanceWhiteAuto_Once,  
    BalanceWhiteAuto_Continuous,  
    NUM_BALANCEWHITEAUTO }  
  
• enum spinGainAutoEnums {  
    GainAuto_Off,  
    GainAuto_Once,  
    GainAuto_Continuous,  
    NUM_GAINAUTO }  
  
• enum spinBalanceRatioSelectorEnums {  
    BalanceRatioSelector_Red,  
    BalanceRatioSelector_Blue,  
    NUM_BALANCERATIOSELECTOR }  
  
• enum spinGainSelectorEnums {  
    GainSelector_All,  
    NUM_GAINSELECTOR }  
  
• enum spinDefectCorrectionModeEnums {  
    DefectCorrectionMode_Average,  
    DefectCorrectionMode_Highlight,  
    DefectCorrectionMode_Zero,  
    NUM_DEFECTCORRECTIONMODE }  
  
• enum spinUserSetSelectorEnums {  
    UserSetSelector_Default,  
    UserSetSelector_UserSet0,  
    UserSetSelector_UserSet1,  
    NUM_USERSETSELECTOR }  
  
• enum spinUserSetDefaultEnums {  
    UserSetDefault_Default,  
    UserSetDefault_UserSet0,  
    UserSetDefault_UserSet1,  
    NUM_USERSETDEFAULT }  
  
• enum spinSerialPortBaudRateEnums {  
    SerialPortBaudRate_Baud300,  
    SerialPortBaudRate_Baud600,  
    SerialPortBaudRate_Baud1200,  
    SerialPortBaudRate_Baud2400,  
    SerialPortBaudRate_Baud4800,  
    SerialPortBaudRate_Baud9600,  
    SerialPortBaudRate_Baud14400,  
    SerialPortBaudRate_Baud19200,  
    SerialPortBaudRate_Baud38400,  
    SerialPortBaudRate_Baud57600,  
    SerialPortBaudRate_Baud115200,  
    SerialPortBaudRate_Baud230400,  
    SerialPortBaudRate_Baud460800,  
    SerialPortBaudRate_Baud921600,  
    NUM_SERIALPORTBAUDRATE }  
  
• enum spinSerialPortParityEnums {  
    SerialPortParity_None,
```



```
SerialPortParity_Odd,  
SerialPortParity_Even,  
SerialPortParity_Mark,  
SerialPortParity_Space,  
NUM_SERIALPORTPARITY }  
• enum spinSerialPortSelectorEnums {  
    SerialPortSelector_SerialPort0,  
    NUM_SERIALPORTSELECTOR }  
• enum spinSerialPortStopBitsEnums {  
    SerialPortStopBits_Bits1,  
    SerialPortStopBits_Bits1AndAHalf,  
    SerialPortStopBits_Bits2,  
    NUM_SERIALPORTSTOPBITS }  
• enum spinSerialPortSourceEnums {  
    SerialPortSource_Line0,  
    SerialPortSource_Line1,  
    SerialPortSource_Line2,  
    SerialPortSource_Line3,  
    SerialPortSource_Off,  
    NUM_SERIALPORTSOURCE }  
• enum spinSequencerModeEnums {  
    SequencerMode_Off,  
    SequencerMode_On,  
    NUM_SEQUENCERMODE }  
• enum spinSequencerConfigurationValidEnums {  
    SequencerConfigurationValid_No,  
    SequencerConfigurationValid_Yes,  
    NUM_SEQUENCERCONFIGURATIONVALID }  
• enum spinSequencerSetValidEnums {  
    SequencerSetValid_No,  
    SequencerSetValid_Yes,  
    NUM_SEQUENCERSETVALID }  
• enum spinSequencerTriggerActivationEnums {  
    SequencerTriggerActivation_RisingEdge,  
    SequencerTriggerActivation_FallingEdge,  
    SequencerTriggerActivation_AnyEdge,  
    SequencerTriggerActivation_LevelHigh,  
    SequencerTriggerActivation_LevelLow,  
    NUM_SEQUENCERTRIGGERACTIVATION }  
• enum spinSequencerConfigurationModeEnums {  
    SequencerConfigurationMode_Off,  
    SequencerConfigurationMode_On,  
    NUM_SEQUENCERCONFIGURATIONMODE }  
• enum spinSequencerTriggerSourceEnums {  
    SequencerTriggerSource_Off,  
    SequencerTriggerSource_FrameStart,  
    NUM_SEQUENCERTRIGGERSOURCE }  
• enum spinTransferQueueModeEnums {  
    TransferQueueMode_FirstInFirstOut,  
    NUM_TRANSFERQUEUEMODE }  
• enum spinTransferOperationModeEnums {  
    TransferOperationMode_Continuous,  
    TransferOperationMode_MultiBlock,  
    NUM_TRANSFEROPERATIONMODE }  
• enum spinTransferControlModeEnums {  
    TransferControlMode_Basic,  
    TransferControlMode_Automatic,
```

```

TransferControlMode_UserControlled,
NUM_TRANSFERCONTROLMODE }

• enum spinChunkGainSelectorEnums {
    ChunkGainSelector_All,
    ChunkGainSelector_Red,
    ChunkGainSelector_Green,
    ChunkGainSelector_Blue,
    NUM_CHUNKGAINSELECTOR }

• enum spinChunkSelectorEnums {
    ChunkSelector_Image,
    ChunkSelector_CRC,
    ChunkSelector_FrameID,
    ChunkSelector_OffsetX,
    ChunkSelector_OffsetY,
    ChunkSelector_Width,
    ChunkSelector_Height,
    ChunkSelector_ExposureTime,
    ChunkSelector_Gain,
    ChunkSelector_BlackLevel,
    ChunkSelector_PixelFormat,
    ChunkSelector_Timestamp,
    ChunkSelector_SequencerSetActive,
    ChunkSelector_SerialData,
    ChunkSelector_ExposureEndLineStatusAll,
    NUM_CHUNKSELECTOR }

• enum spinChunkBlackLevelSelectorEnums {
    ChunkBlackLevelSelector_All,
    NUM_CHUNKBLACKLEVELSELECTOR }

• enum spinChunkPixelFormatEnums {
    ChunkPixelFormat_Mono8,
    ChunkPixelFormat_Mono12Packed,
    ChunkPixelFormat_Mono16,
    ChunkPixelFormat_RGB8Packed,
    ChunkPixelFormat_YUV422Packed,
    ChunkPixelFormat_BayerGR8,
    ChunkPixelFormat_BayerRG8,
    ChunkPixelFormat_BayerGB8,
    ChunkPixelFormat_BayerBG8,
    ChunkPixelFormat_YCbCr601_422_8_CbYCrY,
    NUM_CHUNKPIXELFORMAT }

• enum spinFileOperationStatusEnums {
    FileOperationStatus_Success,
    FileOperationStatus_Failure,
    FileOperationStatus_Overflow,
    NUM_FILEOPERATIONSTATUS }

• enum spinFileOpenModeEnums {
    FileOpenMode_Read,
    FileOpenMode_Write,
    FileOpenMode_ReadWrite,
    NUM_FILEOPENMODE }

• enum spinFileOperationSelectorEnums {
    FileOperationSelector_Open,
    FileOperationSelector_Close,
    FileOperationSelector_Read,
    FileOperationSelector_Write,
    FileOperationSelector_Delete,
    NUM_FILEOPERATIONSELECTOR }

```

- enum `spinFileSelectorEnums` {
 FileSelector_UserSetDefault,
 FileSelector_UserSet0,
 FileSelector_UserSet1,
 FileSelector_UserFile1,
 FileSelector_SerialPort0,
 NUM_FILESELECTOR }
- enum `spinBinningSelectorEnums` {
 BinningSelector_All,
 BinningSelector_Sensor,
 BinningSelector_ISP,
 NUM_BINNINGSELECTOR }
- enum `spinTestPatternGeneratorSelectorEnums` {
 TestPatternGeneratorSelector_Sensor,
 TestPatternGeneratorSelector_PipelineStart,
 NUM_TESTPATTERNGENERATORSELECTOR }
- enum `spinTestPatternEnums` {
 TestPattern_Off,
 TestPattern_Increment,
 TestPattern_SensorTestPattern,
 NUM_TESTPATTERN }
- enum `spinPixelColorFilterEnums` {
 PixelColorFilter_None,
 PixelColorFilter_BayerRG,
 PixelColorFilter_BayerGB,
 PixelColorFilter_BayerGR,
 PixelColorFilter_BayerBG,
 NUM_PIXELCOLORFILTER }
- enum `spinAdcBitDepthEnums` {
 AdcBitDepth_Bit8,
 AdcBitDepth_Bit10,
 AdcBitDepth_Bit12,
 AdcBitDepth_Bit14,
 NUM_ADCBITDEPTH }
- enum `spinDecimationHorizontalModeEnums` {
 DecimationHorizontalMode_Discard,
 NUM_DECIMATIONHORIZONTALMODE }
- enum `spinBinningVerticalModeEnums` {
 BinningVerticalMode_Sum,
 BinningVerticalMode_Average,
 NUM_BINNINGVERTICALMODE }
- enum `spinPixelSizeEnums` {
 PixelSize_Bpp1,
 PixelSize_Bpp2,
 PixelSize_Bpp4,
 PixelSize_Bpp8,
 PixelSize_Bpp10,
 PixelSize_Bpp12,
 PixelSize_Bpp14,
 PixelSize_Bpp16,
 PixelSize_Bpp20,
 PixelSize_Bpp24,
 PixelSize_Bpp30,
 PixelSize_Bpp32,
 PixelSize_Bpp36,
 PixelSize_Bpp48,
 PixelSize_Bpp64,

```
PixelSize_Bpp96,  
NUM_PIXELSIZE }  
  
• enum spinDecimationSelectorEnums {  
    DecimationSelector_All,  
    DecimationSelector_Sensor,  
    NUM_DECIMATIONSELECTOR }  
  
• enum spinImageCompressionModeEnums {  
    ImageCompressionMode_Off,  
    ImageCompressionMode_Lossless,  
    NUM_IMAGECOMPRESSIONMODE }  
  
• enum spinBinningHorizontalModeEnums {  
    BinningHorizontalMode_Sum,  
    BinningHorizontalMode_Average,  
    NUM_BINNINGHORIZONTALMODE }  
  
• enum spinPixelFormatEnums {  
    PixelFormat_Mono8,  
    PixelFormat_Mono16,  
    PixelFormat_RGB8Packed,  
    PixelFormat_BayerGR8,  
    PixelFormat_BayerRG8,  
    PixelFormat_BayerGB8,  
    PixelFormat_BayerBG8,  
    PixelFormat_BayerGR16,  
    PixelFormat_BayerRG16,  
    PixelFormat_BayerGB16,  
    PixelFormat_BayerBG16,  
    PixelFormat_Mono12Packed,  
    PixelFormat_BayerGR12Packed,  
    PixelFormat_BayerRG12Packed,  
    PixelFormat_BayerGB12Packed,  
    PixelFormat_BayerBG12Packed,  
    PixelFormat_YUV411Packed,  
    PixelFormat_YUV422Packed,  
    PixelFormat_YUV444Packed,  
    PixelFormat_Mono12p,  
    PixelFormat_BayerGR12p,  
    PixelFormat_BayerRG12p,  
    PixelFormat_BayerGB12p,  
    PixelFormat_BayerBG12p,  
    PixelFormat_YCbCr8,  
    PixelFormat_YCbCr422_8,  
    PixelFormat_YCbCr411_8,  
    PixelFormat_BGR8,  
    PixelFormat_BGRa8,  
    PixelFormat_Mono10Packed,  
    PixelFormat_BayerGR10Packed,  
    PixelFormat_BayerRG10Packed,  
    PixelFormat_BayerGB10Packed,  
    PixelFormat_BayerBG10Packed,  
    PixelFormat_Mono10p,  
    PixelFormat_BayerGR10p,  
    PixelFormat_BayerRG10p,  
    PixelFormat_BayerGB10p,  
    PixelFormat_BayerBG10p,  
    PixelFormat_Mono1p,  
    PixelFormat_Mono2p,  
    PixelFormat_Mono4p,  
    PixelFormat_Mono8s,
```

PixelFormat_Mono10,
PixelFormat_Mono12,
PixelFormat_Mono14,
PixelFormat_Mono16s,
PixelFormat_Mono32f,
PixelFormat_BayerBG10,
PixelFormat_BayerBG12,
PixelFormat_BayerGB10,
PixelFormat_BayerGB12,
PixelFormat_BayerGR10,
PixelFormat_BayerGR12,
PixelFormat_BayerRG10,
PixelFormat_BayerRG12,
PixelFormat_RGBa8,
PixelFormat_RGBa10,
PixelFormat_RGBa10p,
PixelFormat_RGBa12,
PixelFormat_RGBa12p,
PixelFormat_RGBa14,
PixelFormat_RGBa16,
PixelFormat_RGB8,
PixelFormat_RGB8_Planar,
PixelFormat_RGB10,
PixelFormat_RGB10_Planar,
PixelFormat_RGB10p,
PixelFormat_RGB10p32,
PixelFormat_RGB12,
PixelFormat_RGB12_Planar,
PixelFormat_RGB12p,
PixelFormat_RGB14,
PixelFormat_RGB16,
PixelFormat_RGB16s,
PixelFormat_RGB32f,
PixelFormat_RGB16_Planar,
PixelFormat_RGB565p,
PixelFormat_BGRa10,
PixelFormat_BGRa10p,
PixelFormat_BGRa12,
PixelFormat_BGRa12p,
PixelFormat_BGRa14,
PixelFormat_BGRa16,
PixelFormat_RGBa32f,
PixelFormat_BGR10,
PixelFormat_BGR10p,
PixelFormat_BGR12,
PixelFormat_BGR12p,
PixelFormat_BGR14,
PixelFormat_BGR16,
PixelFormat_BGR565p,
PixelFormat_R8,
PixelFormat_R10,
PixelFormat_R12,
PixelFormat_R16,
PixelFormat_G8,
PixelFormat_G10,
PixelFormat_G12,
PixelFormat_G16,
PixelFormat_B8,

PixelFormat_B10,
PixelFormat_B12,
PixelFormat_B16,
PixelFormat_Coord3D_ABC8,
PixelFormat_Coord3D_ABC8_Planar,
PixelFormat_Coord3D_ABC10p,
PixelFormat_Coord3D_ABC10p_Planar,
PixelFormat_Coord3D_ABC12p,
PixelFormat_Coord3D_ABC12p_Planar,
PixelFormat_Coord3D_ABC16,
PixelFormat_Coord3D_ABC16_Planar,
PixelFormat_Coord3D_ABC32f,
PixelFormat_Coord3D_ABC32f_Planar,
PixelFormat_Coord3D_AC8,
PixelFormat_Coord3D_AC8_Planar,
PixelFormat_Coord3D_AC10p,
PixelFormat_Coord3D_AC10p_Planar,
PixelFormat_Coord3D_AC12p,
PixelFormat_Coord3D_AC12p_Planar,
PixelFormat_Coord3D_AC16,
PixelFormat_Coord3D_AC16_Planar,
PixelFormat_Coord3D_AC32f,
PixelFormat_Coord3D_AC32f_Planar,
PixelFormat_Coord3D_A8,
PixelFormat_Coord3D_A10p,
PixelFormat_Coord3D_A12p,
PixelFormat_Coord3D_A16,
PixelFormat_Coord3D_A32f,
PixelFormat_Coord3D_B8,
PixelFormat_Coord3D_B10p,
PixelFormat_Coord3D_B12p,
PixelFormat_Coord3D_B16,
PixelFormat_Coord3D_B32f,
PixelFormat_Coord3D_C8,
PixelFormat_Coord3D_C10p,
PixelFormat_Coord3D_C12p,
PixelFormat_Coord3D_C16,
PixelFormat_Coord3D_C32f,
PixelFormat_Confidence1,
PixelFormat_Confidence1p,
PixelFormat_Confidence8,
PixelFormat_Confidence16,
PixelFormat_Confidence32f,
PixelFormat_BiColorBGRG8,
PixelFormat_BiColorBGRG10,
PixelFormat_BiColorBGRG10p,
PixelFormat_BiColorBGRG12,
PixelFormat_BiColorBGRG12p,
PixelFormat_BiColorRGBG8,
PixelFormat_BiColorRGBG10,
PixelFormat_BiColorRGBG10p,
PixelFormat_BiColorRGBG12,
PixelFormat_BiColorRGBG12p,
PixelFormat_SCF1WBWG8,
PixelFormat_SCF1WBWG10,
PixelFormat_SCF1WBWG10p,
PixelFormat_SCF1WBWG12,
PixelFormat_SCF1WBWG12p,

PixelFormat_SCF1WBWG14,
PixelFormat_SCF1WBWG16,
PixelFormat_SCF1WGWB8,
PixelFormat_SCF1WGWB10,
PixelFormat_SCF1WGWB10p,
PixelFormat_SCF1WGWB12,
PixelFormat_SCF1WGWB12p,
PixelFormat_SCF1WGWB14,
PixelFormat_SCF1WGWB16,
PixelFormat_SCF1WGWR8,
PixelFormat_SCF1WGWR10,
PixelFormat_SCF1WGWR10p,
PixelFormat_SCF1WGWR12,
PixelFormat_SCF1WGWR12p,
PixelFormat_SCF1WGWR14,
PixelFormat_SCF1WGWR16,
PixelFormat_SCF1WRWG8,
PixelFormat_SCF1WRWG10,
PixelFormat_SCF1WRWG10p,
PixelFormat_SCF1WRWG12,
PixelFormat_SCF1WRWG12p,
PixelFormat_SCF1WRWG14,
PixelFormat_SCF1WRWG16,
PixelFormat_YCbCr8_CbYCr,
PixelFormat_YCbCr10_CbYCr,
PixelFormat_YCbCr10p_CbYCr,
PixelFormat_YCbCr12_CbYCr,
PixelFormat_YCbCr12p_CbYCr,
PixelFormat_YCbCr411_8_CbYYCrYY,
PixelFormat_YCbCr422_8_CbYCrY,
PixelFormat_YCbCr422_10,
PixelFormat_YCbCr422_10_CbYCrY,
PixelFormat_YCbCr422_10p,
PixelFormat_YCbCr422_10p_CbYCrY,
PixelFormat_YCbCr422_12,
PixelFormat_YCbCr422_12_CbYCrY,
PixelFormat_YCbCr422_12p,
PixelFormat_YCbCr422_12p_CbYCrY,
PixelFormat_YCbCr601_8_CbYCr,
PixelFormat_YCbCr601_10_CbYCr,
PixelFormat_YCbCr601_10p_CbYCr,
PixelFormat_YCbCr601_12_CbYCr,
PixelFormat_YCbCr601_12p_CbYCr,
PixelFormat_YCbCr601_411_8_CbYYCrYY,
PixelFormat_YCbCr601_422_8,
PixelFormat_YCbCr601_422_8_CbYCrY,
PixelFormat_YCbCr601_422_10,
PixelFormat_YCbCr601_422_10_CbYCrY,
PixelFormat_YCbCr601_422_10p,
PixelFormat_YCbCr601_422_10p_CbYCrY,
PixelFormat_YCbCr601_422_12,
PixelFormat_YCbCr601_422_12_CbYCrY,
PixelFormat_YCbCr601_422_12p,
PixelFormat_YCbCr601_422_12p_CbYCrY,
PixelFormat_YCbCr709_8_CbYCr,
PixelFormat_YCbCr709_10_CbYCr,
PixelFormat_YCbCr709_10p_CbYCr,
PixelFormat_YCbCr709_12_CbYCr,

```

PixelFormat_YCbCr709_12p_CbYCr,
PixelFormat_YCbCr709_411_8_CbYYCrYY,
PixelFormat_YCbCr709_422_8,
PixelFormat_YCbCr709_422_8_CbYCrY,
PixelFormat_YCbCr709_422_10,
PixelFormat_YCbCr709_422_10_CbYCrY,
PixelFormat_YCbCr709_422_10p,
PixelFormat_YCbCr709_422_10p_CbYCrY,
PixelFormat_YCbCr709_422_12,
PixelFormat_YCbCr709_422_12_CbYCrY,
PixelFormat_YCbCr709_422_12p,
PixelFormat_YCbCr709_422_12p_CbYCrY,
PixelFormat_YUV8_UYV,
PixelFormat_YUV411_8_UYYVYY,
PixelFormat_YUV422_8,
PixelFormat_YUV422_8_UYVY,
PixelFormat_Polarized8,
PixelFormat_Polarized10p,
PixelFormat_Polarized12p,
PixelFormat_Polarized16,
PixelFormat_BayerRGPolarized8,
PixelFormat_BayerRGPolarized10p,
PixelFormat_BayerRGPolarized12p,
PixelFormat_BayerRGPolarized16,
PixelFormat_LLCMono8,
PixelFormat_LLCBayerRG8,
PixelFormat_JPEGMono8,
PixelFormat_JPEGColor8,
PixelFormat_Raw16,
PixelFormat_Raw8,
PixelFormat_R12_Jpeg,
PixelFormat_GR12_Jpeg,
PixelFormat_GB12_Jpeg,
PixelFormat_B12_Jpeg,
UNKNOWN_PIXELFORMAT,
NUM_PIXELFORMAT }

• enum spinDecimationVerticalModeEnums {
    DecimationVerticalMode_Discard,
    NUM_DECIMATIONVERTICALMODE }

• enum spinLineModeEnums {
    LineMode_Input,
    LineMode_Output,
    NUM_LINEMODE }

• enum spinLineSourceEnums {
    LineSource_Off,
    LineSource_Line0,
    LineSource_Line1,
    LineSource_Line2,
    LineSource_Line3,
    LineSource_UserOutput0,
    LineSource_UserOutput1,
    LineSource_UserOutput2,
    LineSource_UserOutput3,
    LineSource_Counter0Active,
    LineSource_Counter1Active,
    LineSource_LogicBlock0,
    LineSource_LogicBlock1,
    LineSource_ExposureActive,

```



```
LineSource_FrameTriggerWait,  
LineSource_SerialPort0,  
LineSource_PPSSignal,  
LineSource_AllPixel,  
LineSource_AnyPixel,  
NUM_LINESOURCE }  
• enum spinLineInputFilterSelectorEnums {  
    LineInputFilterSelector_Deglitch,  
    LineInputFilterSelector_Debounce,  
    NUM_LINEINPUTFILTERSELECTOR }  
• enum spinUserOutputSelectorEnums {  
    UserOutputSelector_UserOutput0,  
    UserOutputSelector_UserOutput1,  
    UserOutputSelector_UserOutput2,  
    UserOutputSelector_UserOutput3,  
    NUM_USEROUTPUTSELECTOR }  
• enum spinLineFormatEnums {  
    LineFormat_NoConnect,  
    LineFormat_TriState,  
    LineFormat_TTL,  
    LineFormat_LVDS,  
    LineFormat_RS422,  
    LineFormat_OptoCoupled,  
    LineFormat_OpenDrain,  
    NUM_LINEFORMAT }  
• enum spinLineSelectorEnums {  
    LineSelector_Line0,  
    LineSelector_Line1,  
    LineSelector_Line2,  
    LineSelector_Line3,  
    NUM_LINESELECTOR }  
• enum spinExposureActiveModeEnums {  
    ExposureActiveMode_Line1,  
    ExposureActiveMode_AnyPixels,  
    ExposureActiveMode_AllPixels,  
    NUM_EXPOSUREACTIVEMODE }  
• enum spinCounterTriggerActivationEnums {  
    CounterTriggerActivation_LevelLow,  
    CounterTriggerActivation_LevelHigh,  
    CounterTriggerActivation_FallingEdge,  
    CounterTriggerActivation_RisingEdge,  
    CounterTriggerActivation_AnyEdge,  
    NUM_COUNTERTRIGGERACTIVATION }  
• enum spinCounterSelectorEnums {  
    CounterSelector_Counter0,  
    CounterSelector_Counter1,  
    NUM_COUNTERSELECTOR }  
• enum spinCounterStatusEnums {  
    CounterStatus_CounterIdle,  
    CounterStatus_CounterTriggerWait,  
    CounterStatus_CounterActive,  
    CounterStatus_CounterCompleted,  
    CounterStatus_CounterOverflow,  
    NUM_COUNTERSTATUS }  
• enum spinCounterTriggerSourceEnums {  
    CounterTriggerSource_Off,  
    CounterTriggerSource_Line0,  
    CounterTriggerSource_Line1,
```

```

CounterTriggerSource_Line2,
CounterTriggerSource_Line3,
CounterTriggerSource_UserOutput0,
CounterTriggerSource_UserOutput1,
CounterTriggerSource_UserOutput2,
CounterTriggerSource_UserOutput3,
CounterTriggerSource_Counter0Start,
CounterTriggerSource_Counter1Start,
CounterTriggerSource_Counter0End,
CounterTriggerSource_Counter1End,
CounterTriggerSource_LogicBlock0,
CounterTriggerSource_LogicBlock1,
CounterTriggerSource_ExposureStart,
CounterTriggerSource_ExposureEnd,
CounterTriggerSource_FrameTriggerWait,
NUM_COUNTERTRIGGERSOURCE }

• enum spinCounterResetSourceEnums {
CounterResetSource_Off,
CounterResetSource_Line0,
CounterResetSource_Line1,
CounterResetSource_Line2,
CounterResetSource_Line3,
CounterResetSource_UserOutput0,
CounterResetSource_UserOutput1,
CounterResetSource_UserOutput2,
CounterResetSource_UserOutput3,
CounterResetSource_Counter0Start,
CounterResetSource_Counter1Start,
CounterResetSource_Counter0End,
CounterResetSource_Counter1End,
CounterResetSource_LogicBlock0,
CounterResetSource_LogicBlock1,
CounterResetSource_ExposureStart,
CounterResetSource_ExposureEnd,
CounterResetSource_FrameTriggerWait,
NUM_COUNTERRESETSOURCE }

• enum spinCounterEventSourceEnums {
CounterEventSource_Off,
CounterEventSource_MHzTick,
CounterEventSource_Line0,
CounterEventSource_Line1,
CounterEventSource_Line2,
CounterEventSource_Line3,
CounterEventSource_UserOutput0,
CounterEventSource_UserOutput1,
CounterEventSource_UserOutput2,
CounterEventSource_UserOutput3,
CounterEventSource_Counter0Start,
CounterEventSource_Counter1Start,
CounterEventSource_Counter0End,
CounterEventSource_Counter1End,
CounterEventSource_LogicBlock0,
CounterEventSource_LogicBlock1,
CounterEventSource_ExposureStart,
CounterEventSource_ExposureEnd,
CounterEventSource_FrameTriggerWait,
NUM_COUNTEREVENTSOURCE }

• enum spinCounterEventActivationEnums {

```

```

CounterEventActivation_LevelLow,
CounterEventActivation_LevelHigh,
CounterEventActivation_FallingEdge,
CounterEventActivation_RisingEdge,
CounterEventActivation_AnyEdge,
NUM_COUNTEREVENTACTIVATION }

• enum spinCounterResetActivationEnums {
CounterResetActivation_LevelLow,
CounterResetActivation_LevelHigh,
CounterResetActivation_FallingEdge,
CounterResetActivation_RisingEdge,
CounterResetActivation_AnyEdge,
NUM_COUNTERRESETACTIVATION }

• enum spinDeviceTypeEnums {
DeviceType_Transmitter,
DeviceType_Receiver,
DeviceType_Transceiver,
DeviceType_Peripheral,
NUM_DEVICETYPE }

• enum spinDeviceConnectionStatusEnums {
DeviceConnectionStatus_Active,
DeviceConnectionStatus_Inactive,
NUM_DEVICECONNECTIONSTATUS }

• enum spinDeviceLinkThroughputLimitModeEnums {
DeviceLinkThroughputLimitMode_On,
DeviceLinkThroughputLimitMode_Off,
NUM_DEVICELINKTHROUGHPUTLIMITMODE }

• enum spinDeviceLinkHeartbeatModeEnums {
DeviceLinkHeartbeatMode_On,
DeviceLinkHeartbeatMode_Off,
NUM_DEVICELINKHEARTBEATMODE }

• enum spinDeviceStreamChannelTypeEnums {
DeviceStreamChannelType_Transmitter,
DeviceStreamChannelType_Receiver,
NUM_DEVICESTREAMCHANNELTYPE }

• enum spinDeviceStreamChannelEndiannessEnums {
DeviceStreamChannelEndianness_Big,
DeviceStreamChannelEndianness_Little,
NUM_DEVICESTREAMCHANNELENDIANNESS }

• enum spinDeviceClockSelectorEnums {
DeviceClockSelector_Sensor,
DeviceClockSelector_SensorDigitization,
DeviceClockSelector_CameraLink,
NUM_DEVICECLOCKSELECTOR }

• enum spinDeviceSerialPortSelectorEnums {
DeviceSerialPortSelector_CameraLink,
NUM_DEVICESERIALPORTSELECTOR }

• enum spinDeviceSerialPortBaudRateEnums {
DeviceSerialPortBaudRate_Baud9600,
DeviceSerialPortBaudRate_Baud19200,
DeviceSerialPortBaudRate_Baud38400,
DeviceSerialPortBaudRate_Baud57600,
DeviceSerialPortBaudRate_Baud115200,
DeviceSerialPortBaudRate_Baud230400,
DeviceSerialPortBaudRate_Baud460800,
DeviceSerialPortBaudRate_Baud921600,
NUM_DEVICESERIALPORTBAUDRATE }

```

- enum `spinSensorTapsEnums` {
 `SensorTaps_One`,
 `SensorTaps_Two`,
 `SensorTaps_Three`,
 `SensorTaps_Four`,
 `SensorTaps_Eight`,
 `SensorTaps_Ten`,
 `NUM_SENSORTAPS` }
- enum `spinSensorDigitizationTapsEnums` {
 `SensorDigitizationTaps_One`,
 `SensorDigitizationTaps_Two`,
 `SensorDigitizationTaps_Three`,
 `SensorDigitizationTaps_Four`,
 `SensorDigitizationTaps_Eight`,
 `SensorDigitizationTaps_Ten`,
 `NUM_SENSORDIGITIZATIONTAPS` }
- enum `spinRegionSelectorEnums` {
 `RegionSelector_Region0`,
 `RegionSelector_Region1`,
 `RegionSelector_Region2`,
 `RegionSelector_All`,
 `NUM_REGIONSELECTOR` }
- enum `spinRegionModeEnums` {
 `RegionMode_Off`,
 `RegionMode_On`,
 `NUM_REGIONMODE` }
- enum `spinRegionDestinationEnums` {
 `RegionDestination_Stream0`,
 `RegionDestination_Stream1`,
 `RegionDestination_Stream2`,
 `NUM_REGIONDESTINATION` }
- enum `spinImageComponentSelectorEnums` {
 `ImageComponentSelector_Intensity`,
 `ImageComponentSelector_Color`,
 `ImageComponentSelector_Infrared`,
 `ImageComponentSelector_Ultraviolet`,
 `ImageComponentSelector_Range`,
 `ImageComponentSelector_Disparity`,
 `ImageComponentSelector_Confidence`,
 `ImageComponentSelector_Scatter`,
 `NUM_IMAGECOMPONENTSELECTOR` }
- enum `spinPixelFormatInfoSelectorEnums` {
 `PixelFormatInfoSelector_Mono1p`,
 `PixelFormatInfoSelector_Mono2p`,
 `PixelFormatInfoSelector_Mono4p`,
 `PixelFormatInfoSelector_Mono8`,
 `PixelFormatInfoSelector_Mono8s`,
 `PixelFormatInfoSelector_Mono10`,
 `PixelFormatInfoSelector_Mono10p`,
 `PixelFormatInfoSelector_Mono12`,
 `PixelFormatInfoSelector_Mono12p`,
 `PixelFormatInfoSelector_Mono14`,
 `PixelFormatInfoSelector_Mono16`,
 `PixelFormatInfoSelector_Mono16s`,
 `PixelFormatInfoSelector_Mono32f`,
 `PixelFormatInfoSelector_BayerBG8`,
 `PixelFormatInfoSelector_BayerBG10`,
 `PixelFormatInfoSelector_BayerBG10p`,

[PixelFormatInfoSelector_BayerBG12,](#)
[PixelFormatInfoSelector_BayerBG12p,](#)
[PixelFormatInfoSelector_BayerBG16,](#)
[PixelFormatInfoSelector_BayerGB8,](#)
[PixelFormatInfoSelector_BayerGB10,](#)
[PixelFormatInfoSelector_BayerGB10p,](#)
[PixelFormatInfoSelector_BayerGB12,](#)
[PixelFormatInfoSelector_BayerGB12p,](#)
[PixelFormatInfoSelector_BayerGB16,](#)
[PixelFormatInfoSelector_BayerGR8,](#)
[PixelFormatInfoSelector_BayerGR10,](#)
[PixelFormatInfoSelector_BayerGR10p,](#)
[PixelFormatInfoSelector_BayerGR12,](#)
[PixelFormatInfoSelector_BayerGR12p,](#)
[PixelFormatInfoSelector_BayerGR16,](#)
[PixelFormatInfoSelector_BayerRG8,](#)
[PixelFormatInfoSelector_BayerRG10,](#)
[PixelFormatInfoSelector_BayerRG10p,](#)
[PixelFormatInfoSelector_BayerRG12,](#)
[PixelFormatInfoSelector_BayerRG12p,](#)
[PixelFormatInfoSelector_BayerRG16,](#)
[PixelFormatInfoSelector_RGBa8,](#)
[PixelFormatInfoSelector_RGBa10,](#)
[PixelFormatInfoSelector_RGBa10p,](#)
[PixelFormatInfoSelector_RGBa12,](#)
[PixelFormatInfoSelector_RGBa12p,](#)
[PixelFormatInfoSelector_RGBa14,](#)
[PixelFormatInfoSelector_RGBa16,](#)
[PixelFormatInfoSelector_RGB8,](#)
[PixelFormatInfoSelector_RGB8_Planar,](#)
[PixelFormatInfoSelector_RGB10,](#)
[PixelFormatInfoSelector_RGB10_Planar,](#)
[PixelFormatInfoSelector_RGB10p,](#)
[PixelFormatInfoSelector_RGB10p32,](#)
[PixelFormatInfoSelector_RGB12,](#)
[PixelFormatInfoSelector_RGB12_Planar,](#)
[PixelFormatInfoSelector_RGB12p,](#)
[PixelFormatInfoSelector_RGB14,](#)
[PixelFormatInfoSelector_RGB16,](#)
[PixelFormatInfoSelector_RGB16s,](#)
[PixelFormatInfoSelector_RGB32f,](#)
[PixelFormatInfoSelector_RGB16_Planar,](#)
[PixelFormatInfoSelector_RGB565p,](#)
[PixelFormatInfoSelector_BGRa8,](#)
[PixelFormatInfoSelector_BGRa10,](#)
[PixelFormatInfoSelector_BGRa10p,](#)
[PixelFormatInfoSelector_BGRa12,](#)
[PixelFormatInfoSelector_BGRa12p,](#)
[PixelFormatInfoSelector_BGRa14,](#)
[PixelFormatInfoSelector_BGRa16,](#)
[PixelFormatInfoSelector_RGBa32f,](#)
[PixelFormatInfoSelector_BGR8,](#)
[PixelFormatInfoSelector_BGR10,](#)
[PixelFormatInfoSelector_BGR10p,](#)
[PixelFormatInfoSelector_BGR12,](#)
[PixelFormatInfoSelector_BGR12p,](#)
[PixelFormatInfoSelector_BGR14,](#)
[PixelFormatInfoSelector_BGR16,](#)

PixelFormatInfoSelector_BGR565p,
PixelFormatInfoSelector_R8,
PixelFormatInfoSelector_R10,
PixelFormatInfoSelector_R12,
PixelFormatInfoSelector_R16,
PixelFormatInfoSelector_G8,
PixelFormatInfoSelector_G10,
PixelFormatInfoSelector_G12,
PixelFormatInfoSelector_G16,
PixelFormatInfoSelector_B8,
PixelFormatInfoSelector_B10,
PixelFormatInfoSelector_B12,
PixelFormatInfoSelector_B16,
PixelFormatInfoSelector_Coord3D_ABC8,
PixelFormatInfoSelector_Coord3D_ABC8_Planar,
PixelFormatInfoSelector_Coord3D_ABC10p,
PixelFormatInfoSelector_Coord3D_ABC10p_Planar,
PixelFormatInfoSelector_Coord3D_ABC12p,
PixelFormatInfoSelector_Coord3D_ABC12p_Planar,
PixelFormatInfoSelector_Coord3D_ABC16,
PixelFormatInfoSelector_Coord3D_ABC16_Planar,
PixelFormatInfoSelector_Coord3D_ABC32f,
PixelFormatInfoSelector_Coord3D_ABC32f_Planar,
PixelFormatInfoSelector_Coord3D_AC8,
PixelFormatInfoSelector_Coord3D_AC8_Planar,
PixelFormatInfoSelector_Coord3D_AC10p,
PixelFormatInfoSelector_Coord3D_AC10p_Planar,
PixelFormatInfoSelector_Coord3D_AC12p,
PixelFormatInfoSelector_Coord3D_AC12p_Planar,
PixelFormatInfoSelector_Coord3D_AC16,
PixelFormatInfoSelector_Coord3D_AC16_Planar,
PixelFormatInfoSelector_Coord3D_AC32f,
PixelFormatInfoSelector_Coord3D_AC32f_Planar,
PixelFormatInfoSelector_Coord3D_A8,
PixelFormatInfoSelector_Coord3D_A10p,
PixelFormatInfoSelector_Coord3D_A12p,
PixelFormatInfoSelector_Coord3D_A16,
PixelFormatInfoSelector_Coord3D_A32f,
PixelFormatInfoSelector_Coord3D_B8,
PixelFormatInfoSelector_Coord3D_B10p,
PixelFormatInfoSelector_Coord3D_B12p,
PixelFormatInfoSelector_Coord3D_B16,
PixelFormatInfoSelector_Coord3D_B32f,
PixelFormatInfoSelector_Coord3D_C8,
PixelFormatInfoSelector_Coord3D_C10p,
PixelFormatInfoSelector_Coord3D_C12p,
PixelFormatInfoSelector_Coord3D_C16,
PixelFormatInfoSelector_Coord3D_C32f,
PixelFormatInfoSelector_Confidence1,
PixelFormatInfoSelector_Confidence1p,
PixelFormatInfoSelector_Confidence8,
PixelFormatInfoSelector_Confidence16,
PixelFormatInfoSelector_Confidence32f,
PixelFormatInfoSelector_BiColorBGRG8,
PixelFormatInfoSelector_BiColorBGRG10,
PixelFormatInfoSelector_BiColorBGRG10p,
PixelFormatInfoSelector_BiColorBGRG12,
PixelFormatInfoSelector_BiColorBGRG12p,

[PixelFormatInfoSelector_BiColorRGBG8,](#)
[PixelFormatInfoSelector_BiColorRGBG10,](#)
[PixelFormatInfoSelector_BiColorRGBG10p,](#)
[PixelFormatInfoSelector_BiColorRGBG12,](#)
[PixelFormatInfoSelector_BiColorRGBG12p,](#)
[PixelFormatInfoSelector_SCF1WBWG8,](#)
[PixelFormatInfoSelector_SCF1WBWG10,](#)
[PixelFormatInfoSelector_SCF1WBWG10p,](#)
[PixelFormatInfoSelector_SCF1WBWG12,](#)
[PixelFormatInfoSelector_SCF1WBWG12p,](#)
[PixelFormatInfoSelector_SCF1WBWG14,](#)
[PixelFormatInfoSelector_SCF1WBWG16,](#)
[PixelFormatInfoSelector_SCF1WGWB8,](#)
[PixelFormatInfoSelector_SCF1WGWB10,](#)
[PixelFormatInfoSelector_SCF1WGWB10p,](#)
[PixelFormatInfoSelector_SCF1WGWB12,](#)
[PixelFormatInfoSelector_SCF1WGWB12p,](#)
[PixelFormatInfoSelector_SCF1WGWB14,](#)
[PixelFormatInfoSelector_SCF1WGWB16,](#)
[PixelFormatInfoSelector_SCF1WGWR8,](#)
[PixelFormatInfoSelector_SCF1WGWR10,](#)
[PixelFormatInfoSelector_SCF1WGWR10p,](#)
[PixelFormatInfoSelector_SCF1WGWR12,](#)
[PixelFormatInfoSelector_SCF1WGWR12p,](#)
[PixelFormatInfoSelector_SCF1WGWR14,](#)
[PixelFormatInfoSelector_SCF1WGWR16,](#)
[PixelFormatInfoSelector_SCF1WRWG8,](#)
[PixelFormatInfoSelector_SCF1WRWG10,](#)
[PixelFormatInfoSelector_SCF1WRWG10p,](#)
[PixelFormatInfoSelector_SCF1WRWG12,](#)
[PixelFormatInfoSelector_SCF1WRWG12p,](#)
[PixelFormatInfoSelector_SCF1WRWG14,](#)
[PixelFormatInfoSelector_SCF1WRWG16,](#)
[PixelFormatInfoSelector_YCbCr8,](#)
[PixelFormatInfoSelector_YCbCr8_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr10_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr10p_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr12_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr12p_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr411_8,](#)
[PixelFormatInfoSelector_YCbCr411_8_CbYYCrYY,](#)
[PixelFormatInfoSelector_YCbCr422_8,](#)
[PixelFormatInfoSelector_YCbCr422_8_CbYCrY,](#)
[PixelFormatInfoSelector_YCbCr422_10,](#)
[PixelFormatInfoSelector_YCbCr422_10_CbYCrY,](#)
[PixelFormatInfoSelector_YCbCr422_10p,](#)
[PixelFormatInfoSelector_YCbCr422_10p_CbYCrY,](#)
[PixelFormatInfoSelector_YCbCr422_12,](#)
[PixelFormatInfoSelector_YCbCr422_12_CbYCrY,](#)
[PixelFormatInfoSelector_YCbCr422_12p,](#)
[PixelFormatInfoSelector_YCbCr422_12p_CbYCrY,](#)
[PixelFormatInfoSelector_YCbCr601_8_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr601_10_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr601_10p_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr601_12_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr601_12p_CbYCr,](#)
[PixelFormatInfoSelector_YCbCr601_411_8_CbYYCrYY,](#)
[PixelFormatInfoSelector_YCbCr601_422_8,](#)

```

PixelFormatInfoSelector_YCbCr601_422_8_CbYCrY,
PixelFormatInfoSelector_YCbCr601_422_10,
PixelFormatInfoSelector_YCbCr601_422_10_CbYCrY,
PixelFormatInfoSelector_YCbCr601_422_10p,
PixelFormatInfoSelector_YCbCr601_422_10p_CbYCrY,
PixelFormatInfoSelector_YCbCr601_422_12,
PixelFormatInfoSelector_YCbCr601_422_12_CbYCrY,
PixelFormatInfoSelector_YCbCr601_422_12p,
PixelFormatInfoSelector_YCbCr601_422_12p_CbYCrY,
PixelFormatInfoSelector_YCbCr709_8_CbYCr,
PixelFormatInfoSelector_YCbCr709_10_CbYCr,
PixelFormatInfoSelector_YCbCr709_10p_CbYCr,
PixelFormatInfoSelector_YCbCr709_12_CbYCr,
PixelFormatInfoSelector_YCbCr709_12p_CbYCr,
PixelFormatInfoSelector_YCbCr709_411_8_CbYYCrYY,
PixelFormatInfoSelector_YCbCr709_422_8,
PixelFormatInfoSelector_YCbCr709_422_8_CbYCrY,
PixelFormatInfoSelector_YCbCr709_422_10,
PixelFormatInfoSelector_YCbCr709_422_10_CbYCrY,
PixelFormatInfoSelector_YCbCr709_422_10p,
PixelFormatInfoSelector_YCbCr709_422_10p_CbYCrY,
PixelFormatInfoSelector_YCbCr709_422_12,
PixelFormatInfoSelector_YCbCr709_422_12_CbYCrY,
PixelFormatInfoSelector_YCbCr709_422_12p,
PixelFormatInfoSelector_YCbCr709_422_12p_CbYCrY,
PixelFormatInfoSelector_YUV8_UYV,
PixelFormatInfoSelector_YUV411_8_UYYVYY,
PixelFormatInfoSelector_YUV422_8,
PixelFormatInfoSelector_YUV422_8_UYVY,
PixelFormatInfoSelector_Polarized8,
PixelFormatInfoSelector_Polarized10p,
PixelFormatInfoSelector_Polarized12p,
PixelFormatInfoSelector_Polarized16,
PixelFormatInfoSelector_BayerRGPolarized8,
PixelFormatInfoSelector_BayerRGPolarized10p,
PixelFormatInfoSelector_BayerRGPolarized12p,
PixelFormatInfoSelector_BayerRGPolarized16,
PixelFormatInfoSelector_LLCMono8,
PixelFormatInfoSelector_LLCBayerRG8,
PixelFormatInfoSelector_JPEGMono8,
PixelFormatInfoSelector_JPEGColor8,
NUM_PIXELFORMATINFOSELECTOR }

• enum spinDeinterlacingEnums {
    Deinterlacing_Off,
    Deinterlacing_LineDuplication,
    Deinterlacing_Weave,
    NUM_DEINTERLACING }

• enum spinImageCompressionRateOptionEnums {
    ImageCompressionRateOption_FixBitrate,
    ImageCompressionRateOption_FixQuality,
    NUM_IMAGECOMPRESSIONRATEOPTION }

• enum spinImageCompressionJPEGFormatOptionEnums {
    ImageCompressionJPEGFormatOption_Lossless,
    ImageCompressionJPEGFormatOption_BaselineStandard,
    ImageCompressionJPEGFormatOption_BaselineOptimized,
    ImageCompressionJPEGFormatOption_Progressive,
    NUM_IMAGECOMPRESSIONJPEGFORMATOPTION }

• enum spinAcquisitionStatusSelectorEnums {

```



```

    AcquisitionStatusSelector_AcquisitionTriggerWait,
    AcquisitionStatusSelector_AcquisitionActive,
    AcquisitionStatusSelector_AcquisitionTransfer,
    AcquisitionStatusSelector_FrameTriggerWait,
    AcquisitionStatusSelector_FrameActive,
    AcquisitionStatusSelector_ExposureActive,
    NUM_ACQUISITIONSTATUSSELECTOR }

• enum spinExposureTimeModeEnums {
    ExposureTimeMode_Common,
    ExposureTimeMode_Individual,
    NUM_EXPOSURETIMEMODE }

• enum spinExposureTimeSelectorEnums {
    ExposureTimeSelector_Common,
    ExposureTimeSelector_Red,
    ExposureTimeSelector_Green,
    ExposureTimeSelector_Blue,
    ExposureTimeSelector_Cyan,
    ExposureTimeSelector_Magenta,
    ExposureTimeSelector_Yellow,
    ExposureTimeSelector_Infrared,
    ExposureTimeSelector_Ultraviolet,
    ExposureTimeSelector_Stage1,
    ExposureTimeSelector_Stage2,
    NUM_EXPOSURETIMESELECTOR }

• enum spinGainAutoBalanceEnums {
    GainAutoBalance_Off,
    GainAutoBalance_Once,
    GainAutoBalance_Continuous,
    NUM_GAINAUTOBALANCE }

• enum spinBlackLevelAutoEnums {
    BlackLevelAuto_Off,
    BlackLevelAuto_Once,
    BlackLevelAuto_Continuous,
    NUM_BLACKLEVELAUTO }

• enum spinBlackLevelAutoBalanceEnums {
    BlackLevelAutoBalance_Off,
    BlackLevelAutoBalance_Once,
    BlackLevelAutoBalance_Continuous,
    NUM_BLACKLEVELAUTOBALANCE }

• enum spinWhiteClipSelectorEnums {
    WhiteClipSelector_All,
    WhiteClipSelector_Red,
    WhiteClipSelector_Green,
    WhiteClipSelector_Blue,
    WhiteClipSelector_Y,
    WhiteClipSelector_U,
    WhiteClipSelector_V,
    WhiteClipSelector_Tap1,
    WhiteClipSelector_Tap2,
    NUM_WHITECLIPSELECTOR }

• enum spinTimerSelectorEnums {
    TimerSelector_Timer0,
    TimerSelector_Timer1,
    TimerSelector_Timer2,
    NUM_TIMERSELECTOR }

• enum spinTimerStatusEnums {
    TimerStatus_TimerIdle,
    TimerStatus_TimerTriggerWait,

```

```

TimerStatus_TimerActive,
TimerStatus_TimerCompleted,
NUM_TIMERSTATUS }

• enum spinTimerTriggerSourceEnums {
TimerTriggerSource_Off,
TimerTriggerSource_AcquisitionTrigger,
TimerTriggerSource_AcquisitionStart,
TimerTriggerSource_AcquisitionEnd,
TimerTriggerSource_FrameTrigger,
TimerTriggerSource_FrameStart,
TimerTriggerSource_FrameEnd,
TimerTriggerSource_FrameBurstStart,
TimerTriggerSource_FrameBurstEnd,
TimerTriggerSource_LineTrigger,
TimerTriggerSource_LineStart,
TimerTriggerSource_LineEnd,
TimerTriggerSource_ExposureStart,
TimerTriggerSource_ExposureEnd,
TimerTriggerSource_Line0,
TimerTriggerSource_Line1,
TimerTriggerSource_Line2,
TimerTriggerSource_UserOutput0,
TimerTriggerSource_UserOutput1,
TimerTriggerSource_UserOutput2,
TimerTriggerSource_Counter0Start,
TimerTriggerSource_Counter1Start,
TimerTriggerSource_Counter2Start,
TimerTriggerSource_Counter0End,
TimerTriggerSource_Counter1End,
TimerTriggerSource_Counter2End,
TimerTriggerSource_Timer0Start,
TimerTriggerSource_Timer1Start,
TimerTriggerSource_Timer2Start,
TimerTriggerSource_Timer0End,
TimerTriggerSource_Timer1End,
TimerTriggerSource_Timer2End,
TimerTriggerSource_Encoder0,
TimerTriggerSource_Encoder1,
TimerTriggerSource_Encoder2,
TimerTriggerSource_SoftwareSignal0,
TimerTriggerSource_SoftwareSignal1,
TimerTriggerSource_SoftwareSignal2,
TimerTriggerSource_Action0,
TimerTriggerSource_Action1,
TimerTriggerSource_Action2,
TimerTriggerSource_LinkTrigger0,
TimerTriggerSource_LinkTrigger1,
TimerTriggerSource_LinkTrigger2,
NUM_TIMERTRIGGERSOURCE }

• enum spinTimerTriggerActivationEnums {
TimerTriggerActivation_RisingEdge,
TimerTriggerActivation_FallingEdge,
TimerTriggerActivation_AnyEdge,
TimerTriggerActivation_LevelHigh,
TimerTriggerActivation_LevelLow,
NUM_TIMERTRIGGERACTIVATION }

• enum spinEncoderSelectorEnums {
EncoderSelector_Encoder0,

```

```

EncoderSelector_Encoder1,
EncoderSelector_Encoder2,
NUM_ENCODERSELECTOR }

• enum spinEncoderSourceAEnums {
EncoderSourceA_Off,
EncoderSourceA_Line0,
EncoderSourceA_Line1,
EncoderSourceA_Line2,
NUM_ENCODERSOURCEA }

• enum spinEncoderSourceBEnums {
EncoderSourceB_Off,
EncoderSourceB_Line0,
EncoderSourceB_Line1,
EncoderSourceB_Line2,
NUM_ENCODERSOURCEB }

• enum spinEncoderModeEnums {
EncoderMode_FourPhase,
EncoderMode_HighResolution,
NUM_ENCODERMODE }

• enum spinEncoderOutputModeEnums {
EncoderOutputMode_Off,
EncoderOutputMode_PositionUp,
EncoderOutputMode_PositionDown,
EncoderOutputMode_DirectionUp,
EncoderOutputMode_DirectionDown,
EncoderOutputMode_Motion,
NUM_ENCODEROUTPUTMODE }

• enum spinEncoderStatusEnums {
EncoderStatus_EncoderUp,
EncoderStatus_EncoderDown,
EncoderStatus_EncoderIdle,
EncoderStatus_EncoderStatic,
NUM_ENCODERSTATUS }

• enum spinEncoderResetSourceEnums {
EncoderResetSource_Off,
EncoderResetSource_AcquisitionTrigger,
EncoderResetSource_AcquisitionStart,
EncoderResetSource_AcquisitionEnd,
EncoderResetSource_FrameTrigger,
EncoderResetSource_FrameStart,
EncoderResetSource_FrameEnd,
EncoderResetSource_ExposureStart,
EncoderResetSource_ExposureEnd,
EncoderResetSource_Line0,
EncoderResetSource_Line1,
EncoderResetSource_Line2,
EncoderResetSource_Counter0Start,
EncoderResetSource_Counter1Start,
EncoderResetSource_Counter2Start,
EncoderResetSource_Counter0End,
EncoderResetSource_Counter1End,
EncoderResetSource_Counter2End,
EncoderResetSource_Timer0Start,
EncoderResetSource_Timer1Start,
EncoderResetSource_Timer2Start,
EncoderResetSource_Timer0End,
EncoderResetSource_Timer1End,
EncoderResetSource_Timer2End,

```

```

EncoderResetSource_UserOutput0,
EncoderResetSource_UserOutput1,
EncoderResetSource_UserOutput2,
EncoderResetSource_SoftwareSignal0,
EncoderResetSource_SoftwareSignal1,
EncoderResetSource_SoftwareSignal2,
EncoderResetSource_Action0,
EncoderResetSource_Action1,
EncoderResetSource_Action2,
EncoderResetSource_LinkTrigger0,
EncoderResetSource_LinkTrigger1,
EncoderResetSource_LinkTrigger2,
NUM_ENCODERRESETSOURCE }

• enum spinEncoderResetActivationEnums {
EncoderResetActivation_RisingEdge,
EncoderResetActivation_FallingEdge,
EncoderResetActivation_AnyEdge,
EncoderResetActivation_LevelHigh,
EncoderResetActivation_LevelLow,
NUM_ENCODERRESETACTIVATION }

• enum spinSoftwareSignalSelectorEnums {
SoftwareSignalSelector_SoftwareSignal0,
SoftwareSignalSelector_SoftwareSignal1,
SoftwareSignalSelector_SoftwareSignal2,
NUM_SOFTWARESIGNALSELECTOR }

• enum spinActionUnconditionalModeEnums {
ActionUnconditionalMode_Off,
ActionUnconditionalMode_On,
NUM_ACTIONUNCONDITIONALMODE }

• enum spinSourceSelectorEnums {
SourceSelector_Source0,
SourceSelector_Source1,
SourceSelector_Source2,
SourceSelector_All,
NUM_SOURCESELECTOR }

• enum spinTransferSelectorEnums {
TransferSelector_Stream0,
TransferSelector_Stream1,
TransferSelector_Stream2,
TransferSelector_All,
NUM_TRANSFERSELECTOR }

• enum spinTransferTriggerSelectorEnums {
TransferTriggerSelector_TransferStart,
TransferTriggerSelector_TransferStop,
TransferTriggerSelector_TransferAbort,
TransferTriggerSelector_TransferPause,
TransferTriggerSelector_TransferResume,
TransferTriggerSelector_TransferActive,
TransferTriggerSelector_TransferBurstStart,
TransferTriggerSelector_TransferBurstStop,
NUM_TRANSFERTRIGGERSELECTOR }

• enum spinTransferTriggerModeEnums {
TransferTriggerMode_Off,
TransferTriggerMode_On,
NUM_TRANSFERTRIGGERMODE }

• enum spinTransferTriggerSourceEnums {
TransferTriggerSource_Line0,
TransferTriggerSource_Line1,

```

```

TransferTriggerSource_Line2,
TransferTriggerSource_Counter0Start,
TransferTriggerSource_Counter1Start,
TransferTriggerSource_Counter2Start,
TransferTriggerSource_Counter0End,
TransferTriggerSource_Counter1End,
TransferTriggerSource_Counter2End,
TransferTriggerSource_Timer0Start,
TransferTriggerSource_Timer1Start,
TransferTriggerSource_Timer2Start,
TransferTriggerSource_Timer0End,
TransferTriggerSource_Timer1End,
TransferTriggerSource_Timer2End,
TransferTriggerSource_SoftwareSignal0,
TransferTriggerSource_SoftwareSignal1,
TransferTriggerSource_SoftwareSignal2,
TransferTriggerSource_Action0,
TransferTriggerSource_Action1,
TransferTriggerSource_Action2,
NUM_TRANSFERTRIGGERSOURCE }
• enum spinTransferTriggerActivationEnums {
TransferTriggerActivation_RisingEdge,
TransferTriggerActivation_FallingEdge,
TransferTriggerActivation_AnyEdge,
TransferTriggerActivation_LevelHigh,
TransferTriggerActivation_LevelLow,
NUM_TRANSFERTRIGGERACTIVATION }
• enum spinTransferStatusSelectorEnums {
TransferStatusSelector_Streaming,
TransferStatusSelector_Paused,
TransferStatusSelector_Stopping,
TransferStatusSelector_Stopped,
TransferStatusSelector_QueueOverflow,
NUM_TRANSFERSTATUSSELECTOR }
• enum spinTransferComponentSelectorEnums {
TransferComponentSelector_Red,
TransferComponentSelector_Green,
TransferComponentSelector_Blue,
TransferComponentSelector_All,
NUM_TRANSFERCOMPONENTSELECTOR }
• enum spinScan3dDistanceUnitEnums {
Scan3dDistanceUnit_Millimeter,
Scan3dDistanceUnit_Inch,
NUM_SCAN3DDISTANCEUNIT }
• enum spinScan3dCoordinateSystemEnums {
Scan3dCoordinateSystem_Cartesian,
Scan3dCoordinateSystem_Spherical,
Scan3dCoordinateSystem_Cylindrical,
NUM_SCAN3DCOORDINATESYSTEM }
• enum spinScan3dOutputModeEnums {
Scan3dOutputMode_UncalibratedC,
Scan3dOutputMode_CalibratedABC_Grid,
Scan3dOutputMode_CalibratedABC_PointCloud,
Scan3dOutputMode_CalibratedAC,
Scan3dOutputMode_CalibratedAC_Linescan,
Scan3dOutputMode_CalibratedC,
Scan3dOutputMode_CalibratedC_Linescan,
Scan3dOutputMode_RectifiedC,

```

```

Scan3dOutputMode_RectifiedC_Linescan,
Scan3dOutputMode_DisparityC,
Scan3dOutputMode_DisparityC_Linescan,
NUM_SCAN3DOUTPUTMODE }

• enum spinScan3dCoordinateSystemReferenceEnums {
Scan3dCoordinateSystemReference_Anchor,
Scan3dCoordinateSystemReference_Transformed,
NUM_SCAN3DCOORDINATESYSTEMREFERENCE }

• enum spinScan3dCoordinateSelectorEnums {
Scan3dCoordinateSelector_CoordinateA,
Scan3dCoordinateSelector_CoordinateB,
Scan3dCoordinateSelector_CoordinateC,
NUM_SCAN3DCOORDINATESELECTOR }

• enum spinScan3dCoordinateTransformSelectorEnums {
Scan3dCoordinateTransformSelector_RotationX,
Scan3dCoordinateTransformSelector_RotationY,
Scan3dCoordinateTransformSelector_RotationZ,
Scan3dCoordinateTransformSelector_TranslationX,
Scan3dCoordinateTransformSelector_TranslationY,
Scan3dCoordinateTransformSelector_TranslationZ,
NUM_SCAN3DCOORDINATETRANSFORMSELECTOR }

• enum spinScan3dCoordinateReferenceSelectorEnums {
Scan3dCoordinateReferenceSelector_RotationX,
Scan3dCoordinateReferenceSelector_RotationY,
Scan3dCoordinateReferenceSelector_RotationZ,
Scan3dCoordinateReferenceSelector_TranslationX,
Scan3dCoordinateReferenceSelector_TranslationY,
Scan3dCoordinateReferenceSelector_TranslationZ,
NUM_SCAN3DCOORDINATEREFERENCESELECTOR }

• enum spinChunkImageComponentEnums {
ChunkImageComponent_Intensity,
ChunkImageComponent_Color,
ChunkImageComponent_Infrared,
ChunkImageComponent_Ultraviolet,
ChunkImageComponent_Range,
ChunkImageComponent_Disparity,
ChunkImageComponent_Confidence,
ChunkImageComponent_Scatter,
NUM_CHUNKIMAGECOMPONENT }

• enum spinChunkCounterSelectorEnums {
ChunkCounterSelector_Counter0,
ChunkCounterSelector_Counter1,
ChunkCounterSelector_Counter2,
NUM_CHUNKCOUNTERSELECTOR }

• enum spinChunkTimerSelectorEnums {
ChunkTimerSelector_Timer0,
ChunkTimerSelector_Timer1,
ChunkTimerSelector_Timer2,
NUM_CHUNKTIMERSELECTOR }

• enum spinChunkEncoderSelectorEnums {
ChunkEncoderSelector_Encoder0,
ChunkEncoderSelector_Encoder1,
ChunkEncoderSelector_Encoder2,
NUM_CHUNKENCODERSELECTOR }

• enum spinChunkEncoderStatusEnums {
ChunkEncoderStatus_EncoderUp,
ChunkEncoderStatus_EncoderDown,
ChunkEncoderStatus_EncoderIdle,

```

- ChunkEncoderStatus_EncoderStatic,
 - NUM_CHUNKENCODERSTATUS }
- enum spinChunkExposureTimeSelectorEnums {
 - ChunkExposureTimeSelector_Common,
 - ChunkExposureTimeSelector_Red,
 - ChunkExposureTimeSelector_Green,
 - ChunkExposureTimeSelector_Blue,
 - ChunkExposureTimeSelector_Cyan,
 - ChunkExposureTimeSelector_Magenta,
 - ChunkExposureTimeSelector_Yellow,
 - ChunkExposureTimeSelector_Infrared,
 - ChunkExposureTimeSelector_Ultraviolet,
 - ChunkExposureTimeSelector_Stage1,
 - ChunkExposureTimeSelector_Stage2,
 - NUM_CHUNKEXPOSURETIMESELECTOR }
- enum spinChunkSourceIDEnums {
 - ChunkSourceID_Source0,
 - ChunkSourceID_Source1,
 - ChunkSourceID_Source2,
 - NUM_CHUNKSOURCEID }
- enum spinChunkRegionIDEnums {
 - ChunkRegionID_Region0,
 - ChunkRegionID_Region1,
 - ChunkRegionID_Region2,
 - NUM_CHUNKREGIONID }
- enum spinChunkTransferStreamIDEnums {
 - ChunkTransferStreamID_Stream0,
 - ChunkTransferStreamID_Stream1,
 - ChunkTransferStreamID_Stream2,
 - ChunkTransferStreamID_Stream3,
 - NUM_CHUNKTRANSFERSTREAMID }
- enum spinChunkScan3dDistanceUnitEnums {
 - ChunkScan3dDistanceUnit_Millimeter,
 - ChunkScan3dDistanceUnit_Inch,
 - NUM_CHUNKSCAN3DDISTANCEUNIT }
- enum spinChunkScan3dOutputModeEnums {
 - ChunkScan3dOutputMode_UncalibratedC,
 - ChunkScan3dOutputMode_CalibratedABC_Grid,
 - ChunkScan3dOutputMode_CalibratedABC_PointCloud,
 - ChunkScan3dOutputMode_CalibratedAC,
 - ChunkScan3dOutputMode_CalibratedAC_Linescan,
 - ChunkScan3dOutputMode_CalibratedC,
 - ChunkScan3dOutputMode_CalibratedC_Linescan,
 - ChunkScan3dOutputMode_RectifiedC,
 - ChunkScan3dOutputMode_RectifiedC_Linescan,
 - ChunkScan3dOutputMode_DisparityC,
 - ChunkScan3dOutputMode_DisparityC_Linescan,
 - NUM_CHUNKSCAN3DOUTPUTMODE }
- enum spinChunkScan3dCoordinateSystemEnums {
 - ChunkScan3dCoordinateSystem_Cartesian,
 - ChunkScan3dCoordinateSystem_Spherical,
 - ChunkScan3dCoordinateSystem_Cylindrical,
 - NUM_CHUNKSCAN3DCOORDINATESYSTEM }
- enum spinChunkScan3dCoordinateSystemReferenceEnums {
 - ChunkScan3dCoordinateSystemReference_Anchor,
 - ChunkScan3dCoordinateSystemReference_Transformed,
 - NUM_CHUNKSCAN3DCOORDINATESYSTEMREFERENCE }

- `enum spinChunkScan3dCoordinateSelectorEnums {`
`ChunkScan3dCoordinateSelector_CoordinateA,`
`ChunkScan3dCoordinateSelector_CoordinateB,`
`ChunkScan3dCoordinateSelector_CoordinateC,`
`NUM_CHUNKSCAN3DCOORDINATESELECTOR }`
- `enum spinChunkScan3dCoordinateTransformSelectorEnums {`
`ChunkScan3dCoordinateTransformSelector_RotationX,`
`ChunkScan3dCoordinateTransformSelector_RotationY,`
`ChunkScan3dCoordinateTransformSelector_RotationZ,`
`ChunkScan3dCoordinateTransformSelector_TranslationX,`
`ChunkScan3dCoordinateTransformSelector_TranslationY,`
`ChunkScan3dCoordinateTransformSelector_TranslationZ,`
`NUM_CHUNKSCAN3DCOORDINATETRANSFORMSELECTOR }`
- `enum spinChunkScan3dCoordinateReferenceSelectorEnums {`
`ChunkScan3dCoordinateReferenceSelector_RotationX,`
`ChunkScan3dCoordinateReferenceSelector_RotationY,`
`ChunkScan3dCoordinateReferenceSelector_RotationZ,`
`ChunkScan3dCoordinateReferenceSelector_TranslationX,`
`ChunkScan3dCoordinateReferenceSelector_TranslationY,`
`ChunkScan3dCoordinateReferenceSelector_TranslationZ,`
`NUM_CHUNKSCAN3DCOORDINATEREFERENCESELECTOR }`
- `enum spinDeviceTapGeometryEnums {`
`DeviceTapGeometry_Geometry_1X_1Y,`
`DeviceTapGeometry_Geometry_1X2_1Y,`
`DeviceTapGeometry_Geometry_1X2_1Y2,`
`DeviceTapGeometry_Geometry_2X_1Y,`
`DeviceTapGeometry_Geometry_2X_1Y2Geometry_2XE_1Y,`
`DeviceTapGeometry_Geometry_2XE_1Y2,`
`DeviceTapGeometry_Geometry_2XM_1Y,`
`DeviceTapGeometry_Geometry_2XM_1Y2,`
`DeviceTapGeometry_Geometry_1X_1Y2,`
`DeviceTapGeometry_Geometry_1X_2YE,`
`DeviceTapGeometry_Geometry_1X3_1Y,`
`DeviceTapGeometry_Geometry_3X_1Y,`
`DeviceTapGeometry_Geometry_1X,`
`DeviceTapGeometry_Geometry_1X2,`
`DeviceTapGeometry_Geometry_2X,`
`DeviceTapGeometry_Geometry_2XE,`
`DeviceTapGeometry_Geometry_2XM,`
`DeviceTapGeometry_Geometry_1X3,`
`DeviceTapGeometry_Geometry_3X,`
`DeviceTapGeometry_Geometry_1X4_1Y,`
`DeviceTapGeometry_Geometry_4X_1Y,`
`DeviceTapGeometry_Geometry_2X2_1Y,`
`DeviceTapGeometry_Geometry_2X2E_1YGeometry_2X2M_1Y,`
`DeviceTapGeometry_Geometry_1X2_2YE,`
`DeviceTapGeometry_Geometry_2X_2YE,`
`DeviceTapGeometry_Geometry_2XE_2YE,`
`DeviceTapGeometry_Geometry_2XM_2YE,`
`DeviceTapGeometry_Geometry_1X4,`
`DeviceTapGeometry_Geometry_4X,`
`DeviceTapGeometry_Geometry_2X2,`
`DeviceTapGeometry_Geometry_2X2E,`
`DeviceTapGeometry_Geometry_2X2M,`
`DeviceTapGeometry_Geometry_1X8_1Y,`
`DeviceTapGeometry_Geometry_8X_1Y,`
`DeviceTapGeometry_Geometry_4X2_1Y,`
`DeviceTapGeometry_Geometry_2X2E_2YE,`


```

DeviceTapGeometry_Geometry_1X8,
DeviceTapGeometry_Geometry_8X,
DeviceTapGeometry_Geometry_4X2,
DeviceTapGeometry_Geometry_4X2E,
DeviceTapGeometry_Geometry_4X2E_1Y,
DeviceTapGeometry_Geometry_1X10_1Y,
DeviceTapGeometry_Geometry_10X_1Y,
DeviceTapGeometry_Geometry_1X10,
DeviceTapGeometry_Geometry_10X,
NUM_DEVICETAPGEOMETRY }

• enum spinGevPhysicalLinkConfigurationEnums {
    GevPhysicalLinkConfiguration_SingleLink,
    GevPhysicalLinkConfiguration_MultiLink,
    GevPhysicalLinkConfiguration_StaticLAG,
    GevPhysicalLinkConfiguration_DynamicLAG,
    NUM_GEVPHYSICALLINKCONFIGURATION }

• enum spinGevCurrentPhysicalLinkConfigurationEnums {
    GevCurrentPhysicalLinkConfiguration_SingleLink,
    GevCurrentPhysicalLinkConfiguration_MultiLink,
    GevCurrentPhysicalLinkConfiguration_StaticLAG,
    GevCurrentPhysicalLinkConfiguration_DynamicLAG,
    NUM_GEVCURRENTPHYSICALLINKCONFIGURATION }

• enum spinGevIPConfigurationStatusEnums {
    GevIPConfigurationStatus_None,
    GevIPConfigurationStatus_PersistentIP,
    GevIPConfigurationStatus_DHCP,
    GevIPConfigurationStatus_LLA,
    GevIPConfigurationStatus_ForceIP,
    NUM_GEVIPCONFIGURATIONSTATUS }

• enum spinGevGVCPExtendedStatusCodesSelectorEnums {
    GevGVCPExtendedStatusCodesSelector_Version1_1,
    GevGVCPExtendedStatusCodesSelector_Version2_0,
    NUM_GEVGVCPEXTENDEDSTATUSCODESSELECTOR }

• enum spinGevGVSPExtendedIDModeEnums {
    GevGVSPExtendedIDMode_Off,
    GevGVSPExtendedIDMode_On,
    NUM_GEVGVSPEXTENDEDIDMODE }

• enum spinCIConfigurationEnums {
    CIConfiguration_Base,
    CIConfiguration_Medium,
    CIConfiguration_Full,
    CIConfiguration_DualBase,
    CIConfiguration_EightyBit,
    NUM_CLCONFIGURATION }

• enum spinCITimeSlotsCountEnums {
    CITimeSlotsCount_One,
    CITimeSlotsCount_Two,
    CITimeSlotsCount_Three,
    NUM_CLTIMESLOTSCOUNT }

• enum spinCxpLinkConfigurationStatusEnums {
    CxpLinkConfigurationStatus_None,
    CxpLinkConfigurationStatus_Pending,
    CxpLinkConfigurationStatus_CXP1_X1,
    CxpLinkConfigurationStatus_CXP2_X1,
    CxpLinkConfigurationStatus_CXP3_X1,
    CxpLinkConfigurationStatus_CXP5_X1,
    CxpLinkConfigurationStatus_CXP6_X1,
    CxpLinkConfigurationStatus_CXP1_X2,

```

```

CxpLinkConfigurationStatus_CXP2_X2,
CxpLinkConfigurationStatus_CXP3_X2,
CxpLinkConfigurationStatus_CXP5_X2,
CxpLinkConfigurationStatus_CXP6_X2,
CxpLinkConfigurationStatus_CXP1_X3,
CxpLinkConfigurationStatus_CXP2_X3,
CxpLinkConfigurationStatus_CXP3_X3,
CxpLinkConfigurationStatus_CXP5_X3,
CxpLinkConfigurationStatus_CXP6_X3,
CxpLinkConfigurationStatus_CXP1_X4,
CxpLinkConfigurationStatus_CXP2_X4,
CxpLinkConfigurationStatus_CXP3_X4,
CxpLinkConfigurationStatus_CXP5_X4,
CxpLinkConfigurationStatus_CXP6_X4,
CxpLinkConfigurationStatus_CXP1_X5,
CxpLinkConfigurationStatus_CXP2_X5,
CxpLinkConfigurationStatus_CXP3_X5,
CxpLinkConfigurationStatus_CXP5_X5,
CxpLinkConfigurationStatus_CXP6_X5,
CxpLinkConfigurationStatus_CXP1_X6,
CxpLinkConfigurationStatus_CXP2_X6,
CxpLinkConfigurationStatus_CXP3_X6,
CxpLinkConfigurationStatus_CXP5_X6,
CxpLinkConfigurationStatus_CXP6_X6,
NUM_CXPLINKCONFIGURATIONSTATUS }

```

- **enum** spinCxpLinkConfigurationPreferredEnums {

```

CxpLinkConfigurationPreferred_CXP1_X1,
CxpLinkConfigurationPreferred_CXP2_X1,
CxpLinkConfigurationPreferred_CXP3_X1,
CxpLinkConfigurationPreferred_CXP5_X1,
CxpLinkConfigurationPreferred_CXP6_X1,
CxpLinkConfigurationPreferred_CXP1_X2,
CxpLinkConfigurationPreferred_CXP2_X2,
CxpLinkConfigurationPreferred_CXP3_X2,
CxpLinkConfigurationPreferred_CXP5_X2,
CxpLinkConfigurationPreferred_CXP6_X2,
CxpLinkConfigurationPreferred_CXP1_X3,
CxpLinkConfigurationPreferred_CXP2_X3,
CxpLinkConfigurationPreferred_CXP3_X3,
CxpLinkConfigurationPreferred_CXP5_X3,
CxpLinkConfigurationPreferred_CXP6_X3,
CxpLinkConfigurationPreferred_CXP1_X4,
CxpLinkConfigurationPreferred_CXP2_X4,
CxpLinkConfigurationPreferred_CXP3_X4,
CxpLinkConfigurationPreferred_CXP5_X4,
CxpLinkConfigurationPreferred_CXP6_X4,
CxpLinkConfigurationPreferred_CXP1_X5,
CxpLinkConfigurationPreferred_CXP2_X5,
CxpLinkConfigurationPreferred_CXP3_X5,
CxpLinkConfigurationPreferred_CXP5_X5,
CxpLinkConfigurationPreferred_CXP6_X5,
CxpLinkConfigurationPreferred_CXP1_X6,
CxpLinkConfigurationPreferred_CXP2_X6,
CxpLinkConfigurationPreferred_CXP3_X6,
CxpLinkConfigurationPreferred_CXP5_X6,
CxpLinkConfigurationPreferred_CXP6_X6,
NUM_CXPLINKCONFIGURATIONPREFERRED }

```

- **enum** spinCxpLinkConfigurationEnums {


```
CxpLinkConfiguration_Auto,  
CxpLinkConfiguration_CXP1_X1,  
CxpLinkConfiguration_CXP2_X1,  
CxpLinkConfiguration_CXP3_X1,  
CxpLinkConfiguration_CXP5_X1,  
CxpLinkConfiguration_CXP6_X1,  
CxpLinkConfiguration_CXP1_X2,  
CxpLinkConfiguration_CXP2_X2,  
CxpLinkConfiguration_CXP3_X2,  
CxpLinkConfiguration_CXP5_X2,  
CxpLinkConfiguration_CXP6_X2,  
CxpLinkConfiguration_CXP1_X3,  
CxpLinkConfiguration_CXP2_X3,  
CxpLinkConfiguration_CXP3_X3,  
CxpLinkConfiguration_CXP5_X3,  
CxpLinkConfiguration_CXP6_X3,  
CxpLinkConfiguration_CXP1_X4,  
CxpLinkConfiguration_CXP2_X4,  
CxpLinkConfiguration_CXP3_X4,  
CxpLinkConfiguration_CXP5_X4,  
CxpLinkConfiguration_CXP6_X4,  
CxpLinkConfiguration_CXP1_X5,  
CxpLinkConfiguration_CXP2_X5,  
CxpLinkConfiguration_CXP3_X5,  
CxpLinkConfiguration_CXP5_X5,  
CxpLinkConfiguration_CXP6_X5,  
CxpLinkConfiguration_CXP1_X6,  
CxpLinkConfiguration_CXP2_X6,  
CxpLinkConfiguration_CXP3_X6,  
CxpLinkConfiguration_CXP5_X6,  
CxpLinkConfiguration_CXP6_X6,  
NUM_CXPLINKCONFIGURATION }
```

- enum spinCxpConnectionTestModeEnums {
CxpConnectionTestMode_Off,
CxpConnectionTestMode_Mode1,
NUM_CXP_CONNECTIONTESTMODE }


- enum spinCxpPoCxpStatusEnums {
CxpPoCxpStatus_Auto,
CxpPoCxpStatus_Off,
CxpPoCxpStatus_Tripped,
NUM_CXPPOCXPSTATUS }

6.2 include/spinc/ChunkDataDefC.h File Reference

Include dependency graph for ChunkDataDefC.h:



This graph shows which files directly or indirectly include this file:




Data Structures

- struct [spinChunkData](#)


The type of information that can be obtained from image chunk data.

6.3 include/spinc/QuickSpinC.h File Reference

Include dependency graph for QuickSpinC.h:



This graph shows which files directly or indirectly include this file:




Functions


- [SPINNAKERC_API quickSpinInit](#) ([spinCamera](#) hCamera, [quickSpin](#) *pQuickSpin)
- [SPINNAKERC_API quickSpinInitEx](#) ([spinCamera](#) hCamera, [quickSpin](#) *pQuickSpin, [quickSpinTLDevice](#) *pQuickSpinTLDevice, [quickSpinTLStream](#) *pQuickSpinTLStream)
- [SPINNAKERC_API quickSpinTLDeviceInit](#) ([spinCamera](#) hCamera, [quickSpinTLDevice](#) *pQuickSpinTLDevice)
- [SPINNAKERC_API quickSpinTLStreamInit](#) ([spinCamera](#) hCamera, [quickSpinTLStream](#) *pQuickSpinTLStream)
- [SPINNAKERC_API quickSpinTLInterfaceInit](#) ([spinInterface](#) hInterface, [quickSpinTLInterface](#) *pQuickSpinTLInterface)
- [SPINNAKERC_API quickSpinTLSystemInit](#) ([spinSystem](#) hSystem, [quickSpinTLSystem](#) *pQuickSpinTLSystem)

6.4 include/spinc/QuickSpinDefsC.h File Reference

Include dependency graph for QuickSpinDefsC.h:



This graph shows which files directly or indirectly include this file:



Data Structures

- struct [quickSpin](#)

Typedefs

- typedef [spinNodeHandle](#) [quickSpinStringNode](#)
- typedef [spinNodeHandle](#) [quickSpinIntegerNode](#)
- typedef [spinNodeHandle](#) [quickSpinFloatNode](#)
- typedef [spinNodeHandle](#) [quickSpinBooleanNode](#)
- typedef [spinNodeHandle](#) [quickSpinEnumerationNode](#)
- typedef [spinNodeHandle](#) [quickSpinCommandNode](#)
- typedef [spinNodeHandle](#) [quickSpinRegisterNode](#)

6.4.1 Typedef Documentation

6.4.1.1 quickSpinBooleanNode

```
typedef spinNodeHandle quickSpinBooleanNode
```

6.4.1.2 quickSpinCommandNode

```
typedef spinNodeHandle quickSpinCommandNode
```

6.4.1.3 quickSpinEnumerationNode

```
typedef spinNodeHandle quickSpinEnumerationNode
```

6.4.1.4 quickSpinFloatNode

```
typedef spinNodeHandle quickSpinFloatNode
```

6.4.1.5 quickSpinIntegerNode

```
typedef spinNodeHandle quickSpinIntegerNode
```

6.4.1.6 quickSpinRegisterNode


```
typedef spinNodeHandle quickSpinRegisterNode
```

6.4.1.7 quickSpinStringNode

```
typedef spinNodeHandle quickSpinStringNode
```

6.5 include/spinc/SpinnakerC.h File Reference

Include dependency graph for SpinnakerC.h:



Functions

- [SPINNAKERC_API spinErrorGetLast](#) ([spinError](#) *pError)
Retrieves the error code of the last error.
- [SPINNAKERC_API spinErrorGetLastMessage](#) (char *pBuf, [size_t](#) *pBufLen)
Retrieves the error message of the last error.
- [SPINNAKERC_API spinErrorGetLastBuildDate](#) (char *pBuf, [size_t](#) *pBufLen)
Retrieves the build date of the last error.
- [SPINNAKERC_API spinErrorGetLastBuildTime](#) (char *pBuf, [size_t](#) *pBufLen)
Retrieves the build time of the last error.
- [SPINNAKERC_API spinErrorGetLastFileName](#) (char *pBuf, [size_t](#) *pBufLen)
Retrieves the filename of the last error.
- [SPINNAKERC_API spinErrorGetLastFullMessage](#) (char *pBuf, [size_t](#) *pBufLen)
Retrieves the full error message of the last error.
- [SPINNAKERC_API spinErrorGetLastFunctionName](#) (char *pBuf, [size_t](#) *pBufLen)
Retrieves the function name of the last error.
- [SPINNAKERC_API spinErrorGetLastLineNumber](#) ([int64_t](#) *pLineNum)
Retrieves the line number of the last error.
- [SPINNAKERC_API spinSystemGetInstance](#) ([spinSystem](#) *phSystem)
Retrieves an instance of the system object; the system is a singleton, so there will only ever be one instance; system instance must be destroyed by calling spinSystemReleaseInstance.
- [SPINNAKERC_API spinSystemReleaseInstance](#) ([spinSystem](#) hSystem)
Releases the system; make sure handle is cleaned up properly by setting it to NULL after system is released; the handle can only be used again after calling spinSystemGetInstance.
- [SPINNAKERC_API spinSystemGetInterfaces](#) ([spinSystem](#) hSystem, [spinInterfaceList](#) hInterfaceList)
Retrieves a list of detected (and enumerable) interfaces on the system; interface lists must be created and destroyed.
- [SPINNAKERC_API spinSystemGetCameras](#) ([spinSystem](#) hSystem, [spinCameraList](#) hCameraList)
Retrieves a list of detected (and enumerable) cameras on the system; camera lists must be created and destroyed.
- [SPINNAKERC_API spinSystemGetCamerasEx](#) ([spinSystem](#) hSystem, [bool8_t](#) bUpdateInterfaces, [bool8_t](#) bUpdateCameras, [spinCameraList](#) hCameraList)
Retrieves a list of detected (and enumerable) cameras on the system; manually set whether to update the current interface and camera lists; camera lists must be created and destroyed.
- [SPINNAKERC_API spinSystemSetLoggingLevel](#) ([spinSystem](#) hSystem, [spinnakerLogLevel](#) logLevel)
Sets the logging level for all logging events on the system.
- [SPINNAKERC_API spinSystemGetLoggingLevel](#) ([spinSystem](#) hSystem, [spinnakerLogLevel](#) *pLogLevel)
Retrieves the logging level for all logging events on the system.
- [SPINNAKERC_API spinSystemRegisterLogEventHandler](#) ([spinSystem](#) hSystem, [spinLogEventHandler](#) h↔LogEventHandler)
Registers a logging event handler to the system (event handlers registered in this way must be unregistered)
- [SPINNAKERC_API spinSystemUnregisterLogEventHandler](#) ([spinSystem](#) hSystem, [spinLogEventHandler](#) hLogEventHandler)
Unregisters a selected logging event handler from the system.
- [SPINNAKERC_API spinSystemUnregisterAllLogEventHandlers](#) ([spinSystem](#) hSystem)
Unregisters all logging event handlers from the system.
- [SPINNAKERC_API spinSystemIsInUse](#) ([spinSystem](#) hSystem, [bool8_t](#) *pbIsInUse)
Checks whether a system is currently in use.
- [SPINNAKERC_API spinSystemRegisterDeviceArrivalEventHandler](#) ([spinSystem](#) hSystem, [spinDevice](#)↔ArrivalEventHandler hDeviceArrivalEventHandler)
Registers a device arrival event handler to every interface on the system (event handlers registered this way must be unregistered)
- [SPINNAKERC_API spinSystemRegisterDeviceRemovalEventHandler](#) ([spinSystem](#) hSystem, [spinDevice](#)↔RemovalEventHandler hDeviceRemovalEventHandler)

Registers a device removal event handler to the system to every interface on the system (event handlers registered this way must be unregistered)

- [SPINNAKERC_API spinSystemUnregisterDeviceArrivalEventHandler](#) ([spinSystem](#) hSystem, [spinDeviceArrivalEventHandler](#) hDeviceArrivalEventHandler)

Unregisters a device arrival event handler from the system.

- [SPINNAKERC_API spinSystemUnregisterDeviceRemovalEventHandler](#) ([spinSystem](#) hSystem, [spinDeviceRemovalEventHandler](#) hDeviceRemovalEventHandler)

Unregisters a device removal event handler from the system.

- [SPINNAKERC_API spinSystemRegisterInterfaceEventHandler](#) ([spinSystem](#) hSystem, [spinInterfaceEventHandler](#) hInterfaceEventHandler)

Registers an interface event handler (device arrival and device removal) to every interface on the system (interface events registered this way must be unregistered) If new interfaces are detected by the system after [spinSystemRegisterInterfaceEventHandler\(\)](#) is called, those interfaces will be automatically registered with this event.

- [SPINNAKERC_API spinSystemUnregisterInterfaceEventHandler](#) ([spinSystem](#) hSystem, [spinInterfaceEventHandler](#) hInterfaceEventHandler)

Unregisters an interface event handler from the system.

- [SPINNAKERC_API spinSystemUpdateCameras](#) ([spinSystem](#) hSystem, [bool8_t](#) *pbChanged)

Updates the list of cameras on the system, informing whether there has been any changes.

- [SPINNAKERC_API spinSystemUpdateCamerasEx](#) ([spinSystem](#) hSystem, [bool8_t](#) bUpdateInterfaces, [bool8_t](#) *pbChanged)

Updates the list of cameras on the system, informing whether there has been any changes; manually set whether to update the current interface lists.

- [SPINNAKERC_API spinSystemSendActionCommand](#) ([spinSystem](#) hSystem, [size_t](#) iDeviceKey, [size_t](#) iGroupKey, [size_t](#) iGroupMask, [size_t](#) iActionTime, [size_t](#) *piResultSize, [actionCommandResult](#) results[])

Broadcast an Action Command to all devices on system.

- [SPINNAKERC_API spinSystemGetLibraryVersion](#) ([spinSystem](#) hSystem, [spinLibraryVersion](#) *hLibraryVersion)

Get current library version of Spinnaker.

- [SPINNAKERC_API spinSystemGetTLNodeMap](#) ([spinSystem](#) hSystem, [spinNodeMapHandle](#) *phNodeMap)

Retrieves the transport layer nodemap from the system.

- [SPINNAKERC_API spinInterfaceListCreateEmpty](#) ([spinInterfaceList](#) *phInterfaceList)

Creates an empty interface list (interface lists created this way must be destroyed)

- [SPINNAKERC_API spinInterfaceListDestroy](#) ([spinInterfaceList](#) hInterfaceList)

Destroys an interface list.

- [SPINNAKERC_API spinInterfaceListGetSize](#) ([spinInterfaceList](#) hInterfaceList, [size_t](#) *pSize)

Retrieves the number of interfaces in an interface list.

- [SPINNAKERC_API spinInterfaceListGet](#) ([spinInterfaceList](#) hInterfaceList, [size_t](#) index, [spinInterface](#) *phInterface)

Retrieves an interface from an interface list using an index (interfaces retrieved this way must be released)

- [SPINNAKERC_API spinInterfaceListClear](#) ([spinInterfaceList](#) hInterfaceList)

Clears an interface list.

- [SPINNAKERC_API spinCameraListCreateEmpty](#) ([spinCameraList](#) *phCameraList)

Creates an empty camera list (camera lists created this way must be destroyed)

- [SPINNAKERC_API spinCameraListDestroy](#) ([spinCameraList](#) hCameraList)

Destroys a camera list.

- [SPINNAKERC_API spinCameraListGetSize](#) ([spinCameraList](#) hCameraList, [size_t](#) *pSize)

Retrieves the number of cameras on a camera list.

- [SPINNAKERC_API spinCameraListGet](#) ([spinCameraList](#) hCameraList, [size_t](#) index, [spinCamera](#) *phCamera)

Retrieves a camera from a camera list using an index.

- [SPINNAKERC_API spinCameraListClear](#) ([spinCameraList](#) hCameraList)

Clears a camera list.

- [SPINNAKERC_API spinCameraListRemove](#) ([spinCameraList](#) hCameraList, [size_t](#) index)

- Removes a camera from a camera list using its index.*

 - [SPINNAKERC_API spinCameraListAppend](#) ([spinCameraList](#) hCameraListBase, [spinCameraList](#) hCamera↔ListToAppend)

Appends all the cameras from one camera list to another.

 - [SPINNAKERC_API spinCameraListGetBySerial](#) ([spinCameraList](#) hCameraList, const char *pSerial, [spin↔Camera](#) *phCamera)

Retrieves a camera from a camera list using its serial number.

 - [SPINNAKERC_API spinCameraListRemoveBySerial](#) ([spinCameraList](#) hCameraList, const char *pSerial)

Removes a camera from a camera list using its serial number.

 - [SPINNAKERC_API spinInterfaceUpdateCameras](#) ([spinInterface](#) hInterface, [bool8_t](#) *pbChanged)

Checks whether any cameras have been connected or disconnected on an interface.

 - [SPINNAKERC_API spinInterfaceGetCameras](#) ([spinInterface](#) hInterface, [spinCameraList](#) hCameraList)

Retrieves a camera list from an interface; camera lists must be created and destroy.

 - [SPINNAKERC_API spinInterfaceGetCamerasEx](#) ([spinInterface](#) hInterface, [bool8_t](#) bUpdateCameras, [spin↔CameraList](#) hCameraList)

Retrieves a camera list from an interface; manually set whether to update the cameras; camera lists must be created and destroyed.

 - [SPINNAKERC_API spinInterfaceGetTLNodeMap](#) ([spinInterface](#) hInterface, [spinNodeMapHandle](#) *phNode↔Map)

Retrieves the transport layer nodemap from an interface.

 - [SPINNAKERC_API spinInterfaceRegisterDeviceArrivalEventHandler](#) ([spinInterface](#) hInterface, [spinDevice↔ArrivalEventHandler](#) hDeviceArrivalEventHandler)

Registers a device arrival event handler on an interface (event handlers registered in this way must be unregistered)

 - [SPINNAKERC_API spinInterfaceRegisterDeviceRemovalEventHandler](#) ([spinInterface](#) hInterface, [spin↔DeviceRemovalEventHandler](#) hDeviceRemovalEventHandler)

Registers a device removal event handler on an interface (event handlers registered in this way must be unregistered)

 - [SPINNAKERC_API spinInterfaceUnregisterDeviceArrivalEventHandler](#) ([spinInterface](#) hInterface, [spin↔DeviceArrivalEventHandler](#) hDeviceArrivalEventHandler)

Unregisters a device arrival event handler from an interface.

 - [SPINNAKERC_API spinInterfaceUnregisterDeviceRemovalEventHandler](#) ([spinInterface](#) hInterface, [spin↔DeviceRemovalEventHandler](#) hDeviceRemovalEventHandler)

Unregisters a device removal event handler from an interface.

 - [SPINNAKERC_API spinInterfaceRegisterInterfaceEventHandler](#) ([spinInterface](#) hInterface, [spinInterface↔EventHandler](#) hInterfaceEventHandler)

Registers an interface event handler (both device arrival and device removal) on an interface.

 - [SPINNAKERC_API spinInterfaceUnregisterInterfaceEventHandler](#) ([spinInterface](#) hInterface, [spinInterface↔EventHandler](#) hInterfaceEventHandler)

Unregisters an interface event handler from an interface.

 - [SPINNAKERC_API spinInterfaceRelease](#) ([spinInterface](#) hInterface)

Releases an interface.

 - [SPINNAKERC_API spinInterfaceIsInUse](#) ([spinInterface](#) hInterface, [bool8_t](#) *pbIsInUse)

Checks whether an interface is in use.

 - [SPINNAKERC_API spinInterfaceSendActionCommand](#) ([spinInterface](#) hInterface, [size_t](#) iDeviceKey, [size_t](#)↔iGroupKey, [size_t](#) iGroupMask, [size_t](#) iActionTime, [size_t](#) *piResultSize, [actionCommandResult](#) results[])

Broadcast an Action Command to all devices on interface.

 - [SPINNAKERC_API spinCameraInit](#) ([spinCamera](#) hCamera)

Initializes a camera, allowing for much more interaction.

 - [SPINNAKERC_API spinCameraDeInit](#) ([spinCamera](#) hCamera)

Deinitializes a camera, greatly reducing functionality.

 - [SPINNAKERC_API spinCameraGetNodeMap](#) ([spinCamera](#) hCamera, [spinNodeMapHandle](#) *phNodeMap)

Retrieves the GenICam nodemap from a camera.

 - [SPINNAKERC_API spinCameraGetTLDeviceNodeMap](#) ([spinCamera](#) hCamera, [spinNodeMapHandle](#) *ph↔NodeMap)

- Retrieves the transport layer device nodemap from a camera.*
- [SPINNAKERC_API spinCameraGetTLStreamNodeMap](#) ([spinCamera](#) hCamera, [spinNodeMapHandle](#) *phNodeMap)
- Retrieves the transport layer stream nodemap from a camera.*
- [SPINNAKERC_API spinCameraGetAccessMode](#) ([spinCamera](#) hCamera, [spinAccessMode](#) *pAccessMode)
- Retrieves the access mode of a camera (as an enum, spinAccessMode)*
- [SPINNAKERC_API spinCameraReadPort](#) ([spinCamera](#) hCamera, uint64_t iAddress, void *pBuffer, size_t iSize)
- [SPINNAKERC_API spinCameraWritePort](#) ([spinCamera](#) hCamera, uint64_t iAddress, void *pBuffer, size_t iSize)
- [SPINNAKERC_API spinCameraBeginAcquisition](#) ([spinCamera](#) hCamera)
- Has a camera start acquiring images.*
- [SPINNAKERC_API spinCameraEndAcquisition](#) ([spinCamera](#) hCamera)
- Has a camera stop acquiring images.*
- [SPINNAKERC_API spinCameraGetNextImage](#) ([spinCamera](#) hCamera, [spinImage](#) *phImage)
- Retrieves an image from a camera.*
- [SPINNAKERC_API spinCameraGetNextImageEx](#) ([spinCamera](#) hCamera, uint64_t grabTimeout, [spinImage](#) *phImage)
- Retrieves an image from a camera; manually set the timeout in milliseconds.*
- [SPINNAKERC_API spinCameraGetUniqueID](#) ([spinCamera](#) hCamera, char *pBuf, size_t *pBufLen)
- Retrieves a unique identifier for a camera.*
- [SPINNAKERC_API spinCameralStreaming](#) ([spinCamera](#) hCamera, bool8_t *pbIsStreaming)
- Checks whether a camera is currently acquiring images.*
- [SPINNAKERC_API spinCameraGetGuiXml](#) ([spinCamera](#) hCamera, char *pBuf, size_t *pBufLen)
- Retrieves the GUI XML from a camera.*
- [SPINNAKERC_API spinCameraRegisterDeviceEventHandler](#) ([spinCamera](#) hCamera, [spinDeviceEventHandler](#) hDeviceEventHandler)
- Registers a universal device event handler (every device event type) to a camera.*
- [SPINNAKERC_API spinCameraRegisterDeviceEventHandlerEx](#) ([spinCamera](#) hCamera, [spinDeviceEventHandler](#) hDeviceEventHandler, const char *pName)
- Registers a specific device event handler (only one device event type) to a camera.*
- [SPINNAKERC_API spinCameraUnregisterDeviceEventHandler](#) ([spinCamera](#) hCamera, [spinDeviceEventHandler](#) hDeviceEventHandler)
- Unregisters a device event handler from a camera.*
- [SPINNAKERC_API spinCameraRegisterImageEventHandler](#) ([spinCamera](#) hCamera, [spinImageEventHandler](#) hImageEventHandler)
- Registers an image event handler to a camera.*
- [SPINNAKERC_API spinCameraUnregisterImageEventHandler](#) ([spinCamera](#) hCamera, [spinImageEventHandler](#) hImageEventHandler)
- Unregisters an image event handler from a camera.*
- [SPINNAKERC_API spinCameraRelease](#) ([spinCamera](#) hCamera)
- Releases a camera.*
- [SPINNAKERC_API spinCameralValid](#) ([spinCamera](#) hCamera, bool8_t *pbValid)
- Checks whether a camera is still valid for use.*
- [SPINNAKERC_API spinCameralInitialized](#) ([spinCamera](#) hCamera, bool8_t *pbInit)
- Checks whether a camera is currently initialized.*
- [SPINNAKERC_API spinCameraDiscoverMaxPacketSize](#) ([spinCamera](#) hCamera, unsigned int *pMaxPacketSize)
- Returns the largest packet size that can be safely used on the interface that device is connected to.*
- [SPINNAKERC_API spinCameraForceIP](#) ()
- Forces the camera to be on the same subnet as its corresponding interface.*
- [SPINNAKERC_API spinImageCreateEmpty](#) ([spinImage](#) *phImage)

- Creates an empty image; images created this way must be destroyed.*

 - [SPINNAKERC_API spinImageCreate](#) ([spinImage](#) hSrcImage, [spinImage](#) *phDestImage)

Creates an image from another; images created this way must be destroyed.

 - [SPINNAKERC_API spinImageCreateEx](#) ([spinImage](#) *phImage, [size_t](#) width, [size_t](#) height, [size_t](#) offsetX, [size_t](#) offsetY, [spinPixelFormatEnums](#) pixelFormat, void *pData)

Creates an image with some set properties; images created this way must be destroyed.

 - [SPINNAKERC_API spinImageDestroy](#) ([spinImage](#) hImage)

Destroys an image.

 - [SPINNAKERC_API spinImageSetDefaultColorProcessing](#) ([spinColorProcessingAlgorithm](#) algorithm)

Sets the default color processing algorithm of all images (if not otherwise set)

 - [SPINNAKERC_API spinImageGetDefaultColorProcessing](#) ([spinColorProcessingAlgorithm](#) *pAlgorithm)

Retrieves the default color processing algorithm.

 - [SPINNAKERC_API spinImageGetColorProcessing](#) ([spinImage](#) hImage, [spinColorProcessingAlgorithm](#) *pAlgorithm)

Retrieves the color processing algorithm of a specific image.

 - [SPINNAKERC_API spinImageConvert](#) ([spinImage](#) hSrcImage, [spinPixelFormatEnums](#) pixelFormat, [spinImage](#) hDestImage)

Converts the pixel format of one image into a new image.

 - [SPINNAKERC_API spinImageConvertEx](#) ([spinImage](#) hSrcImage, [spinPixelFormatEnums](#) pixelFormat, [spinColorProcessingAlgorithm](#) algorithm, [spinImage](#) hDestImage)

Converts the pixel format and color processing algorithm of one image into a new image.

 - [SPINNAKERC_API spinImageReset](#) ([spinImage](#) hImage, [size_t](#) width, [size_t](#) height, [size_t](#) offsetX, [size_t](#) offsetY, [spinPixelFormatEnums](#) pixelFormat)

Resets an image with some set properties.

 - [SPINNAKERC_API spinImageResetEx](#) ([spinImage](#) hImage, [size_t](#) width, [size_t](#) height, [size_t](#) offsetX, [size_t](#) offsetY, [spinPixelFormatEnums](#) pixelFormat, void *pData)

Resets an image with some set properties and image data.

 - [SPINNAKERC_API spinImageGetID](#) ([spinImage](#) hImage, [uint64_t](#) *pId)

Retrieves the ID of an image.

 - [SPINNAKERC_API spinImageGetData](#) ([spinImage](#) hImage, void **ppData)

Retrieves the image data of an image.

 - [SPINNAKERC_API spinImageGetPrivateData](#) ([spinImage](#) hImage, void **ppData)

Retrieves the private data of an image.

 - [SPINNAKERC_API spinImageGetBufferSize](#) ([spinImage](#) hImage, [size_t](#) *pSize)

Retrieves the buffer size of an image.

 - [SPINNAKERC_API spinImageDeepCopy](#) ([spinImage](#) hSrcImage, [spinImage](#) hDestImage)

Creates a deep copy of an image (the destination image must be created as an empty image prior to the deep copy)

 - [SPINNAKERC_API spinImageGetWidth](#) ([spinImage](#) hImage, [size_t](#) *pWidth)

Retrieves the width of an image.

 - [SPINNAKERC_API spinImageGetHeight](#) ([spinImage](#) hImage, [size_t](#) *pHeight)

Retrieves the height of an image.

 - [SPINNAKERC_API spinImageGetOffsetX](#) ([spinImage](#) hImage, [size_t](#) *pOffsetX)

Retrieves the offset of an image along its X axis.

 - [SPINNAKERC_API spinImageGetOffsetY](#) ([spinImage](#) hImage, [size_t](#) *pOffsetY)

Retrieves the offset of an image along its Y axis.

 - [SPINNAKERC_API spinImageGetPaddingX](#) ([spinImage](#) hImage, [size_t](#) *pPaddingX)

Retrieves the padding of an image along its X axis.

 - [SPINNAKERC_API spinImageGetPaddingY](#) ([spinImage](#) hImage, [size_t](#) *pPaddingY)

Retrieves the padding of an image along its Y axis.

 - [SPINNAKERC_API spinImageGetFrameID](#) ([spinImage](#) hImage, [uint64_t](#) *pFrameID)

Retrieves the frame ID of an image.

- [SPINNAKERC_API spinImageGetTimeStamp](#) ([spinImage](#) hImage, [uint64_t](#) *pTimeStamp)
Retrieves the timestamp of an image.
- [SPINNAKERC_API spinImageGetPayloadType](#) ([spinImage](#) hImage, [size_t](#) *pPayloadType)
Retrieves the payload type of an image (as an enum, [spinPayloadTypeInfolDs](#))
- [SPINNAKERC_API spinImageGetTLPayloadType](#) ([spinImage](#) hImage, [spinPayloadTypeInfolDs](#) *pPayloadType)
Retrieves the transport layer payload type of an image (as an enum, [spinPayloadTypeInfolDs](#))
- [SPINNAKERC_API spinImageGetPixelFormat](#) ([spinImage](#) hImage, [spinPixelFormatEnums](#) *pPixelFormat)
Retrieves the pixel format of an image (as an enum, [spinPixelFormatEnums](#))
- [SPINNAKERC_API spinImageGetTLPixelFormat](#) ([spinImage](#) hImage, [uint64_t](#) *pPixelFormat)
Retrieves the transport layer pixel format of an image (as an unsigned integer)
- [SPINNAKERC_API spinImageGetTLPixelFormatNamespace](#) ([spinImage](#) hImage, [spinPixelFormatNamespaceID](#) *pPixelFormatNamespace)
Retrieves the transport layer pixel format namespace of an image (as an enum, [spinPixelFormatNamespaceID](#))
- [SPINNAKERC_API spinImageGetPixelFormatName](#) ([spinImage](#) hImage, [char](#) *pBuf, [size_t](#) *pBufLen)
Retrieves the pixel format of an image (as a symbolic)
- [SPINNAKERC_API spinImageIsIncomplete](#) ([spinImage](#) hImage, [bool8_t](#) *pIsIncomplete)
Checks whether an image is incomplete.
- [SPINNAKERC_API spinImageGetValidPayloadSize](#) ([spinImage](#) hImage, [size_t](#) *pSize)
Retrieves the valid payload size of an image.
- [SPINNAKERC_API spinImageSave](#) ([spinImage](#) hImage, [const char](#) *pFilename, [spinImageFileFormat](#) format)
Saves an image using a specified file format (using an enum, [spinImageFileFormat](#))
- [SPINNAKERC_API spinImageSaveFromExt](#) ([spinImage](#) hImage, [const char](#) *pFilename)
Saves an image using a specified file format (using the extension of the filename)
- [SPINNAKERC_API spinImageSavePng](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinPNGOption](#) *pOption)
Saves an image as a PNG image.
- [SPINNAKERC_API spinImageSavePpm](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinPPMOption](#) *pOption)
Saves an image as a PPM image.
- [SPINNAKERC_API spinImageSavePgm](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinPGMOption](#) *pOption)
Saves an image as an PGM image.
- [SPINNAKERC_API spinImageSaveTiff](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinTIFFOption](#) *pOption)
Saves an image as a TIFF image.
- [SPINNAKERC_API spinImageSaveJpeg](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinJPEGOption](#) *pOption)
Saves an image as a JPEG image.
- [SPINNAKERC_API spinImageSaveJpg2](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinJPG2Option](#) *pOption)
Saves an image as a JPEG 2000 image.
- [SPINNAKERC_API spinImageSaveBmp](#) ([spinImage](#) hImage, [const char](#) *pFilename, [const spinBMPOption](#) *pOption)
Saves an image as a BMP image.
- [SPINNAKERC_API spinImageGetChunkLayoutID](#) ([spinImage](#) hImage, [uint64_t](#) *pId)
Retrieves the chunk layout ID of an image.
- [SPINNAKERC_API spinImageCalculateStatistics](#) ([spinImage](#) hImage, [const spinImageStatistics](#) hStatistics)
Calculates the image statistics of an image.
- [SPINNAKERC_API spinImageGetStatus](#) ([spinImage](#) hImage, [spinImageStatus](#) *pStatus)
Retrieves the image status of an image.

- [SPINNAKERC_API spinImageGetStatusDescription](#) ([spinImageStatus](#) status, char *pBuf, size_t *pBufLen)
Retrieves the description of image status.
- [SPINNAKERC_API spinImageRelease](#) ([spinImage](#) hImage)
Releases an image.
- [SPINNAKERC_API spinImageHasCRC](#) ([spinImage](#) hImage, [bool8_t](#) *pbHasCRC)
Checks whether an image has CRC.
- [SPINNAKERC_API spinImageCheckCRC](#) ([spinImage](#) hImage, [bool8_t](#) *pbCheckCRC)
Checks whether the CRC of an image is correct.
- [SPINNAKERC_API spinImageGetBitsPerPixel](#) ([spinImage](#) hImage, size_t *pBitsPerPixel)
Retrieves the number of bits per pixel of an image.
- [SPINNAKERC_API spinImageGetSize](#) ([spinImage](#) hImage, size_t *pImageSize)
Retrieves the size of an image.
- [SPINNAKERC_API spinImageGetStride](#) ([spinImage](#) hImage, size_t *pStride)
Retrieves the stride of an image.
- [SPINNAKERC_API spinDeviceEventHandlerCreate](#) ([spinDeviceEventHandler](#) *phDeviceEventHandler, [spinDeviceEventFunction](#) pFunction, void *pUserData)
Creates a device event handler.
- [SPINNAKERC_API spinDeviceEventHandlerDestroy](#) ([spinDeviceEventHandler](#) hDeviceEventHandler)
Destroys a device event handler.
- [SPINNAKERC_API spinImageEventHandlerCreate](#) ([spinImageEventHandler](#) *phImageEventHandler, [spinImageEventFunction](#) pFunction, void *pUserData)
Creates an image event handler.
- [SPINNAKERC_API spinImageEventHandlerDestroy](#) ([spinImageEventHandler](#) hImageEventHandler)
Destroys an image event handler.
- [SPINNAKERC_API spinDeviceArrivalEventHandlerCreate](#) ([spinDeviceArrivalEventHandler](#) *phDeviceArrivalEventHandler, [spinArrivalEventFunction](#) pFunction, void *pUserData)
Creates a device arrival event handler.
- [SPINNAKERC_API spinDeviceArrivalEventHandlerDestroy](#) ([spinDeviceArrivalEventHandler](#) hDeviceArrivalEventHandler)
Destroys a device arrival event handler.
- [SPINNAKERC_API spinDeviceRemovalEventHandlerCreate](#) ([spinDeviceRemovalEventHandler](#) *phDeviceRemovalEventHandler, [spinRemovalEventFunction](#) pFunction, void *pUserData)
Creates a device removal event handler.
- [SPINNAKERC_API spinDeviceRemovalEventHandlerDestroy](#) ([spinDeviceRemovalEventHandler](#) hDeviceRemovalEventHandler)
Destroys a device removal event handler.
- [SPINNAKERC_API spinInterfaceEventHandlerCreate](#) ([spinInterfaceEventHandler](#) *phInterfaceEventHandler, [spinArrivalEventFunction](#) pArrivalFunction, [spinRemovalEventFunction](#) pRemovalFunction, void *pUserData)
Creates an interface event handler (both device arrival and device removal)
- [SPINNAKERC_API spinInterfaceEventHandlerDestroy](#) ([spinInterfaceEventHandler](#) hInterfaceEventHandler)
Destroys an interface event handler (both device arrival and device removal)
- [SPINNAKERC_API spinLogEventHandlerCreate](#) ([spinLogEventHandler](#) *phLogEventHandler, [spinLogEventFunction](#) pFunction, void *pUserData)
Creates a log event handler.
- [SPINNAKERC_API spinLogEventHandlerDestroy](#) ([spinLogEventHandler](#) hLogEventHandler)
Destroys a log event handler.
- [SPINNAKERC_API spinImageStatisticsCreate](#) ([spinImageStatistics](#) *phStatistics)
Creates an image statistics context.
- [SPINNAKERC_API spinImageStatisticsDestroy](#) ([spinImageStatistics](#) hStatistics)
Destroys an image statistics context.
- [SPINNAKERC_API spinImageStatisticsEnableAll](#) ([spinImageStatistics](#) hStatistics)

- Enables all channels of an image statistics context.*

 - [SPINNAKERC_API spinImageStatisticsDisableAll](#) ([spinImageStatistics](#) [hStatistics](#))

Disables all channels of an image statistics context.

 - [SPINNAKERC_API spinImageStatisticsEnableGreyOnly](#) ([spinImageStatistics](#) [hStatistics](#))

Disables all channels of an image statistics context except grey-scale.

 - [SPINNAKERC_API spinImageStatisticsEnableRgbOnly](#) ([spinImageStatistics](#) [hStatistics](#))

Disables all channels of an image statistics context except red, blue, and green.

 - [SPINNAKERC_API spinImageStatisticsEnableHslOnly](#) ([spinImageStatistics](#) [hStatistics](#))

Disables all channels of an image statistics context except hue, saturation, and lightness.

 - [SPINNAKERC_API spinImageStatisticsGetChannelStatus](#) ([spinImageStatistics](#) [hStatistics](#), [spinStatisticsChannel](#) [channel](#), [bool8_t](#) [*pbEnabled](#))

Checks whether an image statistics context is enabled.

 - [SPINNAKERC_API spinImageStatisticsSetChannelStatus](#) ([spinImageStatistics](#) [hStatistics](#), [spinStatisticsChannel](#) [channel](#), [bool8_t](#) [bEnable](#))

Sets the status of an image statistics channel.

 - [SPINNAKERC_API spinImageStatisticsGetRange](#) ([spinImageStatistics](#) [hStatistics](#), [spinStatisticsChannel](#) [channel](#), [unsigned int](#) [*pMin](#), [unsigned int](#) [*pMax](#))

Retrieves the range of an image statistics channel.

 - [SPINNAKERC_API spinImageStatisticsGetPixelValueRange](#) ([spinImageStatistics](#) [hStatistics](#), [spinStatisticsChannel](#) [channel](#), [unsigned int](#) [*pMin](#), [unsigned int](#) [*pMax](#))

Retrieves the pixel value range of an image statistics channel.

 - [SPINNAKERC_API spinImageStatisticsGetNumPixelValues](#) ([spinImageStatistics](#) [hStatistics](#), [spinStatisticsChannel](#) [channel](#), [unsigned int](#) [*pNumValues](#))

Retrieves the number of pixel values of an image statistics channel.

 - [SPINNAKERC_API spinImageStatisticsGetMean](#) ([spinImageStatistics](#) [hStatistics](#), [spinStatisticsChannel](#) [channel](#), [float](#) [*pMean](#))

Retrieves the mean of pixel values of an image statistics channel.

 - [SPINNAKERC_API spinImageStatisticsGetHistogram](#) ([spinImageStatistics](#) [hStatistics](#), [spinStatisticsChannel](#) [channel](#), [int](#) [**ppHistogram](#))

Retrieves a histogram of an image statistics channel.

 - [SPINNAKERC_API spinImageStatisticsGetAll](#) ([spinImageStatistics](#) [hStatistics](#), [spinStatisticsChannel](#) [channel](#), [unsigned int](#) [*pRangeMin](#), [unsigned int](#) [*pRangeMax](#), [unsigned int](#) [*pPixelValueMin](#), [unsigned int](#) [*pPixelValueMax](#), [unsigned int](#) [*pNumPixelValues](#), [float](#) [*pPixelValueMean](#), [int](#) [**ppHistogram](#))

Retrieves all available information of an image statistics channel.

 - [SPINNAKERC_API spinLogDataGetCategoryName](#) ([spinLogEventData](#) [hLogEventData](#), [char](#) [*pBuf](#), [size_t](#) [*pBufLen](#))

Retrieves the category name of a log event.

 - [SPINNAKERC_API spinLogDataGetPriority](#) ([spinLogEventData](#) [hLogEventData](#), [int64_t](#) [*pValue](#))

Retrieves the priority of a log event.

 - [SPINNAKERC_API spinLogDataGetPriorityName](#) ([spinLogEventData](#) [hLogEventData](#), [char](#) [*pBuf](#), [size_t](#) [*pBufLen](#))

Retrieves the priority name of a log event.

 - [SPINNAKERC_API spinLogDataGetTimestamp](#) ([spinLogEventData](#) [hLogEventData](#), [char](#) [*pBuf](#), [size_t](#) [*pBufLen](#))

Retrieves the timestamp of a log event.

 - [SPINNAKERC_API spinLogDataGetNDC](#) ([spinLogEventData](#) [hLogEventData](#), [char](#) [*pBuf](#), [size_t](#) [*pBufLen](#))

Retrieves the NDC of a log event.

 - [SPINNAKERC_API spinLogDataGetThreadName](#) ([spinLogEventData](#) [hLogEventData](#), [char](#) [*pBuf](#), [size_t](#) [*pBufLen](#))

Retrieves the thread name of a log event.

 - [SPINNAKERC_API spinLogDataGetLogMessage](#) ([spinLogEventData](#) [hLogEventData](#), [char](#) [*pBuf](#), [size_t](#) [*pBufLen](#))

- Retrieves the log message of a log event.
- [SPINNAKERC_API spinDeviceEventGetId](#) ([spinDeviceEventData](#) hDeviceEventData, [uint64_t](#) *pEventId)
Retrieves the event ID of a device event.
- [SPINNAKERC_API spinDeviceEventGetPayloadData](#) ([spinDeviceEventData](#) hDeviceEventData, [const uint8_t](#) *pBuf, [size_t](#) *pBufSize)
Retrieves the payload data of a device event.
- [SPINNAKERC_API spinDeviceEventGetPayloadDataSize](#) ([spinDeviceEventData](#) hDeviceEventData, [size_t](#) *pBufSize)
Retrieves the payload data size of a device event.
- [SPINNAKERC_API spinDeviceEventGetName](#) ([spinDeviceEventData](#) hDeviceEventData, [char](#) *pBuf, [size_t](#) *pBufLen)
Retrieves the event name of a device event.
- [SPINNAKERC_API spinImageChunkDataGetIntValue](#) ([spinImage](#) hImage, [const char](#) *pName, [int64_t](#) *pValue)
Retrieves the integer value of a device event.
- [SPINNAKERC_API spinImageChunkDataGetFloatValue](#) ([spinImage](#) hImage, [const char](#) *pName, [double](#) *pValue)
Retrieves the float value of a device event.

6.5.1 Function Documentation

6.5.1.1 spinCameraForceIP()

[SPINNAKERC_API](#) spinCameraForceIP ()


Forces the camera to be on the same subnet as its corresponding interface.

Returns


spinError The error code; returns SPINNAKER_ERR_SUCCESS (or 0) for no error

6.6 include/spinc/SpinnakerDefsC.h File Reference

Include dependency graph for SpinnakerDefsC.h:



This graph shows which files directly or indirectly include this file:



Data Structures

- struct [spinPNGOption](#)
Options for saving PNG images.
- struct [spinPPMOption](#)
Options for saving PPM images.
- struct [spinPGMOption](#)
Options for saving PGM images.
- struct [spinTIFFOption](#)
Options for saving TIFF images.
- struct [spinJPEGOption](#)
Options for saving JPEG images.
- struct [spinJPG2Option](#)
Options for saving JPEG 2000 images.
- struct [spinBMPOption](#)
Options for saving BMP images.
- struct [spinMJPEGOption](#)
Options for saving MJPG videos.
- struct [spinH264Option](#)
Options for saving H264 videos.
- struct [spinAVIOption](#)
Options for saving uncompressed videos.
- struct [spinLibraryVersion](#)
Provides easier access to the current version of Spinnaker.
- struct [actionCommandResult](#)
Action Command Result.

Typedefs

- typedef uint8_t [bool8_t](#)
- typedef void * [spinSystem](#)
Handle for system functionality.
- typedef void * [spinInterfaceList](#)
Handle for interface list functionality.
- typedef void * [spinInterface](#)
Handle for interface functionality.
- typedef void * [spinCameraList](#)
Handle for interface functionality.
- typedef void * [spinCamera](#)
Handle for camera functionality.

- typedef void * [spinImage](#)
Handle for image functionality.
- typedef void * [spinImageStatistics](#)
Handle for image statistics functionality.
- typedef void * [spinDeviceEventHandler](#)
Handle for device event handler functionality.
- typedef void * [spinImageEventHandler](#)
Handle for image event handler functionality.
- typedef void * [spinDeviceArrivalEventHandler](#)
Handle for arrival event handler functionality.
- typedef void * [spinDeviceRemovalEventHandler](#)
Handle for removal event handler functionality.
- typedef void * [spinInterfaceEventHandler](#)
Handle for interface event handler functionality.
- typedef void * [spinLogEventHandler](#)
Handle for logging event handler functionality.
- typedef void * [spinLogEventData](#)
Handle for logging event data functionality.
- typedef void * [spinDeviceEventData](#)
Handle for device event data functionality.
- typedef void * [spinVideo](#)
Handle for video recording functionality.
- typedef void(* [spinDeviceEventFunction](#)) (const [spinDeviceEventData](#) hEventData, const char *pEventName, void *pUserData)
Function signatures are used to create and trigger callbacks and events.
- typedef void(* [spinImageEventFunction](#)) (const [spinImage](#) hImage, void *pUserData)
- typedef void(* [spinArrivalEventFunction](#)) (uint64_t deviceSerialNumber, void *pUserData)
- typedef void(* [spinRemovalEventFunction](#)) (uint64_t deviceSerialNumber, void *pUserData)
- typedef void(* [spinLogEventFunction](#)) (const [spinLogEventData](#) hEventData, void *pUserData)

Enumerations

- enum [spinError](#) {
[SPINNAKER_ERR_SUCCESS](#) = 0,
[SPINNAKER_ERR_ERROR](#) = -1001,
[SPINNAKER_ERR_NOT_INITIALIZED](#) = -1002,
[SPINNAKER_ERR_NOT_IMPLEMENTED](#) = -1003,
[SPINNAKER_ERR_RESOURCE_IN_USE](#) = -1004,
[SPINNAKER_ERR_ACCESS_DENIED](#) = -1005,
[SPINNAKER_ERR_INVALID_HANDLE](#) = -1006,
[SPINNAKER_ERR_INVALID_ID](#) = -1007,
[SPINNAKER_ERR_NO_DATA](#) = -1008,
[SPINNAKER_ERR_INVALID_PARAMETER](#) = -1009,
[SPINNAKER_ERR_IO](#) = -1010,
[SPINNAKER_ERR_TIMEOUT](#) = -1011,
[SPINNAKER_ERR_ABORT](#) = -1012,
[SPINNAKER_ERR_INVALID_BUFFER](#) = -1013,
[SPINNAKER_ERR_NOT_AVAILABLE](#) = -1014,
[SPINNAKER_ERR_INVALID_ADDRESS](#) = -1015,
[SPINNAKER_ERR_BUFFER_TOO_SMALL](#) = -1016,
[SPINNAKER_ERR_INVALID_INDEX](#) = -1017,
[SPINNAKER_ERR_PARSING_CHUNK_DATA](#) = -1018,
[SPINNAKER_ERR_INVALID_VALUE](#) = -1019,

```

SPINNAKER_ERR_RESOURCE_EXHAUSTED = -1020,
SPINNAKER_ERR_OUT_OF_MEMORY = -1021,
SPINNAKER_ERR_BUSY = -1022,
GENICAM_ERR_INVALID_ARGUMENT = -2001,
GENICAM_ERR_OUT_OF_RANGE = -2002,
GENICAM_ERR_PROPERTY = -2003,
GENICAM_ERR_RUN_TIME = -2004,
GENICAM_ERR_LOGICAL = -2005,
GENICAM_ERR_ACCESS = -2006,
GENICAM_ERR_TIMEOUT = -2007,
GENICAM_ERR_DYNAMIC_CAST = -2008,
GENICAM_ERR_GENERIC = -2009,
GENICAM_ERR_BAD_ALLOCATION = -2010,
SPINNAKER_ERR_IM_CONVERT = -3001,
SPINNAKER_ERR_IM_COPY = -3002,
SPINNAKER_ERR_IM_MALLOC = -3003,
SPINNAKER_ERR_IM_NOT_SUPPORTED = -3004,
SPINNAKER_ERR_IM_HISTOGRAM_RANGE = -3005,
SPINNAKER_ERR_IM_HISTOGRAM_MEAN = -3006,
SPINNAKER_ERR_IM_MIN_MAX = -3007,
SPINNAKER_ERR_IM_COLOR_CONVERSION = -3008,
SPINNAKER_ERR_CUSTOM_ID = -10000 }

```

The error codes used in Spinnaker C.

- enum `spinColorProcessingAlgorithm` {
`DEFAULT`,
`NO_COLOR_PROCESSING`,
`NEAREST_NEIGHBOR`,
`NEAREST_NEIGHBOR_AVG`,
`BILINEAR`,
`EDGE_SENSING`,
`HQ_LINEAR`,
`IPP`,
`DIRECTIONAL_FILTER`,
`RIGOROUS`,
`WEIGHTED_DIRECTIONAL_FILTER` }

Color processing algorithms.

- enum `spinStatisticsChannel` {
`GREY`,
`RED`,
`GREEN`,
`BLUE`,
`HUE`,
`SATURATION`,
`LIGHTNESS`,
`NUM_STATISTICS_CHANNELS` }

Channels that allow statistics to be calculated.

- enum `spinImageFileFormat` {
`FROM_FILE_EXT` = -1,
`PGM`,
`PPM`,
`BMP`,
`JPEG`,
`JPEG2000`,
`TIFF`,
`PNG`,
`RAW`,
`IMAGE_FILE_FORMAT_FORCE_32BITS` = 0x7FFFFFFF }

File formats to be used for saving images to disk.

- enum `spinPixelFormatNamespaceID` {
`SPINNAKER_PIXELFORMAT_NAMESPACE_UNKNOWN` = 0,
`SPINNAKER_PIXELFORMAT_NAMESPACE_GEV` = 1,
`SPINNAKER_PIXELFORMAT_NAMESPACE_IIDC` = 2,
`SPINNAKER_PIXELFORMAT_NAMESPACE_PFNC_16BIT` = 3,
`SPINNAKER_PIXELFORMAT_NAMESPACE_PFNC_32BIT` = 4,
`SPINNAKER_PIXELFORMAT_NAMESPACE_CUSTOM_ID` = 1000 }

This enum represents the namespace in which the TL specific pixel format resides.

- enum `spinImageStatus` {
`IMAGE_UNKNOWN_ERROR` = -1,
`IMAGE_NO_ERROR` = 0,
`IMAGE_CRC_CHECK_FAILED` = 1,
`IMAGE_DATA_OVERFLOW` = 2,
`IMAGE_MISSING_PACKETS` = 3,
`IMAGE_LEADER_BUFFER_SIZE_INCONSISTENT` = 4,
`IMAGE_TRAILER_BUFFER_SIZE_INCONSISTENT` = 5,
`IMAGE_PACKETID_INCONSISTENT` = 6,
`IMAGE_MISSING_LEADER` = 7,
`IMAGE_MISSING_TRAILER` = 8,
`IMAGE_DATA_INCOMPLETE` = 9,
`IMAGE_INFO_INCONSISTENT` = 10,
`IMAGE_CHUNK_DATA_INVALID` = 11,
`IMAGE_NO_SYSTEM_RESOURCES` = 12 }

Status of images returned from `spinImageGetStatus()` call.

- enum `spinnakerLogLevel` {
`LOG_LEVEL_OFF` = -1,
`LOG_LEVEL_FATAL` = 0,
`LOG_LEVEL_ALERT` = 100,
`LOG_LEVEL_CRIT` = 200,
`LOG_LEVEL_ERROR` = 300,
`LOG_LEVEL_WARN` = 400,
`LOG_LEVEL_NOTICE` = 500,
`LOG_LEVEL_INFO` = 600,
`LOG_LEVEL_DEBUG` = 700,
`LOG_LEVEL_NOTSET` = 800 }

log levels

- enum `spinPayloadTypeInfoIDs` {
`PAYLOAD_TYPE_UNKNOWN` = 0,
`PAYLOAD_TYPE_IMAGE` = 1,
`PAYLOAD_TYPE_RAW_DATA` = 2,
`PAYLOAD_TYPE_FILE` = 3,
`PAYLOAD_TYPE_CHUNK_DATA` = 4,
`PAYLOAD_TYPE_JPEG` = 5,
`PAYLOAD_TYPE_JPEG2000` = 6,
`PAYLOAD_TYPE_H264` = 7,
`PAYLOAD_TYPE_CHUNK_ONLY` = 8,
`PAYLOAD_TYPE_DEVICE_SPECIFIC` = 9,
`PAYLOAD_TYPE_MULTI_PART` = 10,
`PAYLOAD_TYPE_CUSTOM_ID` = 1000,
`PAYLOAD_TYPE_EXTENDED_CHUNK` = 1001 }
- enum `spinCompressionMethod` {
`NONE` = 1,
`PACKBITS`,
`DEFLATE`,
`ADOBE_DEFLATE`,
`CCITTFAX3`,

```
CCITTFAX4,
LZW,
JPG }
```

Compression method used in saving TIFF images in the [spinTIFFOption](#) struct.

- enum [actionCommandStatus](#) {
[ACTION_COMMAND_STATUS_OK](#) = 0,
[ACTION_COMMAND_STATUS_NO_REF_TIME](#) = 0x8013,
[ACTION_COMMAND_STATUS_OVERFLOW](#) = 0x8015,
[ACTION_COMMAND_STATUS_ACTION_LATE](#) = 0x8016,
[ACTION_COMMAND_STATUS_ERROR](#) = 0x8FFF }


Possible Status Codes Returned from Action Command.

Variables


- static const [bool8_t False](#) = 0
- static const [bool8_t True](#) = 1

6.7 include/spinc/SpinnakerGenApiC.h File Reference

Include dependency graph for SpinnakerGenApiC.h:



This graph shows which files directly or indirectly include this file:



Functions

- **SPINNAKERC_API spinNodeMapGetNode** (**spinNodeMapHandle** hNodeMap, const char *pName, **spinNodeHandle** *phNode)
Retrieves a node from the nodemap by name.
- **SPINNAKERC_API spinNodeMapGetNumNodes** (**spinNodeMapHandle** hNodeMap, size_t *pValue)
Gets the number of nodes in the map.
- **SPINNAKERC_API spinNodeMapGetNodeByIndex** (**spinNodeMapHandle** hNodeMap, size_t index, **spinNodeHandle** *phNode)
Retrieves a node from the nodemap by index.
- **SPINNAKERC_API spinNodeMapPoll** (**spinNodeMapHandle** hNodeMap, int64_t timestamp)
Fires nodes which have a polling time.
- **SPINNAKERC_API spinNodesImplemented** (**spinNodeHandle** hNode, bool8_t *pbResult)
Checks whether a node is implemented.
- **SPINNAKERC_API spinNodesReadable** (**spinNodeHandle** hNode, bool8_t *pbResult)
Checks whether a node is readable.
- **SPINNAKERC_API spinNodesWritable** (**spinNodeHandle** hNode, bool8_t *pbResult)
Checks whether a node is writable.
- **SPINNAKERC_API spinNodesAvailable** (**spinNodeHandle** hNode, bool8_t *pbResult)
Checks whether a node is available.
- **SPINNAKERC_API spinNodesEqual** (**spinNodeHandle** hNodeFirst, **spinNodeHandle** hNodeSecond, bool8_t *pbResult)
Checks whether two nodes are equal.
- **SPINNAKERC_API spinNodeGetAccessMode** (**spinNodeHandle** hNode, **spinAccessMode** *pAccessMode)
Retrieves the access mode of a node (as an enum, spinAccessMode)
- **SPINNAKERC_API spinNodeGetName** (**spinNodeHandle** hNode, char *pBuf, size_t *pBufLen)
Retrieves the name of a node (no whitespace)
- **SPINNAKERC_API spinNodeGetNameSpace** (**spinNodeHandle** hNode, **spinNameSpace** *pNamespace)
Retrieve the namespace of a node (as an enum, spinNameSpace)
- **SPINNAKERC_API spinNodeGetVisibility** (**spinNodeHandle** hNode, **spinVisibility** *pVisibility)
Retrieves the recommended visibility of a node (as an enum, spinVisibility)
- **SPINNAKERC_API spinNodeInvalidateNode** (**spinNodeHandle** hNode)
Invalidates a node in case its values may have changed, rendering it no longer valid.
- **SPINNAKERC_API spinNodeGetCachingMode** (**spinNodeHandle** hNode, **spinCachingMode** *pCachingMode)

- Retrieves the caching mode of a node (as an enum, spinCachingMode)*
- [SPINNAKERC_API spinNodeGetToolTip](#) (spinNodeHandle hNode, char *pBuf, size_t *pBufLen)
Retrieves a short description of a node.
- [SPINNAKERC_API spinNodeGetDescription](#) (spinNodeHandle hNode, char *pBuf, size_t *pBufLen)
Retrieves a longer description of a node.
- [SPINNAKERC_API spinNodeGetDisplayName](#) (spinNodeHandle hNode, char *pBuf, size_t *pBufLen)
Retrieves the display name of a node (whitespace possible)
- [SPINNAKERC_API spinNodeGetType](#) (spinNodeHandle hNode, spinNodeType *pType)
Retrieves the type of a node (as an enum, spinNodeType)
- [SPINNAKERC_API spinNodeGetPollingTime](#) (spinNodeHandle hNode, int64_t *pPollingTime)
Retrieve the polling time of a node.
- [SPINNAKERC_API spinNodeRegisterCallback](#) (spinNodeHandle hNode, spinNodeCallbackFunction pCb↔
Function, spinNodeCallbackHandle *phCb)
Registers a callback to a node.
- [SPINNAKERC_API spinNodeDeregisterCallback](#) (spinNodeHandle hNode, spinNodeCallbackHandle hCb)
Unregisters a callback from a node.
- [SPINNAKERC_API spinNodeGetImposedAccessMode](#) (spinNodeHandle hNode, spinAccessMode
imposedAccessMode)
Retrieves the imposed access mode of a node.
- [SPINNAKERC_API spinNodeGetImposedVisibility](#) (spinNodeHandle hNode, spinVisibility imposedVisibility)
Retrieves the imposed visibility of a node.
- [SPINNAKERC_API spinNodeToString](#) (spinNodeHandle hNode, char *pBuf, size_t *pBufLen)
Retrieves the value of any node type as a c-string.
- [SPINNAKERC_API spinNodeToStringEx](#) (spinNodeHandle hNode, bool8_t bVerify, char *pBuf, size_t *p↔
BufLen)
Retrieves the value of any node type as a c-string; manually set whether to verify the node.
- [SPINNAKERC_API spinNodeFromString](#) (spinNodeHandle hNode, const char *pBuf)
Sets the value of any node type from a c-string; it is important to ensure that the value of the c-string is appropriate to the node type.
- [SPINNAKERC_API spinNodeFromStringEx](#) (spinNodeHandle hNode, bool8_t bVerify, const char *pBuf)
Sets the value of any node type from a c-string; manually set whether to verify the node; ensure the value of the c-string is appropriate to the node type.
- [SPINNAKERC_API spinStringSetValue](#) (spinNodeHandle hNode, const char *pBuf)
Sets the value of a string node.
- [SPINNAKERC_API spinStringSetValueEx](#) (spinNodeHandle hNode, bool8_t bVerify, const char *pBuf)
Sets the value of a string node; manually set whether to verify the node.
- [SPINNAKERC_API spinStringGetValue](#) (spinNodeHandle hNode, char *pBuf, size_t *pBufLen)
Retrieves the value of a string node as a c-string.
- [SPINNAKERC_API spinStringGetValueEx](#) (spinNodeHandle hNode, bool8_t bVerify, char *pBuf, size_t *p↔
BufLen)
Retrieves the value of a string node as a cstring; manually set whether to verify the node.
- [SPINNAKERC_API spinStringGetMaxLength](#) (spinNodeHandle hNode, int64_t *pValue)
Retrieves the maximum length of the c-string to be returned.
- [SPINNAKERC_API spinIntegerSetValue](#) (spinNodeHandle hNode, int64_t value)
Sets the value of an integer node.
- [SPINNAKERC_API spinIntegerSetValueEx](#) (spinNodeHandle hNode, bool8_t bVerify, int64_t value)
Sets the value of an integer node; manually set whether to verify the node.
- [SPINNAKERC_API spinIntegerGetValue](#) (spinNodeHandle hNode, int64_t *pValue)
Retrieves the value of an integer node.
- [SPINNAKERC_API spinIntegerGetValueEx](#) (spinNodeHandle hNode, bool8_t bVerify, int64_t *pValue)
Retrieves the value of an integer node; manually set whether to verify the node.
- [SPINNAKERC_API spinIntegerGetMin](#) (spinNodeHandle hNode, int64_t *pValue)

- Retrieves the minimum value of an integer node; all potential values must be greater than or equal to the minimum.*

 - [SPINNAKERC_API spinIntegerGetMax](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pValue)

Retrieves the maximum value of an integer node; all potential values must be lesser than or equal to the maximum.

 - [SPINNAKERC_API spinIntegerGetInc](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pValue)

Retrieves the increment of an integer node; all possible values must be divisible by the increment.

 - [SPINNAKERC_API spinIntegerGetRepresentation](#) ([spinNodeHandle](#) hNode, [spinRepresentation](#) *pValue)

Retrieves the numerical representation of the value of a node; i.e.

 - [SPINNAKERC_API spinFloatSetValue](#) ([spinNodeHandle](#) hNode, double value)

Sets the value of a float node.

 - [SPINNAKERC_API spinFloatSetValueEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, double value)

Sets the value of a float node; manually set whether to verify the node.

 - [SPINNAKERC_API spinFloatGetValue](#) ([spinNodeHandle](#) hNode, double *pValue)

Retrieves the value of a float node.

 - [SPINNAKERC_API spinFloatGetValueEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, double *pValue)

Retrieves the value of a float node; manually set whether to verify the node.

 - [SPINNAKERC_API spinFloatGetMin](#) ([spinNodeHandle](#) hNode, double *pValue)

Retrieves the minimum value of a float node; all potential values must be greater than or equal to the minimum.

 - [SPINNAKERC_API spinFloatGetMax](#) ([spinNodeHandle](#) hNode, double *pValue)

Retrieves the maximum value of a float node; all potential values must be lesser than or equal to the maximum.

 - [SPINNAKERC_API spinFloatGetRepresentation](#) ([spinNodeHandle](#) hNode, [spinRepresentation](#) *pValue)

Retrieves the numerical representation of the value of a node; i.e.

 - [SPINNAKERC_API spinFloatGetUnit](#) ([spinNodeHandle](#) hNode, char *pBuf, [size_t](#) *pBufLen)

Retrieves the units of the float node value.

 - [SPINNAKERC_API spinEnumerationGetNumEntries](#) ([spinNodeHandle](#) hNode, [size_t](#) *pValue)

Retrieves the number of entries of an enum node.

 - [SPINNAKERC_API spinEnumerationGetEntryByIndex](#) ([spinNodeHandle](#) hNode, [size_t](#) index, [spinNodeHandle](#) *phEntry)

Retrieves an entry node from an enum node using an index.

 - [SPINNAKERC_API spinEnumerationGetEntryByName](#) ([spinNodeHandle](#) hNode, const char *pName, [spinNodeHandle](#) *phEntry)

Retrieves an entry node from an enum node using the entry's symbolic.

 - [SPINNAKERC_API spinEnumerationGetCurrentEntry](#) ([spinNodeHandle](#) hNode, [spinNodeHandle](#) *phEntry)

Retrieves the currently selected entry node from an enum node.

 - [SPINNAKERC_API spinEnumerationSetIntValue](#) ([spinNodeHandle](#) hNode, [int64_t](#) value)

Sets a new entry using its integer value retrieved from a call to [spinEnumerationEntryGetIntValue\(\)](#); note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).

 - [SPINNAKERC_API spinEnumerationSetEnumValue](#) ([spinNodeHandle](#) hNode, [size_t](#) value)

Sets a new entry using its enum; note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).

 - [SPINNAKERC_API spinEnumerationEntryGetIntValue](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pValue)

Retrieves the integer value of an entry node; note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).

 - [SPINNAKERC_API spinEnumerationEntryGetEnumValue](#) ([spinNodeHandle](#) hNode, [size_t](#) *pValue)

Retrieves the enum value (as an integer) of an entry node; note that enumeration entry int and enum values are different - int values defined on camera, enum values found in [SpinnakerDefsC.h](#).

 - [SPINNAKERC_API spinEnumerationEntryGetSymbolic](#) ([spinNodeHandle](#) hNode, char *pBuf, [size_t](#) *pBufLen)

Retrieves the symbolic of an entry node as a c-string.

 - [SPINNAKERC_API spinBooleanSetValue](#) ([spinNodeHandle](#) hNode, [bool8_t](#) value)

Sets the value of a boolean node; boolean values are represented by 'True' (which equals '0') and 'False' (which equals '1')


 - [SPINNAKERC_API spinBooleanGetValue](#) ([spinNodeHandle](#) hNode, [bool8_t](#) *pValue)

Retrieves the value of a boolean node; boolean values are represented by 'True' (which equals '0') and 'False' (which equals '1')

- [SPINNAKERC_API spinCommandExecute](#) ([spinNodeHandle](#) hNode)
Executes the action associated to a command node.
- [SPINNAKERC_API spinCommandIsDone](#) ([spinNodeHandle](#) hNode, [bool8_t](#) *pbValue)
Retrieves whether or not the action of a command node has completed.
- [SPINNAKERC_API spinCategoryGetNumFeatures](#) ([spinNodeHandle](#) hNode, [size_t](#) *pValue)
Retrieves the number of a features (or child nodes) of a category node.
- [SPINNAKERC_API spinCategoryGetFeatureByIndex](#) ([spinNodeHandle](#) hNode, [size_t](#) index, [spinNodeHandle](#) *phFeature)
Retrieves a node from a category node using an index.
- [SPINNAKERC_API spinRegisterGet](#) ([spinNodeHandle](#) hNode, [uint8_t](#) *pBuf, [int64_t](#) length)
Retrieves the value of a register node.
- [SPINNAKERC_API spinRegisterGetEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, [bool8_t](#) bIgnoreCache, [uint8_t](#) *pBuf, [int64_t](#) length)
Retrieves the value of a register node; manually set whether to verify the node and whether to ignore the cache.
- [SPINNAKERC_API spinRegisterGetAddress](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pAddress)
Retrieves the address of a register node.
- [SPINNAKERC_API spinRegisterGetLength](#) ([spinNodeHandle](#) hNode, [int64_t](#) *pLength)
Retrieves the length (in bytes) of the value of a register node.
- [SPINNAKERC_API spinRegisterSet](#) ([spinNodeHandle](#) hNode, [const uint8_t](#) *pBuf, [int64_t](#) length)
Sets the value of a register node.
- [SPINNAKERC_API spinRegisterSetEx](#) ([spinNodeHandle](#) hNode, [bool8_t](#) bVerify, [const uint8_t](#) *pBuf, [int64_t](#) length)
Sets the value of a register node; manually set whether to verify the node.
- [SPINNAKERC_API spinRegisterSetReference](#) ([spinNodeHandle](#) hNode, [spinNodeHandle](#) hRef)
Uses a second node as a reference for a register node.

6.8 include/spinc/SpinnakerGenApiDefsC.h File Reference

This graph shows which files directly or indirectly include this file:



Typedefs

- typedef void * [spinNodeMapHandle](#)
Handle for nodemap functionality.
- typedef void * [spinNodeHandle](#)
Handle for node functionality.
- typedef void * [spinNodeCallbackHandle](#)
Handle for callback functionality.
- typedef void(* [spinNodeCallbackFunction](#)) ([spinNodeHandle](#) hNode)
Function signatures are used to create and trigger callbacks and events.

Enumerations

- enum `spinNodeType` {
`ValueNode`,
`BaseNode`,
`IntegerNode`,
`BooleanNode`,
`FloatNode`,
`CommandNode`,
`StringNode`,
`RegisterNode`,
`EnumerationNode`,
`EnumEntryNode`,
`CategoryNode`,
`PortNode`,
`UnknownNode` = -1 }
- enum `spinSign` {
`Signed`,
`Unsigned`,
`_UndefinedSign` }
- enum `spinAccessMode` {
`NI`,
`NA`,
`WO`,
`RO`,
`RW`,
`_UndefinedAccesMode`,
`_CycleDetectAccesMode` }
- enum `spinVisibility` {
`Beginner` = 0,
`Expert` = 1,
`Guru` = 2,
`Invisible` = 3,
`_UndefinedVisibility` = 99 }
- enum `spinCachingMode` {
`NoCache`,
`WriteThrough`,
`WriteAround`,
`_UndefinedCachingMode` }
- enum `spinRepresentation` {
`Linear`,
`Logarithmic`,
`Boolean`,
`PureNumber`,
`HexNumber`,
`IPV4Address`,
`MACAddress`,
`_UndefinedRepresentation` }
recommended representation of a node value
- enum `spinEndianness` {
`BigEndian`,
`LittleEndian`,
`_UndefinedEndian` }
Endianness of a value in a register.
- enum `spinNameSpace` {
`Custom`,
`Standard`,
`_UndefinedNameSpace` }

Defines if a node name is standard or custom.

- enum `spinStandardNameSpace` {
`None`,
`GEV`,
`IIDC`,
`CL`,
`USB`,
`_UndefinedStandardNameSpace` }

Defines from which standard namespace a node name comes from.

- enum `spinYesNo` {
`Yes` = 1,
`No` = 0,
`_UndefinedYesNo` = 2 }

Defines the chices of a Yes/No alternative.

- enum `spinSlope` {
`Increasing`,
`Decreasing`,
`Varying`,
`Automatic`,
`_UndefinedESlope` }

typedef for fomula type

- enum `spinXMLValidation` {
`xvLoad` = 0x00000001L,
`xvCycles` = 0x00000002L,
`xvSFNC` = 0x00000004L,
`xvDefault` = 0x00000000L,
`xvAll` = 0xffffffffL,
`_UndefinedEXMLValidation` = 0x80000000L }

typedef describing the different validity checks which can be performed on an XML file

- enum `spinDisplayNotation` {
`fnAutomatic`,
`fnFixed`,
`fnScientific`,
`_UndefinedEDisplayNotation` }

typedef for float notation

- enum `spinInterfaceType` {
`intflValue`,
`intflBase`,
`intflInteger`,
`intflBoolean`,
`intflCommand`,
`intflFloat`,
`intflString`,
`intflRegister`,
`intflCategory`,
`intflEnumeration`,
`intflEnumEntry`,
`intflPort` }


typedef for interface type

- enum `spinLinkType` {
`ctAllDependingNodes`,
`ctAllTerminalNodes`,
`ctInvalidators`,
`ctReadingChildren`,
`ctWritingChildren`,
`ctDependingChildren` }


- typedef for link type*
 - enum `spinIncMode` {
 - `noIncrement`,
 - `fixedIncrement`,
 - `listIncrement` }
 - typedef for increment mode*
 - enum `spinInputDirection` {
 - `idFrom`,
 - `idTo`,
 - `idNone` }
 - typedef for link type*

6.9 include/spinc/SpinnakerPlatformC.h File Reference

Include dependency graph for SpinnakerPlatformC.h:



This graph shows which files directly or indirectly include this file:



Macros

- #define `SPINNAKERC_API` `SPINC_IMPORT_EXPORT` `spinError` `SPINC_CALLTYPE`


6.9.1 Macro Definition Documentation

6.9.1.1 SPINNAKERC_API

```
#define SPINNAKERC_API SPINC_IMPORT_EXPORT spinError SPINC_CALLTYPE
```

6.10 include/spinc/SpinVideoC.h File Reference

Include dependency graph for SpinVideoC.h:




Functions

- [SPINNAKERC_API spinVideoOpenUncompressed](#) ([spinVideo](#) *phSpinVideo, const char *pName, [spinAVIOOption](#) option)
- [SPINNAKERC_API spinVideoOpenMJPEG](#) ([spinVideo](#) *phSpinVideo, const char *pName, [spinMJPGOption](#) option)
- [SPINNAKERC_API spinVideoOpenH264](#) ([spinVideo](#) *phSpinVideo, const char *pName, [spinH264Option](#) option)
- [SPINNAKERC_API spinVideoAppend](#) ([spinVideo](#) hSpinVideo, [spinImage](#) hImage)
- [SPINNAKERC_API spinVideoSetMaximumFileSize](#) ([spinVideo](#) hSpinVideo, unsigned int size)
Set the maximum file size (in megabytes) of a AVI/MP4 file.
- [SPINNAKERC_API spinVideoClose](#) ([spinVideo](#) hSpinVideo)

6.11 include/spinc/TransportLayerDefsC.h File Reference

This graph shows which files directly or indirectly include this file:



Enumerations

- enum `spinTLStreamTypeEnums` {
`StreamType_GigEVision`,
`StreamType_CameraLink`,
`StreamType_CameraLinkHS`,
`StreamType_CoaXPress`,
`StreamType_USB3Vision`,
`StreamType_Custom`,
`NUMSTREAMTYPE` }


The enumeration definitions for transport layer nodes.

- enum `spinTLStreamBufferCountModeEnums` {
`StreamBufferCountMode_Manual`,
`StreamBufferCountMode_Auto`,
`NUMSTREAMBUFFERCOUNTMODE` }
- enum `spinTLStreamBufferHandlingModeEnums` {
`StreamBufferHandlingMode_OldestFirst`,
`StreamBufferHandlingMode_OldestFirstOverwrite`,
`StreamBufferHandlingMode_NewestOnly`,
`StreamBufferHandlingMode_NewestFirst`,
`NUMSTREAMBUFFERHANDLINGMODE` }
- enum `spinTLDeviceTypeEnums` {
`DeviceType_GigEVision`,
`DeviceType_CameraLink`,
`DeviceType_CameraLinkHS`,
`DeviceType_CoaXPress`,
`DeviceType_USB3Vision`,
`DeviceType_Custom`,
`NUMDEVICETYPE` }
- enum `spinTLDeviceAccessStatusEnums` {
`DeviceAccessStatus_Unknown`,
`DeviceAccessStatus_ReadWrite`,
`DeviceAccessStatus_ReadOnly`,
`DeviceAccessStatus_NoAccess`,
`DeviceAccessStatus_Busy`,
`DeviceAccessStatus_OpenReadWrite`,
`DeviceAccessStatus_OpenReadOnly`,
`NUMDEVICEACCESSSTATUS` }
- enum `spinTLGevCCPEnums` {
`GevCCP_EnumEntry_GevCCP_OpenAccess`,
`GevCCP_EnumEntry_GevCCP_ExclusiveAccess`,
`GevCCP_EnumEntry_GevCCP_ControlAccess`,
`NUMGEVCCP` }


- enum [spinTLGUIXMLLocationEnums](#) {
 [GUIXMLLocation_Device](#),
 [GUIXMLLocation_Host](#),
 [NUMGUIXMLLOCATION](#) }
- enum [spinTLGenICamXMLLocationEnums](#) {
 [GenICamXMLLocation_Device](#),
 [GenICamXMLLocation_Host](#),
 [NUMGENICAMXMLLOCATION](#) }
- enum [spinTLDeviceEndiannessMechanismEnums](#) {
 [DeviceEndiannessMechanism_Legacy](#),
 [DeviceEndiannessMechanism_Standard](#),
 [NUMDEVICEENDIANESSMECHANISM](#) }
- enum [spinTLDeviceCurrentSpeedEnums](#) {
 [DeviceCurrentSpeed_UnknownSpeed](#),
 [DeviceCurrentSpeed_LowSpeed](#),
 [DeviceCurrentSpeed_FullSpeed](#),
 [DeviceCurrentSpeed_HighSpeed](#),
 [DeviceCurrentSpeed_SuperSpeed](#),
 [NUMDEVICECURRENTSPEED](#) }
- enum [spinTLInterfaceTypeEnums](#) {
 [InterfaceType_GigEVision](#),
 [InterfaceType_CameraLink](#),
 [InterfaceType_CameraLinkHS](#),
 [InterfaceType_CoaXPress](#),
 [InterfaceType_USB3Vision](#),
 [InterfaceType_Custom](#),
 [NUMINTERFACETYPE](#) }
- enum [spinTLPOEStatusEnums](#) {
 [POEStatus_NotSupported](#),
 [POEStatus_PowerOff](#),
 [POEStatus_PowerOn](#),
 [NUMPOESTATUS](#) }
- enum [spinTLFilterDriverStatusEnums](#) {
 [FilterDriverStatus_NotSupported](#),
 [FilterDriverStatus_Disabled](#),
 [FilterDriverStatus_Enabled](#),
 [NUMFILTERDRIVERSTATUS](#) }
- enum [spinTLTLTypeEnums](#) {
 [TLType_GigEVision](#),
 [TLType_CameraLink](#),
 [TLType_CameraLinkHS](#),
 [TLType_CoaXPress](#),
 [TLType_USB3Vision](#),
 [TLType_Mixed](#),
 [TLType_Custom](#),
 [NUMTLTYPE](#) }

6.12 include/spinc/TransportLayerDeviceC.h File Reference

Include dependency graph for TransportLayerDeviceC.h:



This graph shows which files directly or indirectly include this file:




Data Structures


- struct [quickSpinTLDevice](#)

6.13 include/spinc/TransportLayerInterfaceC.h File Reference

Include dependency graph for TransportLayerInterfaceC.h:



This graph shows which files directly or indirectly include this file:




Data Structures


- struct [quickSpinTLInterface](#)

6.14 include/spinc/TransportLayerStreamC.h File Reference

Include dependency graph for TransportLayerStreamC.h:



This graph shows which files directly or indirectly include this file:




Data Structures


- struct [quickSpinTLStream](#)

6.15 include/spinc/TransportLayerSystemC.h File Reference

Include dependency graph for TransportLayerSystemC.h:



This graph shows which files directly or indirectly include this file:



Data Structures

- struct [quickSpinTLSystem](#)

Index

- aPAUSEMACCtrlFramesReceived
 - quickSpin, [347](#)
- aPAUSEMACCtrlFramesTransmitted
 - quickSpin, [347](#)
- AasRoiEnable
 - quickSpin, [344](#)
- AasRoiHeight
 - quickSpin, [344](#)
- AasRoiOffsetX
 - quickSpin, [344](#)
- AasRoiOffsetY
 - quickSpin, [344](#)
- AasRoiWidth
 - quickSpin, [344](#)
- AcquisitionAbort
 - quickSpin, [345](#)
- AcquisitionArm
 - quickSpin, [345](#)
- AcquisitionBurstFrameCount
 - quickSpin, [345](#)
- AcquisitionFrameCount
 - quickSpin, [345](#)
- AcquisitionFrameRate
 - quickSpin, [345](#)
- AcquisitionFrameRateEnable
 - quickSpin, [345](#)
- AcquisitionLineRate
 - quickSpin, [345](#)
- AcquisitionMode
 - quickSpin, [345](#)
- AcquisitionResultingFrameRate
 - quickSpin, [346](#)
- AcquisitionStart
 - quickSpin, [346](#)
- AcquisitionStatus
 - quickSpin, [346](#)
- AcquisitionStatusSelector
 - quickSpin, [346](#)
- AcquisitionStop
 - quickSpin, [346](#)
- ActionCommand
 - quickSpinTLInterface, [435](#)
- actionCommandResult, [331](#)
 - DeviceAddress, [331](#)
 - Status, [331](#)
- actionCommandStatus
 - Spinnaker C Structures, [248](#)
- ActionDeviceKey
 - quickSpin, [346](#)
- ActionGroupKey
 - quickSpin, [346](#)
- ActionGroupMask
 - quickSpin, [346](#)
- ActionQueueSize
 - quickSpin, [347](#)
- ActionSelector
 - quickSpin, [347](#)
- ActionUnconditionalMode
 - quickSpin, [347](#)
- AdaptiveCompressionEnable
 - quickSpin, [347](#)
- AdcBitDepth
 - quickSpin, [347](#)
- AutoAlgorithmSelector
 - quickSpin, [347](#)
- AutoExposureControlLoopDamping
 - quickSpin, [348](#)
- AutoExposureControlPriority
 - quickSpin, [348](#)
- AutoExposureEVCompensation
 - quickSpin, [348](#)
- AutoExposureExposureTimeLowerLimit
 - quickSpin, [348](#)
- AutoExposureExposureTimeUpperLimit
 - quickSpin, [348](#)
- AutoExposureGainLowerLimit
 - quickSpin, [348](#)
- AutoExposureGainUpperLimit
 - quickSpin, [348](#)
- AutoExposureGreyValueLowerLimit
 - quickSpin, [348](#)
- AutoExposureGreyValueUpperLimit
 - quickSpin, [349](#)
- AutoExposureLightingMode
 - quickSpin, [349](#)
- AutoExposureMeteringMode
 - quickSpin, [349](#)
- AutoExposureTargetGreyValue
 - quickSpin, [349](#)
- AutoExposureTargetGreyValueAuto
 - quickSpin, [349](#)
- BalanceRatio
 - quickSpin, [349](#)
- BalanceRatioSelector
 - quickSpin, [349](#)
- BalanceWhiteAuto
 - quickSpin, [349](#)
- BalanceWhiteAutoDamping

- quickSpin, [350](#)
- BalanceWhiteAutoLowerLimit
 - quickSpin, [350](#)
- BalanceWhiteAutoProfile
 - quickSpin, [350](#)
- BalanceWhiteAutoUpperLimit
 - quickSpin, [350](#)
- binaryFile
 - spinPGMOption, [463](#)
 - spinPPMOption, [465](#)
- BinningHorizontal
 - quickSpin, [350](#)
- BinningHorizontalMode
 - quickSpin, [350](#)
- BinningSelector
 - quickSpin, [350](#)
- BinningVertical
 - quickSpin, [350](#)
- BinningVerticalMode
 - quickSpin, [351](#)
- bitrate
 - spinH264Option, [458](#)
- BlackLevel
 - quickSpin, [351](#)
- BlackLevelAuto
 - quickSpin, [351](#)
- BlackLevelAutoBalance
 - quickSpin, [351](#)
- BlackLevelClampingEnable
 - quickSpin, [351](#)
- BlackLevelRaw
 - quickSpin, [351](#)
- BlackLevelSelector
 - quickSpin, [351](#)
- bool8_t
 - Spinnaker C Definitions, [8](#)
- build
 - spinLibraryVersion, [461](#)
- Camera Access, [167](#)
 - spinCameraBeginAcquisition, [168](#)
 - spinCameraDelInit, [169](#)
 - spinCameraEndAcquisition, [169](#)
 - spinCameraGetAccessMode, [169](#)
 - spinCameraGetGuiXml, [170](#)
 - spinCameraGetNextImage, [170](#)
 - spinCameraGetNextImageEx, [171](#)
 - spinCameraGetNodeMap, [171](#)
 - spinCameraGetTLDeviceNodeMap, [172](#)
 - spinCameraGetTLStreamNodeMap, [172](#)
 - spinCameraGetUniqueID, [173](#)
 - spinCameraInit, [173](#)
 - spinCamerasInitialized, [174](#)
 - spinCamerasStreaming, [174](#)
 - spinCamerasValid, [175](#)
 - spinCameraReadPort, [175](#)
 - spinCameraRegisterDeviceEventHandler, [175](#)
 - spinCameraRegisterDeviceEventHandlerEx, [176](#)
 - spinCameraRegisterImageEventHandler, [176](#)
 - spinCameraRelease, [177](#)
 - spinCameraUnregisterDeviceEventHandler, [177](#)
 - spinCameraUnregisterImageEventHandler, [178](#)
 - spinCameraWritePort, [178](#)
- Camera Enumerations, [9](#)
 - spinAcquisitionModeEnums, [41](#)
 - spinAcquisitionStatusSelectorEnums, [41](#)
 - spinActionUnconditionalModeEnums, [42](#)
 - spinAdcBitDepthEnums, [42](#)
 - spinAutoAlgorithmSelectorEnums, [42](#)
 - spinAutoExposureControlPriorityEnums, [43](#)
 - spinAutoExposureLightingModeEnums, [43](#)
 - spinAutoExposureMeteringModeEnums, [43](#)
 - spinAutoExposureTargetGreyValueAutoEnums, [44](#)
 - spinBalanceRatioSelectorEnums, [44](#)
 - spinBalanceWhiteAutoEnums, [45](#)
 - spinBalanceWhiteAutoProfileEnums, [45](#)
 - spinBinningHorizontalModeEnums, [45](#)
 - spinBinningSelectorEnums, [46](#)
 - spinBinningVerticalModeEnums, [46](#)
 - spinBlackLevelAutoBalanceEnums, [46](#)
 - spinBlackLevelAutoEnums, [47](#)
 - spinBlackLevelSelectorEnums, [47](#)
 - spinChunkBlackLevelSelectorEnums, [47](#)
 - spinChunkCounterSelectorEnums, [47](#)
 - spinChunkEncoderSelectorEnums, [48](#)
 - spinChunkEncoderStatusEnums, [48](#)
 - spinChunkExposureTimeSelectorEnums, [48](#)
 - spinChunkGainSelectorEnums, [49](#)
 - spinChunkImageComponentEnums, [49](#)
 - spinChunkPixelFormatEnums, [50](#)
 - spinChunkRegionIDEnums, [50](#)
 - spinChunkScan3dCoordinateReferenceSelector↔
Enums, [50](#)
 - spinChunkScan3dCoordinateSelectorEnums, [51](#)
 - spinChunkScan3dCoordinateSystemEnums, [51](#)
 - spinChunkScan3dCoordinateSystemReference↔
Enums, [51](#)
 - spinChunkScan3dCoordinateTransformSelector↔
Enums, [52](#)
 - spinChunkScan3dDistanceUnitEnums, [52](#)
 - spinChunkScan3dOutputModeEnums, [53](#)
 - spinChunkSelectorEnums, [53](#)
 - spinChunkSourceIDEnums, [54](#)
 - spinChunkTimerSelectorEnums, [54](#)
 - spinChunkTransferStreamIDEnums, [55](#)
 - spinCIConfigurationEnums, [55](#)
 - spinCITimeSlotsCountEnums, [55](#)
 - spinColorTransformationSelectorEnums, [56](#)
 - spinColorTransformationValueSelectorEnums, [56](#)
 - spinCounterEventActivationEnums, [57](#)
 - spinCounterEventSourceEnums, [57](#)
 - spinCounterResetActivationEnums, [58](#)
 - spinCounterResetSourceEnums, [58](#)
 - spinCounterSelectorEnums, [58](#)
 - spinCounterStatusEnums, [59](#)
 - spinCounterTriggerActivationEnums, [59](#)
 - spinCounterTriggerSourceEnums, [59](#)

- spinCxpConnectionTestModeEnums, 60
- spinCxpLinkConfigurationEnums, 60
- spinCxpLinkConfigurationPreferredEnums, 61
- spinCxpLinkConfigurationStatusEnums, 62
- spinCxpPoCxpStatusEnums, 63
- spinDecimationHorizontalModeEnums, 64
- spinDecimationSelectorEnums, 64
- spinDecimationVerticalModeEnums, 64
- spinDefectCorrectionModeEnums, 64
- spinDeinterlacingEnums, 65
- spinDeviceCharacterSetEnums, 65
- spinDeviceClockSelectorEnums, 65
- spinDeviceConnectionStatusEnums, 66
- spinDeviceIndicatorModeEnums, 66
- spinDeviceLinkHeartbeatModeEnums, 66
- spinDeviceLinkThroughputLimitModeEnums, 68
- spinDevicePowerSupplySelectorEnums, 68
- spinDeviceRegistersEndiannessEnums, 68
- spinDeviceScanTypeEnums, 69
- spinDeviceSerialPortBaudRateEnums, 69
- spinDeviceSerialPortSelectorEnums, 69
- spinDeviceStreamChannelEndiannessEnums, 69
- spinDeviceStreamChannelTypeEnums, 70
- spinDeviceTLTypeEnums, 72
- spinDeviceTapGeometryEnums, 70
- spinDeviceTemperatureSelectorEnums, 71
- spinDeviceTypeEnums, 72
- spinEncoderModeEnums, 72
- spinEncoderOutputModeEnums, 73
- spinEncoderResetActivationEnums, 73
- spinEncoderResetSourceEnums, 74
- spinEncoderSelectorEnums, 75
- spinEncoderSourceAEnums, 75
- spinEncoderSourceBEnums, 75
- spinEncoderStatusEnums, 76
- spinEventNotificationEnums, 76
- spinEventSelectorEnums, 76
- spinExposureActiveModeEnums, 77
- spinExposureAutoEnums, 77
- spinExposureModeEnums, 77
- spinExposureTimeModeEnums, 78
- spinExposureTimeSelectorEnums, 78
- spinFileOpenModeEnums, 79
- spinFileOperationSelectorEnums, 79
- spinFileOperationStatusEnums, 79
- spinFileSelectorEnums, 80
- spinGainAutoBalanceEnums, 80
- spinGainAutoEnums, 80
- spinGainSelectorEnums, 81
- spinGevCCPEnums, 81
- spinGevCurrentPhysicalLinkConfigurationEnums, 81
- spinGevGVCPExtendedStatusCodesSelector↔
Enums, 81
- spinGevGVSPExtentedIDModeEnums, 82
- spinGevIEEE1588ClockAccuracyEnums, 82
- spinGevIEEE1588ModeEnums, 82
- spinGevIEEE1588StatusEnums, 83
- spinGevIPConfigurationStatusEnums, 83
- spinGevPhysicalLinkConfigurationEnums, 83
- spinGevSupportedOptionSelectorEnums, 84
- spinImageComponentSelectorEnums, 85
- spinImageCompressionJPEGFormatOption↔
Enums, 85
- spinImageCompressionModeEnums, 86
- spinImageCompressionRateOptionEnums, 86
- spinLUTSelectorEnums, 90
- spinLineFormatEnums, 86
- spinLineInputFilterSelectorEnums, 87
- spinLineModeEnums, 87
- spinLineSelectorEnums, 87
- spinLineSourceEnums, 88
- spinLogicBlockLUTInputActivationEnums, 88
- spinLogicBlockLUTInputSelectorEnums, 89
- spinLogicBlockLUTInputSourceEnums, 89
- spinLogicBlockLUTSelectorEnums, 90
- spinLogicBlockSelectorEnums, 90
- spinPixelColorFilterEnums, 91
- spinPixelFormatEnums, 91
- spinPixelFormatInfoSelectorEnums, 97
- spinPixelSizeEnums, 102
- spinRegionDestinationEnums, 103
- spinRegionModeEnums, 103
- spinRegionSelectorEnums, 104
- spinRgbTransformLightSourceEnums, 104
- spinScan3dCoordinateReferenceSelectorEnums, 104
- spinScan3dCoordinateSelectorEnums, 105
- spinScan3dCoordinateSystemEnums, 105
- spinScan3dCoordinateSystemReferenceEnums, 105
- spinScan3dCoordinateTransformSelectorEnums, 106
- spinScan3dDistanceUnitEnums, 106
- spinScan3dOutputModeEnums, 107
- spinSensorDigitizationTapsEnums, 107
- spinSensorShutterModeEnums, 108
- spinSensorTapsEnums, 108
- spinSequencerConfigurationModeEnums, 109
- spinSequencerConfigurationValidEnums, 109
- spinSequencerModeEnums, 109
- spinSequencerSetValidEnums, 109
- spinSequencerTriggerActivationEnums, 110
- spinSequencerTriggerSourceEnums, 110
- spinSerialPortBaudRateEnums, 110
- spinSerialPortParityEnums, 111
- spinSerialPortSelectorEnums, 111
- spinSerialPortSourceEnums, 112
- spinSerialPortStopBitsEnums, 112
- spinSoftwareSignalSelectorEnums, 112
- spinSourceSelectorEnums, 113
- spinTestPatternEnums, 113
- spinTestPatternGeneratorSelectorEnums, 113
- spinTimerSelectorEnums, 114
- spinTimerStatusEnums, 114
- spinTimerTriggerActivationEnums, 114

- spinTimerTriggerSourceEnums, [115](#)
- spinTransferComponentSelectorEnums, [116](#)
- spinTransferControlModeEnums, [116](#)
- spinTransferOperationModeEnums, [117](#)
- spinTransferQueueModeEnums, [117](#)
- spinTransferSelectorEnums, [117](#)
- spinTransferStatusSelectorEnums, [118](#)
- spinTransferTriggerActivationEnums, [118](#)
- spinTransferTriggerModeEnums, [118](#)
- spinTransferTriggerSelectorEnums, [119](#)
- spinTransferTriggerSourceEnums, [119](#)
- spinTriggerActivationEnums, [120](#)
- spinTriggerModeEnums, [121](#)
- spinTriggerOverlapEnums, [121](#)
- spinTriggerSelectorEnums, [121](#)
- spinTriggerSourceEnums, [121](#)
- spinUserOutputSelectorEnums, [122](#)
- spinUserSetDefaultEnums, [122](#)
- spinUserSetSelectorEnums, [123](#)
- spinWhiteClipSelectorEnums, [123](#)
- CameraList Access, [153](#)
 - spinCameraListAppend, [153](#)
 - spinCameraListClear, [154](#)
 - spinCameraListCreateEmpty, [154](#)
 - spinCameraListDestroy, [155](#)
 - spinCameraListGet, [155](#)
 - spinCameraListGetBySerial, [156](#)
 - spinCameraListGetSize, [156](#)
 - spinCameraListRemove, [157](#)
 - spinCameraListRemoveBySerial, [157](#)
- Chunk data access, [232](#)
 - spinImageChunkDataGetFloatValue, [232](#)
 - spinImageChunkDataGetIntValue, [232](#)
- Chunk Data Structures, [124](#)
- ChunkBlackLevel
 - quickSpin, [351](#)
- ChunkBlackLevelSelector
 - quickSpin, [352](#)
- ChunkCRC
 - quickSpin, [352](#)
- ChunkCounterSelector
 - quickSpin, [352](#)
- ChunkCounterValue
 - quickSpin, [352](#)
- ChunkEnable
 - quickSpin, [352](#)
- ChunkEncoderSelector
 - quickSpin, [352](#)
- ChunkEncoderStatus
 - quickSpin, [352](#)
- ChunkEncoderValue
 - quickSpin, [352](#)
- ChunkExposureEndLineStatusAll
 - quickSpin, [353](#)
- ChunkExposureTime
 - quickSpin, [353](#)
- ChunkExposureTimeSelector
 - quickSpin, [353](#)
- ChunkFrameID
 - quickSpin, [353](#)
- ChunkGain
 - quickSpin, [353](#)
- ChunkGainSelector
 - quickSpin, [353](#)
- ChunkHeight
 - quickSpin, [353](#)
- ChunkImage
 - quickSpin, [353](#)
- ChunkImageComponent
 - quickSpin, [354](#)
- ChunkInferenceBoundingBoxResult
 - quickSpin, [354](#)
- ChunkInferenceConfidence
 - quickSpin, [354](#)
- ChunkInferenceFrameId
 - quickSpin, [354](#)
- ChunkInferenceResult
 - quickSpin, [354](#)
- ChunkLinePitch
 - quickSpin, [354](#)
- ChunkLineStatusAll
 - quickSpin, [354](#)
- ChunkModeActive
 - quickSpin, [354](#)
- ChunkOffsetX
 - quickSpin, [355](#)
- ChunkOffsetY
 - quickSpin, [355](#)
- ChunkPartSelector
 - quickSpin, [355](#)
- ChunkPixelDynamicRangeMax
 - quickSpin, [355](#)
- ChunkPixelDynamicRangeMin
 - quickSpin, [355](#)
- ChunkPixelFormat
 - quickSpin, [355](#)
- ChunkRegionID
 - quickSpin, [355](#)
- ChunkScan3dAxisMax
 - quickSpin, [355](#)
- ChunkScan3dAxisMin
 - quickSpin, [356](#)
- ChunkScan3dCoordinateOffset
 - quickSpin, [356](#)
- ChunkScan3dCoordinateReferenceSelector
 - quickSpin, [356](#)
- ChunkScan3dCoordinateReferenceValue
 - quickSpin, [356](#)
- ChunkScan3dCoordinateScale
 - quickSpin, [356](#)
- ChunkScan3dCoordinateSelector
 - quickSpin, [356](#)
- ChunkScan3dCoordinateSystem
 - quickSpin, [356](#)
- ChunkScan3dCoordinateSystemReference
 - quickSpin, [356](#)

- ChunkScan3dCoordinateTransformSelector
 - quickSpin, [357](#)
- ChunkScan3dDistanceUnit
 - quickSpin, [357](#)
- ChunkScan3dInvalidDataFlag
 - quickSpin, [357](#)
- ChunkScan3dInvalidDataValue
 - quickSpin, [357](#)
- ChunkScan3dOutputMode
 - quickSpin, [357](#)
- ChunkScan3dTransformValue
 - quickSpin, [357](#)
- ChunkScanLineSelector
 - quickSpin, [357](#)
- ChunkSelector
 - quickSpin, [357](#)
- ChunkSequencerSetActive
 - quickSpin, [358](#)
- ChunkSerialData
 - quickSpin, [358](#)
- ChunkSerialDataLength
 - quickSpin, [358](#)
- ChunkSerialReceiveOverflow
 - quickSpin, [358](#)
- ChunkSourceID
 - quickSpin, [358](#)
- ChunkStreamChannelID
 - quickSpin, [358](#)
- ChunkTimerSelector
 - quickSpin, [358](#)
- ChunkTimerValue
 - quickSpin, [358](#)
- ChunkTimestamp
 - quickSpin, [359](#)
- ChunkTimestampLatchValue
 - quickSpin, [359](#)
- ChunkTransferBlockID
 - quickSpin, [359](#)
- ChunkTransferQueueCurrentBlockCount
 - quickSpin, [359](#)
- ChunkTransferStreamID
 - quickSpin, [359](#)
- ChunkWidth
 - quickSpin, [359](#)
- CIConfiguration
 - quickSpin, [359](#)
- CITimeSlotsCount
 - quickSpin, [359](#)
- ColorTransformationEnable
 - quickSpin, [360](#)
- ColorTransformationSelector
 - quickSpin, [360](#)
- ColorTransformationValue
 - quickSpin, [360](#)
- ColorTransformationValueSelector
 - quickSpin, [360](#)
- compression
 - spinTIFFOption, [466](#)
- compressionLevel
 - spinPNGOption, [464](#)
- CompressionRatio
 - quickSpin, [360](#)
- CounterDelay
 - quickSpin, [360](#)
- CounterDuration
 - quickSpin, [360](#)
- CounterEventActivation
 - quickSpin, [360](#)
- CounterEventSource
 - quickSpin, [361](#)
- CounterReset
 - quickSpin, [361](#)
- CounterResetActivation
 - quickSpin, [361](#)
- CounterResetSource
 - quickSpin, [361](#)
- CounterSelector
 - quickSpin, [361](#)
- CounterStatus
 - quickSpin, [361](#)
- CounterTriggerActivation
 - quickSpin, [361](#)
- CounterTriggerSource
 - quickSpin, [361](#)
- CounterValue
 - quickSpin, [362](#)
- CounterValueAtReset
 - quickSpin, [362](#)
- CxpConnectionSelector
 - quickSpin, [362](#)
- CxpConnectionTestErrorCount
 - quickSpin, [362](#)
- CxpConnectionTestMode
 - quickSpin, [362](#)
- CxpConnectionTestPacketCount
 - quickSpin, [362](#)
- CxpLinkConfiguration
 - quickSpin, [362](#)
- CxpLinkConfigurationPreferred
 - quickSpin, [362](#)
- CxpLinkConfigurationStatus
 - quickSpin, [363](#)
- CxpPoCxpAuto
 - quickSpin, [363](#)
- CxpPoCxpStatus
 - quickSpin, [363](#)
- CxpPoCxpTripReset
 - quickSpin, [363](#)
- CxpPoCxpTurnOff
 - quickSpin, [363](#)
- DecimationHorizontal
 - quickSpin, [363](#)
- DecimationHorizontalMode
 - quickSpin, [363](#)
- DecimationSelector
 - quickSpin, [363](#)

- DecimationVertical
 - [quickSpin, 364](#)
- DecimationVerticalMode
 - [quickSpin, 364](#)
- DefectCorrectStaticEnable
 - [quickSpin, 364](#)
- DefectCorrectionMode
 - [quickSpin, 364](#)
- DefectTableApply
 - [quickSpin, 364](#)
- DefectTableCoordinateX
 - [quickSpin, 364](#)
- DefectTableCoordinateY
 - [quickSpin, 364](#)
- DefectTableFactoryRestore
 - [quickSpin, 364](#)
- DefectTableIndex
 - [quickSpin, 365](#)
- DefectTablePixelCount
 - [quickSpin, 365](#)
- DefectTableSave
 - [quickSpin, 365](#)
- Deinterlacing
 - [quickSpin, 365](#)
- Device Event Data Access, [229](#)
 - [spinDeviceEventGetId, 229](#)
 - [spinDeviceEventGetName, 230](#)
 - [spinDeviceEventGetPayloadData, 230](#)
 - [spinDeviceEventGetPayloadDataSize, 231](#)
- DeviceAccessStatus
 - [quickSpinTLDevice, 429](#)
 - [quickSpinTLInterface, 435](#)
- DeviceAddress
 - [actionCommandResult, 331](#)
- DeviceCharacterSet
 - [quickSpin, 365](#)
- DeviceClockFrequency
 - [quickSpin, 365](#)
- DeviceClockSelector
 - [quickSpin, 365](#)
- DeviceConnectionSelector
 - [quickSpin, 365](#)
- DeviceConnectionSpeed
 - [quickSpin, 366](#)
- DeviceConnectionStatus
 - [quickSpin, 366](#)
- DeviceCount
 - [quickSpinTLInterface, 435](#)
- DeviceCurrentSpeed
 - [quickSpinTLDevice, 429](#)
- DeviceDisplayName
 - [quickSpinTLDevice, 429](#)
- DeviceDriverVersion
 - [quickSpinTLDevice, 429](#)
- DeviceEndiannessMechanism
 - [quickSpinTLDevice, 429](#)
- DeviceEventChannelCount
 - [quickSpin, 366](#)
- DeviceFamilyName
 - [quickSpin, 366](#)
- DeviceFeaturePersistenceEnd
 - [quickSpin, 366](#)
- DeviceFeaturePersistenceStart
 - [quickSpin, 366](#)
- DeviceFirmwareVersion
 - [quickSpin, 366](#)
- DeviceGenCPVersionMajor
 - [quickSpin, 366](#)
- DeviceGenCPVersionMinor
 - [quickSpin, 367](#)
- DeviceID
 - [quickSpin, 367](#)
 - [quickSpinTLDevice, 430](#)
 - [quickSpinTLInterface, 436](#)
- DeviceIndicatorMode
 - [quickSpin, 367](#)
- DeviceInstanceId
 - [quickSpinTLDevice, 430](#)
- DevicesUpdater
 - [quickSpinTLDevice, 430](#)
- DeviceLinkBandwidthReserve
 - [quickSpin, 367](#)
- DeviceLinkCommandTimeout
 - [quickSpin, 367](#)
- DeviceLinkConnectionCount
 - [quickSpin, 367](#)
- DeviceLinkCurrentThroughput
 - [quickSpin, 367](#)
- DeviceLinkHeartbeatMode
 - [quickSpin, 367](#)
- DeviceLinkHeartbeatTimeout
 - [quickSpin, 368](#)
- DeviceLinkSelector
 - [quickSpin, 368](#)
- DeviceLinkSpeed
 - [quickSpin, 368](#)
 - [quickSpinTLDevice, 430](#)
- DeviceLinkThroughputLimit
 - [quickSpin, 368](#)
- DeviceLinkThroughputLimitMode
 - [quickSpin, 368](#)
- DeviceLocation
 - [quickSpinTLDevice, 430](#)
- DeviceManifestEntrySelector
 - [quickSpin, 368](#)
- DeviceManifestPrimaryURL
 - [quickSpin, 368](#)
- DeviceManifestSchemaMajorVersion
 - [quickSpin, 368](#)
- DeviceManifestSchemaMinorVersion
 - [quickSpin, 369](#)
- DeviceManifestSecondaryURL
 - [quickSpin, 369](#)
- DeviceManifestXMLMajorVersion
 - [quickSpin, 369](#)
- DeviceManifestXMLMinorVersion

- quickSpin, [369](#)
- DeviceManifestXMLSubMinorVersion
 - quickSpin, [369](#)
- DeviceManufacturerInfo
 - quickSpin, [369](#)
- DeviceMaxThroughput
 - quickSpin, [369](#)
- DeviceModelName
 - quickSpin, [369](#)
 - quickSpinTLDevice, [430](#)
 - quickSpinTLInterface, [436](#)
- DeviceMulticastMonitorMode
 - quickSpinTLDevice, [430](#)
- DevicePowerSupplySelector
 - quickSpin, [370](#)
- DeviceRegistersCheck
 - quickSpin, [370](#)
- DeviceRegistersEndianness
 - quickSpin, [370](#)
- DeviceRegistersStreamingEnd
 - quickSpin, [370](#)
- DeviceRegistersStreamingStart
 - quickSpin, [370](#)
- DeviceRegistersValid
 - quickSpin, [370](#)
- DeviceReset
 - quickSpin, [370](#)
- DeviceSFNCVersionMajor
 - quickSpin, [371](#)
- DeviceSFNCVersionMinor
 - quickSpin, [371](#)
- DeviceSFNCVersionSubMinor
 - quickSpin, [371](#)
- DeviceScanType
 - quickSpin, [370](#)
- DeviceSelector
 - quickSpinTLInterface, [436](#)
- DeviceSerialNumber
 - quickSpin, [371](#)
 - quickSpinTLDevice, [430](#)
 - quickSpinTLInterface, [436](#)
- DeviceSerialPortBaudRate
 - quickSpin, [371](#)
- DeviceSerialPortSelector
 - quickSpin, [371](#)
- DeviceStreamChannelCount
 - quickSpin, [371](#)
- DeviceStreamChannelEndianness
 - quickSpin, [371](#)
- DeviceStreamChannelLink
 - quickSpin, [372](#)
- DeviceStreamChannelPacketSize
 - quickSpin, [372](#)
- DeviceStreamChannelSelector
 - quickSpin, [372](#)
- DeviceStreamChannelType
 - quickSpin, [372](#)
- DeviceTLType
 - quickSpin, [372](#)
- DeviceTLVersionMajor
 - quickSpin, [373](#)
- DeviceTLVersionMinor
 - quickSpin, [373](#)
- DeviceTLVersionSubMinor
 - quickSpin, [373](#)
- DeviceTapGeometry
 - quickSpin, [372](#)
- DeviceTemperature
 - quickSpin, [372](#)
- DeviceTemperatureSelector
 - quickSpin, [372](#)
- DeviceType
 - quickSpin, [373](#)
 - quickSpinTLDevice, [431](#)
- DeviceU3VProtocol
 - quickSpinTLDevice, [431](#)
- DeviceUnlock
 - quickSpinTLInterface, [436](#)
- DeviceUpdateList
 - quickSpinTLInterface, [436](#)
- DeviceUptime
 - quickSpin, [373](#)
- DeviceUserID
 - quickSpin, [373](#)
 - quickSpinTLDevice, [431](#)
- DeviceVendorName
 - quickSpin, [373](#)
 - quickSpinTLDevice, [431](#)
 - quickSpinTLInterface, [436](#)
- DeviceVersion
 - quickSpin, [373](#)
 - quickSpinTLDevice, [431](#)
- EncoderDivider
 - quickSpin, [374](#)
- EncoderMode
 - quickSpin, [374](#)
- EncoderOutputMode
 - quickSpin, [374](#)
- EncoderReset
 - quickSpin, [374](#)
- EncoderResetActivation
 - quickSpin, [374](#)
- EncoderResetSource
 - quickSpin, [374](#)
- EncoderSelector
 - quickSpin, [374](#)
- EncoderSourceA
 - quickSpin, [374](#)
- EncoderSourceB
 - quickSpin, [375](#)
- EncoderStatus
 - quickSpin, [375](#)
- EncoderTimeout
 - quickSpin, [375](#)
- EncoderValue
 - quickSpin, [375](#)

- EncoderValueAtReset
 - quickSpin, [375](#)
- EnumerateGEVInterfaces
 - quickSpinTLSystem, [446](#)
- EnumerationCount
 - quickSpin, [375](#)
- Error Handling, [130](#)
 - spinErrorGetLast, [130](#)
 - spinErrorGetLastBuildDate, [131](#)
 - spinErrorGetLastBuildTime, [131](#)
 - spinErrorGetLastFileName, [132](#)
 - spinErrorGetLastFullMessage, [132](#)
 - spinErrorGetLastFunctionName, [133](#)
 - spinErrorGetLastLineNumber, [133](#)
 - spinErrorGetLastMessage, [134](#)
- Event Access, [208](#)
 - spinDeviceArrivalEventHandlerCreate, [208](#)
 - spinDeviceArrivalEventHandlerDestroy, [209](#)
 - spinDeviceEventHandlerCreate, [209](#)
 - spinDeviceEventHandlerDestroy, [210](#)
 - spinDeviceRemovalEventHandlerCreate, [210](#)
 - spinDeviceRemovalEventHandlerDestroy, [211](#)
 - spinImageEventHandlerCreate, [211](#)
 - spinImageEventHandlerDestroy, [212](#)
 - spinInterfaceEventHandlerCreate, [212](#)
 - spinInterfaceEventHandlerDestroy, [213](#)
 - spinLogEventHandlerCreate, [213](#)
 - spinLogEventHandlerDestroy, [214](#)
- EventAcquisitionEnd
 - quickSpin, [375](#)
- EventAcquisitionEndFrameID
 - quickSpin, [375](#)
- EventAcquisitionEndTimestamp
 - quickSpin, [376](#)
- EventAcquisitionError
 - quickSpin, [376](#)
- EventAcquisitionErrorFrameID
 - quickSpin, [376](#)
- EventAcquisitionErrorTimestamp
 - quickSpin, [376](#)
- EventAcquisitionStart
 - quickSpin, [376](#)
- EventAcquisitionStartFrameID
 - quickSpin, [376](#)
- EventAcquisitionStartTimestamp
 - quickSpin, [376](#)
- EventAcquisitionTransferEnd
 - quickSpin, [376](#)
- EventAcquisitionTransferEndFrameID
 - quickSpin, [377](#)
- EventAcquisitionTransferEndTimestamp
 - quickSpin, [377](#)
- EventAcquisitionTransferStart
 - quickSpin, [377](#)
- EventAcquisitionTransferStartFrameID
 - quickSpin, [377](#)
- EventAcquisitionTransferStartTimestamp
 - quickSpin, [377](#)
- EventAcquisitionTrigger
 - quickSpin, [377](#)
- EventAcquisitionTriggerFrameID
 - quickSpin, [377](#)
- EventAcquisitionTriggerTimestamp
 - quickSpin, [377](#)
- EventActionLate
 - quickSpin, [378](#)
- EventActionLateFrameID
 - quickSpin, [378](#)
- EventActionLateTimestamp
 - quickSpin, [378](#)
- EventCounter0End
 - quickSpin, [378](#)
- EventCounter0EndFrameID
 - quickSpin, [378](#)
- EventCounter0EndTimestamp
 - quickSpin, [378](#)
- EventCounter0Start
 - quickSpin, [378](#)
- EventCounter0StartFrameID
 - quickSpin, [378](#)
- EventCounter0StartTimestamp
 - quickSpin, [379](#)
- EventCounter1End
 - quickSpin, [379](#)
- EventCounter1EndFrameID
 - quickSpin, [379](#)
- EventCounter1EndTimestamp
 - quickSpin, [379](#)
- EventCounter1Start
 - quickSpin, [379](#)
- EventCounter1StartFrameID
 - quickSpin, [379](#)
- EventCounter1StartTimestamp
 - quickSpin, [379](#)
- EventEncoder0Restarted
 - quickSpin, [379](#)
- EventEncoder0RestartedFrameID
 - quickSpin, [380](#)
- EventEncoder0RestartedTimestamp
 - quickSpin, [380](#)
- EventEncoder0Stopped
 - quickSpin, [380](#)
- EventEncoder0StoppedFrameID
 - quickSpin, [380](#)
- EventEncoder0StoppedTimestamp
 - quickSpin, [380](#)
- EventEncoder1Restarted
 - quickSpin, [380](#)
- EventEncoder1RestartedFrameID
 - quickSpin, [380](#)
- EventEncoder1RestartedTimestamp
 - quickSpin, [380](#)
- EventEncoder1Stopped
 - quickSpin, [381](#)
- EventEncoder1StoppedFrameID
 - quickSpin, [381](#)

- EventEncoder1StoppedTimestamp
 - [quickSpin, 381](#)
- EventError
 - [quickSpin, 381](#)
- EventErrorCode
 - [quickSpin, 381](#)
- EventErrorFrameID
 - [quickSpin, 381](#)
- EventErrorTimestamp
 - [quickSpin, 381](#)
- EventExposureEnd
 - [quickSpin, 381](#)
- EventExposureEndFrameID
 - [quickSpin, 382](#)
- EventExposureEndTimestamp
 - [quickSpin, 382](#)
- EventExposureStart
 - [quickSpin, 382](#)
- EventExposureStartFrameID
 - [quickSpin, 382](#)
- EventExposureStartTimestamp
 - [quickSpin, 382](#)
- EventFrameBurstEnd
 - [quickSpin, 382](#)
- EventFrameBurstEndFrameID
 - [quickSpin, 382](#)
- EventFrameBurstEndTimestamp
 - [quickSpin, 382](#)
- EventFrameBurstStart
 - [quickSpin, 383](#)
- EventFrameBurstStartFrameID
 - [quickSpin, 383](#)
- EventFrameBurstStartTimestamp
 - [quickSpin, 383](#)
- EventFrameEnd
 - [quickSpin, 383](#)
- EventFrameEndFrameID
 - [quickSpin, 383](#)
- EventFrameEndTimestamp
 - [quickSpin, 383](#)
- EventFrameStart
 - [quickSpin, 383](#)
- EventFrameStartFrameID
 - [quickSpin, 383](#)
- EventFrameStartTimestamp
 - [quickSpin, 384](#)
- EventFrameTransferEnd
 - [quickSpin, 384](#)
- EventFrameTransferEndFrameID
 - [quickSpin, 384](#)
- EventFrameTransferEndTimestamp
 - [quickSpin, 384](#)
- EventFrameTransferStart
 - [quickSpin, 384](#)
- EventFrameTransferStartFrameID
 - [quickSpin, 384](#)
- EventFrameTransferStartTimestamp
 - [quickSpin, 384](#)
- EventFrameTrigger
 - [quickSpin, 384](#)
- EventFrameTriggerFrameID
 - [quickSpin, 385](#)
- EventFrameTriggerTimestamp
 - [quickSpin, 385](#)
- EventLine0AnyEdge
 - [quickSpin, 385](#)
- EventLine0AnyEdgeFrameID
 - [quickSpin, 385](#)
- EventLine0AnyEdgeTimestamp
 - [quickSpin, 385](#)
- EventLine0FallingEdge
 - [quickSpin, 385](#)
- EventLine0FallingEdgeFrameID
 - [quickSpin, 385](#)
- EventLine0FallingEdgeTimestamp
 - [quickSpin, 385](#)
- EventLine0RisingEdge
 - [quickSpin, 386](#)
- EventLine0RisingEdgeFrameID
 - [quickSpin, 386](#)
- EventLine0RisingEdgeTimestamp
 - [quickSpin, 386](#)
- EventLine1AnyEdge
 - [quickSpin, 386](#)
- EventLine1AnyEdgeFrameID
 - [quickSpin, 386](#)
- EventLine1AnyEdgeTimestamp
 - [quickSpin, 386](#)
- EventLine1FallingEdge
 - [quickSpin, 386](#)
- EventLine1FallingEdgeFrameID
 - [quickSpin, 386](#)
- EventLine1FallingEdgeTimestamp
 - [quickSpin, 387](#)
- EventLine1RisingEdge
 - [quickSpin, 387](#)
- EventLine1RisingEdgeFrameID
 - [quickSpin, 387](#)
- EventLine1RisingEdgeTimestamp
 - [quickSpin, 387](#)
- EventLinkSpeedChange
 - [quickSpin, 387](#)
- EventLinkSpeedChangeFrameID
 - [quickSpin, 387](#)
- EventLinkSpeedChangeTimestamp
 - [quickSpin, 387](#)
- EventLinkTrigger0
 - [quickSpin, 387](#)
- EventLinkTrigger0FrameID
 - [quickSpin, 388](#)
- EventLinkTrigger0Timestamp
 - [quickSpin, 388](#)
- EventLinkTrigger1
 - [quickSpin, 388](#)
- EventLinkTrigger1FrameID
 - [quickSpin, 388](#)

- EventLinkTrigger1Timestamp
 - quickSpin, [388](#)
- EventNotification
 - quickSpin, [388](#)
- EventSelector
 - quickSpin, [388](#)
- EventSequencerSetChange
 - quickSpin, [388](#)
- EventSequencerSetChangeFrameID
 - quickSpin, [389](#)
- EventSequencerSetChangeTimestamp
 - quickSpin, [389](#)
- EventSerialData
 - quickSpin, [389](#)
- EventSerialDataLength
 - quickSpin, [389](#)
- EventSerialPortReceive
 - quickSpin, [389](#)
- EventSerialPortReceiveTimestamp
 - quickSpin, [389](#)
- EventSerialReceiveOverflow
 - quickSpin, [389](#)
- EventStream0TransferBlockEnd
 - quickSpin, [389](#)
- EventStream0TransferBlockEndFrameID
 - quickSpin, [390](#)
- EventStream0TransferBlockEndTimestamp
 - quickSpin, [390](#)
- EventStream0TransferBlockStart
 - quickSpin, [390](#)
- EventStream0TransferBlockStartFrameID
 - quickSpin, [390](#)
- EventStream0TransferBlockStartTimestamp
 - quickSpin, [390](#)
- EventStream0TransferBlockTrigger
 - quickSpin, [390](#)
- EventStream0TransferBlockTriggerFrameID
 - quickSpin, [390](#)
- EventStream0TransferBlockTriggerTimestamp
 - quickSpin, [390](#)
- EventStream0TransferBurstEnd
 - quickSpin, [391](#)
- EventStream0TransferBurstEndFrameID
 - quickSpin, [391](#)
- EventStream0TransferBurstEndTimestamp
 - quickSpin, [391](#)
- EventStream0TransferBurstStart
 - quickSpin, [391](#)
- EventStream0TransferBurstStartFrameID
 - quickSpin, [391](#)
- EventStream0TransferBurstStartTimestamp
 - quickSpin, [391](#)
- EventStream0TransferEnd
 - quickSpin, [391](#)
- EventStream0TransferEndFrameID
 - quickSpin, [391](#)
- EventStream0TransferEndTimestamp
 - quickSpin, [392](#)
- EventStream0TransferOverflow
 - quickSpin, [392](#)
- EventStream0TransferOverflowFrameID
 - quickSpin, [392](#)
- EventStream0TransferOverflowTimestamp
 - quickSpin, [392](#)
- EventStream0TransferPause
 - quickSpin, [392](#)
- EventStream0TransferPauseFrameID
 - quickSpin, [392](#)
- EventStream0TransferPauseTimestamp
 - quickSpin, [392](#)
- EventStream0TransferResume
 - quickSpin, [392](#)
- EventStream0TransferResumeFrameID
 - quickSpin, [393](#)
- EventStream0TransferResumeTimestamp
 - quickSpin, [393](#)
- EventStream0TransferStart
 - quickSpin, [393](#)
- EventStream0TransferStartFrameID
 - quickSpin, [393](#)
- EventStream0TransferStartTimestamp
 - quickSpin, [393](#)
- EventTest
 - quickSpin, [393](#)
- EventTestTimestamp
 - quickSpin, [393](#)
- EventTimer0End
 - quickSpin, [393](#)
- EventTimer0EndFrameID
 - quickSpin, [394](#)
- EventTimer0EndTimestamp
 - quickSpin, [394](#)
- EventTimer0Start
 - quickSpin, [394](#)
- EventTimer0StartFrameID
 - quickSpin, [394](#)
- EventTimer0StartTimestamp
 - quickSpin, [394](#)
- EventTimer1End
 - quickSpin, [394](#)
- EventTimer1EndFrameID
 - quickSpin, [394](#)
- EventTimer1EndTimestamp
 - quickSpin, [394](#)
- EventTimer1Start
 - quickSpin, [395](#)
- EventTimer1StartFrameID
 - quickSpin, [395](#)
- EventTimer1StartTimestamp
 - quickSpin, [395](#)
- ExposureActiveMode
 - quickSpin, [395](#)
- ExposureAuto
 - quickSpin, [395](#)
- ExposureMode
 - quickSpin, [395](#)

- ExposureTime
 - quickSpin, [395](#)
- ExposureTimeMode
 - quickSpin, [395](#)
- ExposureTimeSelector
 - quickSpin, [396](#)
- FactoryReset
 - quickSpin, [396](#)
- False
 - Spinnaker C Definitions, [8](#)
- FileAccessBuffer
 - quickSpin, [396](#)
- FileAccessLength
 - quickSpin, [396](#)
- FileAccessOffset
 - quickSpin, [396](#)
- FileOpenMode
 - quickSpin, [396](#)
- FileOperationExecute
 - quickSpin, [396](#)
- FileOperationResult
 - quickSpin, [396](#)
- FileOperationSelector
 - quickSpin, [397](#)
- FileOperationStatus
 - quickSpin, [397](#)
- FileSelector
 - quickSpin, [397](#)
- FileSize
 - quickSpin, [397](#)
- FilterDriverStatus
 - quickSpinTLInterface, [436](#)
- frameRate
 - spinAVIOption, [450](#)
 - spinH264Option, [458](#)
 - spinMJPEGOption, [462](#)
- GUIXMLLocation
 - quickSpinTLDevice, [434](#)
- GUIXMLPath
 - quickSpinTLDevice, [434](#)
- Gain
 - quickSpin, [397](#)
- GainAuto
 - quickSpin, [397](#)
- GainAutoBalance
 - quickSpin, [397](#)
- GainSelector
 - quickSpin, [397](#)
- Gamma
 - quickSpin, [398](#)
- GammaEnable
 - quickSpin, [398](#)
- GenICamXMLLocation
 - quickSpinTLDevice, [431](#)
- GenICamXMLPath
 - quickSpinTLDevice, [431](#)
- GenTLFNCVersionMajor
 - quickSpinTLSystem, [446](#)
- GenTLFNCVersionMinor
 - quickSpinTLSystem, [447](#)
- GenTLFNCVersionSubMinor
 - quickSpinTLSystem, [447](#)
- GenTLVersionMajor
 - quickSpinTLSystem, [447](#)
- GenTLVersionMinor
 - quickSpinTLSystem, [447](#)
- GevActionDeviceKey
 - quickSpinTLInterface, [437](#)
- GevActionGroupKey
 - quickSpinTLInterface, [437](#)
- GevActionGroupMask
 - quickSpinTLInterface, [437](#)
- GevActionTime
 - quickSpinTLInterface, [437](#)
- GevActiveLinkCount
 - quickSpin, [398](#)
- GevCCP
 - quickSpin, [398](#)
 - quickSpinTLDevice, [431](#)
- GevCurrentDefaultGateway
 - quickSpin, [398](#)
- GevCurrentIPAddress
 - quickSpin, [398](#)
- GevCurrentIPConfigurationDHCP
 - quickSpin, [398](#)
- GevCurrentIPConfigurationLLA
 - quickSpin, [398](#)
- GevCurrentIPConfigurationPersistentIP
 - quickSpin, [399](#)
- GevCurrentPhysicalLinkConfiguration
 - quickSpin, [399](#)
- GevCurrentSubnetMask
 - quickSpin, [399](#)
- GevDeviceAutoForceIP
 - quickSpinTLDevice, [432](#)
 - quickSpinTLInterface, [437](#)
- GevDeviceDiscoverMaximumPacketSize
 - quickSpinTLDevice, [432](#)
- GevDeviceForceGateway
 - quickSpinTLDevice, [432](#)
 - quickSpinTLInterface, [437](#)
- GevDeviceForceIPAddress
 - quickSpinTLDevice, [432](#)
 - quickSpinTLInterface, [437](#)
- GevDeviceForceIP
 - quickSpinTLDevice, [432](#)
 - quickSpinTLInterface, [437](#)
- GevDeviceForceSubnetMask
 - quickSpinTLDevice, [432](#)
 - quickSpinTLInterface, [438](#)
- GevDeviceGateway
 - quickSpinTLDevice, [432](#)
 - quickSpinTLInterface, [438](#)
- GevDeviceIPAddress
 - quickSpinTLDevice, [432](#)

- quickSpinTLInterface, [438](#)
- GevDeviceIsWrongSubnet
 - quickSpinTLDevice, [433](#)
- GevDeviceMACAddress
 - quickSpinTLDevice, [433](#)
 - quickSpinTLInterface, [438](#)
- GevDeviceMaximumPacketSize
 - quickSpinTLDevice, [433](#)
- GevDeviceMaximumRetryCount
 - quickSpinTLDevice, [433](#)
- GevDeviceModelsBigEndian
 - quickSpinTLDevice, [433](#)
- GevDevicePort
 - quickSpinTLDevice, [433](#)
- GevDeviceReadAndWriteTimeout
 - quickSpinTLDevice, [433](#)
- GevDeviceSubnetMask
 - quickSpinTLDevice, [433](#)
 - quickSpinTLInterface, [438](#)
- GevDiscoveryAckDelay
 - quickSpin, [399](#)
- GevFailedPacketCount
 - quickSpinTLStream, [442](#)
- GevFirstURL
 - quickSpin, [399](#)
- GevGVCPExtendedStatusCodes
 - quickSpin, [399](#)
- GevGVCPExtendedStatusCodesSelector
 - quickSpin, [399](#)
- GevGVCPHeartbeatDisable
 - quickSpin, [399](#)
- GevGVCPPendingAck
 - quickSpin, [400](#)
- GevGVCPPendingTimeout
 - quickSpin, [400](#)
- GevGVSPExtendedIDMode
 - quickSpin, [400](#)
- GevHeartbeatTimeout
 - quickSpin, [400](#)
- GevIEEE1588
 - quickSpin, [400](#)
- GevIEEE1588ClockAccuracy
 - quickSpin, [400](#)
- GevIEEE1588Mode
 - quickSpin, [400](#)
- GevIEEE1588Status
 - quickSpin, [400](#)
- GevIPConfigurationStatus
 - quickSpin, [401](#)
- GevInterfaceDefaultGateway
 - quickSpinTLSystem, [447](#)
- GevInterfaceDefaultIPAddress
 - quickSpinTLSystem, [447](#)
- GevInterfaceDefaultSubnetMask
 - quickSpinTLSystem, [447](#)
- GevInterfaceGateway
 - quickSpinTLInterface, [438](#)
- GevInterfaceGatewaySelector
 - quickSpinTLInterface, [438](#)
- GevInterfaceMACAddress
 - quickSpinTLInterface, [438](#)
 - quickSpinTLSystem, [447](#)
- GevInterfaceMTU
 - quickSpinTLInterface, [439](#)
- GevInterfaceReceiveLinkSpeed
 - quickSpinTLInterface, [439](#)
- GevInterfaceSelector
 - quickSpin, [401](#)
- GevInterfaceSubnetIPAddress
 - quickSpinTLInterface, [439](#)
- GevInterfaceSubnetMask
 - quickSpinTLInterface, [439](#)
- GevInterfaceSubnetSelector
 - quickSpinTLInterface, [439](#)
- GevInterfaceTransmitLinkSpeed
 - quickSpinTLInterface, [439](#)
- GevMACAddress
 - quickSpin, [401](#)
- GevMCDA
 - quickSpin, [401](#)
- GevMCPHostPort
 - quickSpin, [401](#)
- GevMCRC
 - quickSpin, [401](#)
- GevMCSP
 - quickSpin, [401](#)
- GevMCTT
 - quickSpin, [401](#)
- GevMaximumNumberResendRequests
 - quickSpinTLStream, [442](#)
- GevNumberOfInterfaces
 - quickSpin, [402](#)
- GevPAUSEFrameReception
 - quickSpin, [402](#)
- GevPAUSEFrameTransmission
 - quickSpin, [402](#)
- GevPacketResendMode
 - quickSpinTLStream, [442](#)
- GevPacketResendTimeout
 - quickSpinTLStream, [443](#)
- GevPersistentDefaultGateway
 - quickSpin, [402](#)
- GevPersistentIPAddress
 - quickSpin, [402](#)
- GevPersistentSubnetMask
 - quickSpin, [402](#)
- GevPhysicalLinkConfiguration
 - quickSpin, [402](#)
- GevPrimaryApplicationIPAddress
 - quickSpin, [402](#)
- GevPrimaryApplicationSocket
 - quickSpin, [403](#)
- GevPrimaryApplicationSwitchoverKey
 - quickSpin, [403](#)
- GevResendPacketCount
 - quickSpinTLStream, [443](#)

- GevResendRequestCount
 - quickSpinTLStream, [443](#)
- GevSCCFGAllInTransmission
 - quickSpin, [403](#)
- GevSCCFGExtendedChunkData
 - quickSpin, [403](#)
- GevSCCFGPacketResendDestination
 - quickSpin, [403](#)
- GevSCCFGUnconditionalStreaming
 - quickSpin, [403](#)
- GevSCDA
 - quickSpin, [403](#)
- GevSCPDDirection
 - quickSpin, [404](#)
- GevSCPHostPort
 - quickSpin, [404](#)
- GevSCPIInterfaceIndex
 - quickSpin, [404](#)
- GevSCPSBigEndian
 - quickSpin, [404](#)
- GevSCPSDoNotFragment
 - quickSpin, [404](#)
- GevSCPSFireTestPacket
 - quickSpin, [404](#)
- GevSCPSPacketSize
 - quickSpin, [404](#)
- GevSCPD
 - quickSpin, [403](#)
- GevSCSP
 - quickSpin, [404](#)
- GevSCZoneConfigurationLock
 - quickSpin, [405](#)
- GevSCZoneCount
 - quickSpin, [405](#)
- GevSCZoneDirectionAll
 - quickSpin, [405](#)
- GevSecondURL
 - quickSpin, [405](#)
- GevStreamChannelSelector
 - quickSpin, [405](#)
- GevSupportedOption
 - quickSpin, [405](#)
- GevSupportedOptionSelector
 - quickSpin, [405](#)
- GevTimestampTickFrequency
 - quickSpin, [405](#)
- GevTotalPacketCount
 - quickSpinTLStream, [443](#)
- GevVersionMajor
 - quickSpinTLDDevice, [434](#)
 - quickSpinTLSystem, [448](#)
- GevVersionMinor
 - quickSpinTLDDevice, [434](#)
 - quickSpinTLSystem, [448](#)
- GuiXmlManifestAddress
 - quickSpin, [406](#)
- Height
 - quickSpin, [406](#)
- height
 - spinH264Option, [458](#)
- HeightMax
 - quickSpin, [406](#)
- HostAdapterDriverVersion
 - quickSpinTLInterface, [439](#)
- HostAdapterName
 - quickSpinTLInterface, [439](#)
- HostAdapterVendor
 - quickSpinTLInterface, [440](#)
- IBoolean Access, [290](#)
 - spinBooleanGetValue, [290](#)
 - spinBooleanSetValue, [291](#)
- ICategory Access, [294](#)
 - spinCategoryGetFeatureByIndex, [294](#)
 - spinCategoryGetNumFeatures, [295](#)
- ICommand Access, [292](#)
 - spinCommandExecute, [292](#)
 - spinCommandIsDone, [293](#)
- IEnumEntry Access, [287](#)
 - spinEnumerationEntryGetEnumValue, [287](#)
 - spinEnumerationEntryGetIntValue, [288](#)
 - spinEnumerationEntryGetSymbolic, [288](#)
- IEnumeration Access, [283](#)
 - spinEnumerationGetCurrentEntry, [283](#)
 - spinEnumerationGetEntryByIndex, [284](#)
 - spinEnumerationGetEntryByName, [284](#)
 - spinEnumerationGetNumEntries, [285](#)
 - spinEnumerationSetEnumValue, [285](#)
 - spinEnumerationSetIntValue, [286](#)
- IFloat Access, [278](#)
 - spinFloatGetMax, [278](#)
 - spinFloatGetMin, [279](#)
 - spinFloatGetRepresentation, [279](#)
 - spinFloatGetUnit, [280](#)
 - spinFloatGetValue, [280](#)
 - spinFloatGetValueEx, [281](#)
 - spinFloatSetValue, [281](#)
 - spinFloatSetValueEx, [282](#)
- IInteger Access, [273](#)
 - spinIntegerGetInc, [273](#)
 - spinIntegerGetMax, [274](#)
 - spinIntegerGetMin, [274](#)
 - spinIntegerGetRepresentation, [275](#)
 - spinIntegerGetValue, [275](#)
 - spinIntegerGetValueEx, [276](#)
 - spinIntegerSetValue, [276](#)
 - spinIntegerSetValueEx, [277](#)
- IRegister Access, [296](#)
 - spinRegisterGet, [296](#)
 - spinRegisterGetAddress, [297](#)
 - spinRegisterGetEx, [297](#)
 - spinRegisterGetLength, [298](#)
 - spinRegisterSet, [299](#)
 - spinRegisterSetEx, [299](#)
 - spinRegisterSetReference, [300](#)
- IValue Access, [266](#)
 - spinNodeFromString, [266](#)

- spinNodeFromStringEx, 267
- spinNodeToString, 267
- spinNodeToStringEx, 268
- Image Access, 179
 - spinImageCalculateStatistics, 181
 - spinImageCheckCRC, 182
 - spinImageConvert, 182
 - spinImageConvertEx, 183
 - spinImageCreate, 183
 - spinImageCreateEmpty, 184
 - spinImageCreateEx, 184
 - spinImageDeepCopy, 185
 - spinImageDestroy, 185
 - spinImageGetBitsPerPixel, 186
 - spinImageGetBufferSize, 186
 - spinImageGetChunkLayoutID, 187
 - spinImageGetColorProcessing, 187
 - spinImageGetData, 188
 - spinImageGetDefaultColorProcessing, 188
 - spinImageGetFrameID, 188
 - spinImageGetHeight, 189
 - spinImageGetID, 189
 - spinImageGetOffsetX, 190
 - spinImageGetOffsetY, 190
 - spinImageGetPaddingX, 191
 - spinImageGetPaddingY, 191
 - spinImageGetPayloadType, 192
 - spinImageGetPixelFormat, 192
 - spinImageGetPixelFormatName, 193
 - spinImageGetPrivateData, 193
 - spinImageGetSize, 194
 - spinImageGetStatus, 194
 - spinImageGetStatusDescription, 195
 - spinImageGetStride, 195
 - spinImageGetTLPayloadType, 196
 - spinImageGetTLPixelFormat, 197
 - spinImageGetTLPixelFormatNamespace, 197
 - spinImageGetTimeStamp, 196
 - spinImageGetValidPayloadSize, 198
 - spinImageGetWidth, 198
 - spinImageHasCRC, 199
 - spinImageIsIncomplete, 199
 - spinImageRelease, 200
 - spinImageReset, 200
 - spinImageResetEx, 201
 - spinImageSave, 202
 - spinImageSaveBmp, 202
 - spinImageSaveFromExt, 203
 - spinImageSaveJpeg, 203
 - spinImageSaveJpg2, 204
 - spinImageSavePgm, 204
 - spinImageSavePng, 205
 - spinImageSavePpm, 205
 - spinImageSaveTiff, 206
 - spinImageSetDefaultColorProcessing, 206
- ImageComponentEnable
 - quickSpin, 406
- ImageComponentSelector
 - quickSpin, 406
- ImageCompressionBitrate
 - quickSpin, 406
- ImageCompressionJPEGFormatOption
 - quickSpin, 406
- ImageCompressionMode
 - quickSpin, 406
- ImageCompressionQuality
 - quickSpin, 407
- ImageCompressionRateOption
 - quickSpin, 407
- ImageStatistics Access, 215
 - spinImageStatisticsCreate, 216
 - spinImageStatisticsDestroy, 216
 - spinImageStatisticsDisableAll, 216
 - spinImageStatisticsEnableAll, 217
 - spinImageStatisticsEnableGreyOnly, 217
 - spinImageStatisticsEnableHslOnly, 218
 - spinImageStatisticsEnableRgbOnly, 218
 - spinImageStatisticsGetAll, 219
 - spinImageStatisticsGetChannelStatus, 219
 - spinImageStatisticsGetHistogram, 220
 - spinImageStatisticsGetMean, 220
 - spinImageStatisticsGetNumPixelValues, 221
 - spinImageStatisticsGetPixelValueRange, 221
 - spinImageStatisticsGetRange, 222
 - spinImageStatisticsSetChannelStatus, 222
- include/spinc/CameraDefsC.h, 467
- include/spinc/ChunkDataDefC.h, 500
- include/spinc/QuickSpinC.h, 501
- include/spinc/QuickSpinDefsC.h, 501
- include/spinc/SpinVideoC.h, 525
- include/spinc/SpinnakerC.h, 503
- include/spinc/SpinnakerDefsC.h, 512
- include/spinc/SpinnakerGenApiC.h, 517
- include/spinc/SpinnakerGenApiDefsC.h, 521
- include/spinc/SpinnakerPlatformC.h, 524
- include/spinc/TransportLayerDefsC.h, 526
- include/spinc/TransportLayerDeviceC.h, 528
- include/spinc/TransportLayerInterfaceC.h, 528
- include/spinc/TransportLayerStreamC.h, 529
- include/spinc/TransportLayerSystemC.h, 530
- IncompatibleDeviceCount
 - quickSpinTLInterface, 440
- IncompatibleDeviceID
 - quickSpinTLInterface, 440
- IncompatibleDeviceModelName
 - quickSpinTLInterface, 440
- IncompatibleDeviceSelector
 - quickSpinTLInterface, 440
- IncompatibleDeviceVendorName
 - quickSpinTLInterface, 440
- IncompatibleGevDeviceIPAddress
 - quickSpinTLInterface, 440
- IncompatibleGevDeviceMACAddress
 - quickSpinTLInterface, 440
- IncompatibleGevDeviceSubnetMask
 - quickSpinTLInterface, 441

- indexedColor_8bit
 - spinBMPOption, [451](#)
- Interface Access, [159](#)
 - spinInterfaceGetCameras, [160](#)
 - spinInterfaceGetCamerasEx, [160](#)
 - spinInterfaceGetTLNodeMap, [161](#)
 - spinInterfaceIsInUse, [161](#)
 - spinInterfaceRegisterDeviceArrivalEventHandler, [162](#)
 - spinInterfaceRegisterDeviceRemovalEvent↔Handler, [162](#)
 - spinInterfaceRegisterInterfaceEventHandler, [163](#)
 - spinInterfaceRelease, [163](#)
 - spinInterfaceSendActionCommand, [164](#)
 - spinInterfaceUnregisterDeviceArrivalEventHandler, [164](#)
 - spinInterfaceUnregisterDeviceRemovalEvent↔Handler, [165](#)
 - spinInterfaceUnregisterInterfaceEventHandler, [165](#)
 - spinInterfaceUpdateCameras, [166](#)
- InterfaceDisplayName
 - quickSpinTLInterface, [441](#)
 - quickSpinTLSystem, [448](#)
- InterfaceID
 - quickSpinTLInterface, [441](#)
 - quickSpinTLSystem, [448](#)
- InterfaceList Access, [149](#)
 - spinInterfaceListClear, [149](#)
 - spinInterfaceListCreateEmpty, [150](#)
 - spinInterfaceListDestroy, [150](#)
 - spinInterfaceListGet, [151](#)
 - spinInterfaceListGetSize, [151](#)
- InterfaceSelector
 - quickSpinTLSystem, [448](#)
- InterfaceType
 - quickSpinTLInterface, [441](#)
- InterfaceUpdateList
 - quickSpinTLSystem, [448](#)
- interlaced
 - spinPNGOption, [464](#)
- IspEnable
 - quickSpin, [407](#)
- LUTEnable
 - quickSpin, [409](#)
- LUTIndex
 - quickSpin, [410](#)
- LUTSelector
 - quickSpin, [410](#)
- LUTValue
 - quickSpin, [410](#)
- LUTValueAll
 - quickSpin, [410](#)
- LineFilterWidth
 - quickSpin, [407](#)
- LineFormat
 - quickSpin, [407](#)
- LineInputFilterSelector
 - quickSpin, [407](#)
- LineInverter
 - quickSpin, [407](#)
- LineMode
 - quickSpin, [407](#)
- LinePitch
 - quickSpin, [408](#)
- LineSelector
 - quickSpin, [408](#)
- LineSource
 - quickSpin, [408](#)
- LineStatus
 - quickSpin, [408](#)
- LineStatusAll
 - quickSpin, [408](#)
- LinkErrorCount
 - quickSpin, [408](#)
- LinkUptime
 - quickSpin, [408](#)
- Logging Event Data Access, [224](#)
 - spinLogDataGetCategoryName, [224](#)
 - spinLogDataGetLogMessage, [225](#)
 - spinLogDataGetNDC, [225](#)
 - spinLogDataGetPriority, [226](#)
 - spinLogDataGetPriorityName, [226](#)
 - spinLogDataGetThreadName, [227](#)
 - spinLogDataGetTimestamp, [227](#)
- LogicBlockLUTInputActivation
 - quickSpin, [408](#)
- LogicBlockLUTInputSelector
 - quickSpin, [409](#)
- LogicBlockLUTInputSource
 - quickSpin, [409](#)
- LogicBlockLUTOutputValue
 - quickSpin, [409](#)
- LogicBlockLUTOutputValueAll
 - quickSpin, [409](#)
- LogicBlockLUTRowIndex
 - quickSpin, [409](#)
- LogicBlockLUTSelector
 - quickSpin, [409](#)
- LogicBlockSelector
 - quickSpin, [409](#)
- m_blackLevel
 - spinChunkData, [452](#)
- m_cRC
 - spinChunkData, [453](#)
- m_counterValue
 - spinChunkData, [452](#)
- m_encoderValue
 - spinChunkData, [453](#)
- m_exposureEndLineStatusAll
 - spinChunkData, [453](#)
- m_exposureTime
 - spinChunkData, [453](#)
- m_frameID
 - spinChunkData, [453](#)
- m_gain
 - spinChunkData, [453](#)

- m_height
 - spinChunkData, [453](#)
- m_image
 - spinChunkData, [453](#)
- m_inferenceConfidence
 - spinChunkData, [454](#)
- m_inferenceFrameId
 - spinChunkData, [454](#)
- m_inferenceResult
 - spinChunkData, [454](#)
- m_linePitch
 - spinChunkData, [454](#)
- m_lineStatusAll
 - spinChunkData, [454](#)
- m_offsetX
 - spinChunkData, [454](#)
- m_offsetY
 - spinChunkData, [454](#)
- m_partSelector
 - spinChunkData, [454](#)
- m_pixelDynamicRangeMax
 - spinChunkData, [455](#)
- m_pixelDynamicRangeMin
 - spinChunkData, [455](#)
- m_scan3dAxisMax
 - spinChunkData, [455](#)
- m_scan3dAxisMin
 - spinChunkData, [455](#)
- m_scan3dCoordinateOffset
 - spinChunkData, [455](#)
- m_scan3dCoordinateReferenceValue
 - spinChunkData, [455](#)
- m_scan3dCoordinateScale
 - spinChunkData, [455](#)
- m_scan3dInvalidDataValue
 - spinChunkData, [455](#)
- m_scan3dTransformValue
 - spinChunkData, [456](#)
- m_scanLineSelector
 - spinChunkData, [456](#)
- m_sequencerSetActive
 - spinChunkData, [456](#)
- m_serialDataLength
 - spinChunkData, [456](#)
- m_streamChannelID
 - spinChunkData, [456](#)
- m_timerValue
 - spinChunkData, [456](#)
- m_timestamp
 - spinChunkData, [456](#)
- m_timestampLatchValue
 - spinChunkData, [456](#)
- m_transferBlockID
 - spinChunkData, [457](#)
- m_transferQueueCurrentBlockCount
 - spinChunkData, [457](#)
- m_width
 - spinChunkData, [457](#)
- major
 - spinLibraryVersion, [461](#)
- MaxDeviceResetTime
 - quickSpin, [410](#)
- minor
 - spinLibraryVersion, [461](#)
- Node Access, [254](#)
 - spinNodeDeregisterCallback, [255](#)
 - spinNodeGetAccessMode, [255](#)
 - spinNodeGetCachingMode, [256](#)
 - spinNodeGetDescription, [256](#)
 - spinNodeGetDisplayName, [257](#)
 - spinNodeGetImposedAccessMode, [258](#)
 - spinNodeGetImposedVisibility, [258](#)
 - spinNodeGetName, [258](#)
 - spinNodeGetNameSpace, [259](#)
 - spinNodeGetPollingTime, [259](#)
 - spinNodeGetToolTip, [260](#)
 - spinNodeGetType, [260](#)
 - spinNodeGetVisibility, [261](#)
 - spinNodeInvalidateNode, [261](#)
 - spinNodesAvailable, [262](#)
 - spinNodesEqual, [262](#)
 - spinNodesImplemented, [263](#)
 - spinNodesReadable, [263](#)
 - spinNodesWritable, [264](#)
 - spinNodeRegisterCallback, [264](#)
- Node Map Access, [251](#)
 - spinNodeMapGetNode, [251](#)
 - spinNodeMapGetNodeByIndex, [252](#)
 - spinNodeMapGetNumNodes, [252](#)
 - spinNodeMapPoll, [253](#)
- OffsetX
 - quickSpin, [410](#)
- OffsetY
 - quickSpin, [410](#)
- POEStatus
 - quickSpinTLInterface, [441](#)
- PacketResendRequestCount
 - quickSpin, [410](#)
- PayloadSize
 - quickSpin, [411](#)
- PixelColorFilter
 - quickSpin, [411](#)
- PixelDynamicRangeMax
 - quickSpin, [411](#)
- PixelDynamicRangeMin
 - quickSpin, [411](#)
- PixelFormat
 - quickSpin, [411](#)
- PixelFormatInfoID
 - quickSpin, [411](#)
- PixelFormatInfoSelector
 - quickSpin, [411](#)
- PixelSize
 - quickSpin, [411](#)

- PowerSupplyCurrent
 - quickSpin, [412](#)
- PowerSupplyVoltage
 - quickSpin, [412](#)
- progressive
 - spinJPEGOption, [459](#)
- quality
 - spinJPEGOption, [459](#)
 - spinJPG2Option, [460](#)
 - spinMJPEGOption, [462](#)
- quickSpin, [332](#)
 - aPAUSEMACCtrlFramesReceived, [347](#)
 - aPAUSEMACCtrlFramesTransmitted, [347](#)
 - AasRoiEnable, [344](#)
 - AasRoiHeight, [344](#)
 - AasRoiOffsetX, [344](#)
 - AasRoiOffsetY, [344](#)
 - AasRoiWidth, [344](#)
 - AcquisitionAbort, [345](#)
 - AcquisitionArm, [345](#)
 - AcquisitionBurstFrameCount, [345](#)
 - AcquisitionFrameCount, [345](#)
 - AcquisitionFrameRate, [345](#)
 - AcquisitionFrameRateEnable, [345](#)
 - AcquisitionLineRate, [345](#)
 - AcquisitionMode, [345](#)
 - AcquisitionResultingFrameRate, [346](#)
 - AcquisitionStart, [346](#)
 - AcquisitionStatus, [346](#)
 - AcquisitionStatusSelector, [346](#)
 - AcquisitionStop, [346](#)
 - ActionDeviceKey, [346](#)
 - ActionGroupKey, [346](#)
 - ActionGroupMask, [346](#)
 - ActionQueueSize, [347](#)
 - ActionSelector, [347](#)
 - ActionUnconditionalMode, [347](#)
 - AdaptiveCompressionEnable, [347](#)
 - AdcBitDepth, [347](#)
 - AutoAlgorithmSelector, [347](#)
 - AutoExposureControlLoopDamping, [348](#)
 - AutoExposureControlPriority, [348](#)
 - AutoExposureEVCompensation, [348](#)
 - AutoExposureExposureTimeLowerLimit, [348](#)
 - AutoExposureExposureTimeUpperLimit, [348](#)
 - AutoExposureGainLowerLimit, [348](#)
 - AutoExposureGainUpperLimit, [348](#)
 - AutoExposureGreyValueLowerLimit, [348](#)
 - AutoExposureGreyValueUpperLimit, [349](#)
 - AutoExposureLightingMode, [349](#)
 - AutoExposureMeteringMode, [349](#)
 - AutoExposureTargetGreyValue, [349](#)
 - AutoExposureTargetGreyValueAuto, [349](#)
 - BalanceRatio, [349](#)
 - BalanceRatioSelector, [349](#)
 - BalanceWhiteAuto, [349](#)
 - BalanceWhiteAutoDamping, [350](#)
 - BalanceWhiteAutoLowerLimit, [350](#)
 - BalanceWhiteAutoProfile, [350](#)
 - BalanceWhiteAutoUpperLimit, [350](#)
 - BinningHorizontal, [350](#)
 - BinningHorizontalMode, [350](#)
 - BinningSelector, [350](#)
 - BinningVertical, [350](#)
 - BinningVerticalMode, [351](#)
 - BlackLevel, [351](#)
 - BlackLevelAuto, [351](#)
 - BlackLevelAutoBalance, [351](#)
 - BlackLevelClampingEnable, [351](#)
 - BlackLevelRaw, [351](#)
 - BlackLevelSelector, [351](#)
 - ChunkBlackLevel, [351](#)
 - ChunkBlackLevelSelector, [352](#)
 - ChunkCRC, [352](#)
 - ChunkCounterSelector, [352](#)
 - ChunkCounterValue, [352](#)
 - ChunkEnable, [352](#)
 - ChunkEncoderSelector, [352](#)
 - ChunkEncoderStatus, [352](#)
 - ChunkEncoderValue, [352](#)
 - ChunkExposureEndLineStatusAll, [353](#)
 - ChunkExposureTime, [353](#)
 - ChunkExposureTimeSelector, [353](#)
 - ChunkFrameID, [353](#)
 - ChunkGain, [353](#)
 - ChunkGainSelector, [353](#)
 - ChunkHeight, [353](#)
 - ChunkImage, [353](#)
 - ChunkImageComponent, [354](#)
 - ChunkInferenceBoundingBoxResult, [354](#)
 - ChunkInferenceConfidence, [354](#)
 - ChunkInferenceFrameId, [354](#)
 - ChunkInferenceResult, [354](#)
 - ChunkLinePitch, [354](#)
 - ChunkLineStatusAll, [354](#)
 - ChunkModeActive, [354](#)
 - ChunkOffsetX, [355](#)
 - ChunkOffsetY, [355](#)
 - ChunkPartSelector, [355](#)
 - ChunkPixelDynamicRangeMax, [355](#)
 - ChunkPixelDynamicRangeMin, [355](#)
 - ChunkPixelFormat, [355](#)
 - ChunkRegionID, [355](#)
 - ChunkScan3dAxisMax, [355](#)
 - ChunkScan3dAxisMin, [356](#)
 - ChunkScan3dCoordinateOffset, [356](#)
 - ChunkScan3dCoordinateReferenceSelector, [356](#)
 - ChunkScan3dCoordinateReferenceValue, [356](#)
 - ChunkScan3dCoordinateScale, [356](#)
 - ChunkScan3dCoordinateSelector, [356](#)
 - ChunkScan3dCoordinateSystem, [356](#)
 - ChunkScan3dCoordinateSystemReference, [356](#)
 - ChunkScan3dCoordinateTransformSelector, [357](#)
 - ChunkScan3dDistanceUnit, [357](#)
 - ChunkScan3dInvalidDataFlag, [357](#)
 - ChunkScan3dInvalidDataValue, [357](#)

- ChunkScan3dOutputMode, 357
- ChunkScan3dTransformValue, 357
- ChunkScanLineSelector, 357
- ChunkSelector, 357
- ChunkSequencerSetActive, 358
- ChunkSerialData, 358
- ChunkSerialDataLength, 358
- ChunkSerialReceiveOverflow, 358
- ChunkSourceID, 358
- ChunkStreamChannelID, 358
- ChunkTimerSelector, 358
- ChunkTimerValue, 358
- ChunkTimestamp, 359
- ChunkTimestampLatchValue, 359
- ChunkTransferBlockID, 359
- ChunkTransferQueueCurrentBlockCount, 359
- ChunkTransferStreamID, 359
- ChunkWidth, 359
- CICongfiguration, 359
- CITimeSlotsCount, 359
- ColorTransformationEnable, 360
- ColorTransformationSelector, 360
- ColorTransformationValue, 360
- ColorTransformationValueSelector, 360
- CompressionRatio, 360
- CounterDelay, 360
- CounterDuration, 360
- CounterEventActivation, 360
- CounterEventSource, 361
- CounterReset, 361
- CounterResetActivation, 361
- CounterResetSource, 361
- CounterSelector, 361
- CounterStatus, 361
- CounterTriggerActivation, 361
- CounterTriggerSource, 361
- CounterValue, 362
- CounterValueAtReset, 362
- CxpConnectionSelector, 362
- CxpConnectionTestErrorCount, 362
- CxpConnectionTestMode, 362
- CxpConnectionTestPacketCount, 362
- CxpLinkConfiguration, 362
- CxpLinkConfigurationPreferred, 362
- CxpLinkConfigurationStatus, 363
- CxpPoCxpAuto, 363
- CxpPoCxpStatus, 363
- CxpPoCxpTripReset, 363
- CxpPoCxpTurnOff, 363
- DecimationHorizontal, 363
- DecimationHorizontalMode, 363
- DecimationSelector, 363
- DecimationVertical, 364
- DecimationVerticalMode, 364
- DefectCorrectStaticEnable, 364
- DefectCorrectionMode, 364
- DefectTableApply, 364
- DefectTableCoordinateX, 364
- DefectTableCoordinateY, 364
- DefectTableFactoryRestore, 364
- DefectTableIndex, 365
- DefectTablePixelCount, 365
- DefectTableSave, 365
- Deinterlacing, 365
- DeviceCharacterSet, 365
- DeviceClockFrequency, 365
- DeviceClockSelector, 365
- DeviceConnectionSelector, 365
- DeviceConnectionSpeed, 366
- DeviceConnectionStatus, 366
- DeviceEventChannelCount, 366
- DeviceFamilyName, 366
- DeviceFeaturePersistenceEnd, 366
- DeviceFeaturePersistenceStart, 366
- DeviceFirmwareVersion, 366
- DeviceGenCPVersionMajor, 366
- DeviceGenCPVersionMinor, 367
- DeviceID, 367
- DeviceIndicatorMode, 367
- DeviceLinkBandwidthReserve, 367
- DeviceLinkCommandTimeout, 367
- DeviceLinkConnectionCount, 367
- DeviceLinkCurrentThroughput, 367
- DeviceLinkHeartbeatMode, 367
- DeviceLinkHeartbeatTimeout, 368
- DeviceLinkSelector, 368
- DeviceLinkSpeed, 368
- DeviceLinkThroughputLimit, 368
- DeviceLinkThroughputLimitMode, 368
- DeviceManifestEntrySelector, 368
- DeviceManifestPrimaryURL, 368
- DeviceManifestSchemaMajorVersion, 368
- DeviceManifestSchemaMinorVersion, 369
- DeviceManifestSecondaryURL, 369
- DeviceManifestXMLMajorVersion, 369
- DeviceManifestXMLMinorVersion, 369
- DeviceManifestXMLSubMinorVersion, 369
- DeviceManufacturerInfo, 369
- DeviceMaxThroughput, 369
- DeviceModelName, 369
- DevicePowerSupplySelector, 370
- DeviceRegistersCheck, 370
- DeviceRegistersEndianness, 370
- DeviceRegistersStreamingEnd, 370
- DeviceRegistersStreamingStart, 370
- DeviceRegistersValid, 370
- DeviceReset, 370
- DeviceSFNCVersionMajor, 371
- DeviceSFNCVersionMinor, 371
- DeviceSFNCVersionSubMinor, 371
- DeviceScanType, 370
- DeviceSerialNumber, 371
- DeviceSerialPortBaudRate, 371
- DeviceSerialPortSelector, 371
- DeviceStreamChannelCount, 371
- DeviceStreamChannelEndianness, 371

DeviceStreamChannelLink, [372](#)
DeviceStreamChannelPacketSize, [372](#)
DeviceStreamChannelSelector, [372](#)
DeviceStreamChannelType, [372](#)
DeviceTLType, [372](#)
DeviceTLVersionMajor, [373](#)
DeviceTLVersionMinor, [373](#)
DeviceTLVersionSubMinor, [373](#)
DeviceTapGeometry, [372](#)
DeviceTemperature, [372](#)
DeviceTemperatureSelector, [372](#)
DeviceType, [373](#)
DeviceUptime, [373](#)
DeviceUserID, [373](#)
DeviceVendorName, [373](#)
DeviceVersion, [373](#)
EncoderDivider, [374](#)
EncoderMode, [374](#)
EncoderOutputMode, [374](#)
EncoderReset, [374](#)
EncoderResetActivation, [374](#)
EncoderResetSource, [374](#)
EncoderSelector, [374](#)
EncoderSourceA, [374](#)
EncoderSourceB, [375](#)
EncoderStatus, [375](#)
EncoderTimeout, [375](#)
EncoderValue, [375](#)
EncoderValueAtReset, [375](#)
EnumerationCount, [375](#)
EventAcquisitionEnd, [375](#)
EventAcquisitionEndFrameID, [375](#)
EventAcquisitionEndTimestamp, [376](#)
EventAcquisitionError, [376](#)
EventAcquisitionErrorFrameID, [376](#)
EventAcquisitionErrorTimestamp, [376](#)
EventAcquisitionStart, [376](#)
EventAcquisitionStartFrameID, [376](#)
EventAcquisitionStartTimestamp, [376](#)
EventAcquisitionTransferEnd, [376](#)
EventAcquisitionTransferEndFrameID, [377](#)
EventAcquisitionTransferEndTimestamp, [377](#)
EventAcquisitionTransferStart, [377](#)
EventAcquisitionTransferStartFrameID, [377](#)
EventAcquisitionTransferStartTimestamp, [377](#)
EventAcquisitionTrigger, [377](#)
EventAcquisitionTriggerFrameID, [377](#)
EventAcquisitionTriggerTimestamp, [377](#)
EventActionLate, [378](#)
EventActionLateFrameID, [378](#)
EventActionLateTimestamp, [378](#)
EventCounter0End, [378](#)
EventCounter0EndFrameID, [378](#)
EventCounter0EndTimestamp, [378](#)
EventCounter0Start, [378](#)
EventCounter0StartFrameID, [378](#)
EventCounter0StartTimestamp, [379](#)
EventCounter1End, [379](#)
EventCounter1EndFrameID, [379](#)
EventCounter1EndTimestamp, [379](#)
EventCounter1Start, [379](#)
EventCounter1StartFrameID, [379](#)
EventCounter1StartTimestamp, [379](#)
EventEncoder0Restarted, [379](#)
EventEncoder0RestartedFrameID, [380](#)
EventEncoder0RestartedTimestamp, [380](#)
EventEncoder0Stopped, [380](#)
EventEncoder0StoppedFrameID, [380](#)
EventEncoder0StoppedTimestamp, [380](#)
EventEncoder1Restarted, [380](#)
EventEncoder1RestartedFrameID, [380](#)
EventEncoder1RestartedTimestamp, [380](#)
EventEncoder1Stopped, [381](#)
EventEncoder1StoppedFrameID, [381](#)
EventEncoder1StoppedTimestamp, [381](#)
EventError, [381](#)
EventErrorCode, [381](#)
EventErrorFrameID, [381](#)
EventErrorTimestamp, [381](#)
EventExposureEnd, [381](#)
EventExposureEndFrameID, [382](#)
EventExposureEndTimestamp, [382](#)
EventExposureStart, [382](#)
EventExposureStartFrameID, [382](#)
EventExposureStartTimestamp, [382](#)
EventFrameBurstEnd, [382](#)
EventFrameBurstEndFrameID, [382](#)
EventFrameBurstEndTimestamp, [382](#)
EventFrameBurstStart, [383](#)
EventFrameBurstStartFrameID, [383](#)
EventFrameBurstStartTimestamp, [383](#)
EventFrameEnd, [383](#)
EventFrameEndFrameID, [383](#)
EventFrameEndTimestamp, [383](#)
EventFrameStart, [383](#)
EventFrameStartFrameID, [383](#)
EventFrameStartTimestamp, [384](#)
EventFrameTransferEnd, [384](#)
EventFrameTransferEndFrameID, [384](#)
EventFrameTransferEndTimestamp, [384](#)
EventFrameTransferStart, [384](#)
EventFrameTransferStartFrameID, [384](#)
EventFrameTransferStartTimestamp, [384](#)
EventFrameTrigger, [384](#)
EventFrameTriggerFrameID, [385](#)
EventFrameTriggerTimestamp, [385](#)
EventLine0AnyEdge, [385](#)
EventLine0AnyEdgeFrameID, [385](#)
EventLine0AnyEdgeTimestamp, [385](#)
EventLine0FallingEdge, [385](#)
EventLine0FallingEdgeFrameID, [385](#)
EventLine0FallingEdgeTimestamp, [385](#)
EventLine0RisingEdge, [386](#)
EventLine0RisingEdgeFrameID, [386](#)
EventLine0RisingEdgeTimestamp, [386](#)
EventLine1AnyEdge, [386](#)

- EventLine1AnyEdgeFrameID, [386](#)
- EventLine1AnyEdgeTimestamp, [386](#)
- EventLine1FallingEdge, [386](#)
- EventLine1FallingEdgeFrameID, [386](#)
- EventLine1FallingEdgeTimestamp, [387](#)
- EventLine1RisingEdge, [387](#)
- EventLine1RisingEdgeFrameID, [387](#)
- EventLine1RisingEdgeTimestamp, [387](#)
- EventLinkSpeedChange, [387](#)
- EventLinkSpeedChangeFrameID, [387](#)
- EventLinkSpeedChangeTimestamp, [387](#)
- EventLinkTrigger0, [387](#)
- EventLinkTrigger0FrameID, [388](#)
- EventLinkTrigger0Timestamp, [388](#)
- EventLinkTrigger1, [388](#)
- EventLinkTrigger1FrameID, [388](#)
- EventLinkTrigger1Timestamp, [388](#)
- EventNotification, [388](#)
- EventSelector, [388](#)
- EventSequencerSetChange, [388](#)
- EventSequencerSetChangeFrameID, [389](#)
- EventSequencerSetChangeTimestamp, [389](#)
- EventSerialData, [389](#)
- EventSerialDataLength, [389](#)
- EventSerialPortReceive, [389](#)
- EventSerialPortReceiveTimestamp, [389](#)
- EventSerialReceiveOverflow, [389](#)
- EventStream0TransferBlockEnd, [389](#)
- EventStream0TransferBlockEndFrameID, [390](#)
- EventStream0TransferBlockEndTimestamp, [390](#)
- EventStream0TransferBlockStart, [390](#)
- EventStream0TransferBlockStartFrameID, [390](#)
- EventStream0TransferBlockStartTimestamp, [390](#)
- EventStream0TransferBlockTrigger, [390](#)
- EventStream0TransferBlockTriggerFrameID, [390](#)
- EventStream0TransferBlockTriggerTimestamp, [390](#)
- EventStream0TransferBurstEnd, [391](#)
- EventStream0TransferBurstEndFrameID, [391](#)
- EventStream0TransferBurstEndTimestamp, [391](#)
- EventStream0TransferBurstStart, [391](#)
- EventStream0TransferBurstStartFrameID, [391](#)
- EventStream0TransferBurstStartTimestamp, [391](#)
- EventStream0TransferEnd, [391](#)
- EventStream0TransferEndFrameID, [391](#)
- EventStream0TransferEndTimestamp, [392](#)
- EventStream0TransferOverflow, [392](#)
- EventStream0TransferOverflowFrameID, [392](#)
- EventStream0TransferOverflowTimestamp, [392](#)
- EventStream0TransferPause, [392](#)
- EventStream0TransferPauseFrameID, [392](#)
- EventStream0TransferPauseTimestamp, [392](#)
- EventStream0TransferResume, [392](#)
- EventStream0TransferResumeFrameID, [393](#)
- EventStream0TransferResumeTimestamp, [393](#)
- EventStream0TransferStart, [393](#)
- EventStream0TransferStartFrameID, [393](#)
- EventStream0TransferStartTimestamp, [393](#)
- EventTest, [393](#)
- EventTestTimestamp, [393](#)
- EventTimer0End, [393](#)
- EventTimer0EndFrameID, [394](#)
- EventTimer0EndTimestamp, [394](#)
- EventTimer0Start, [394](#)
- EventTimer0StartFrameID, [394](#)
- EventTimer0StartTimestamp, [394](#)
- EventTimer1End, [394](#)
- EventTimer1EndFrameID, [394](#)
- EventTimer1EndTimestamp, [394](#)
- EventTimer1Start, [395](#)
- EventTimer1StartFrameID, [395](#)
- EventTimer1StartTimestamp, [395](#)
- ExposureActiveMode, [395](#)
- ExposureAuto, [395](#)
- ExposureMode, [395](#)
- ExposureTime, [395](#)
- ExposureTimeMode, [395](#)
- ExposureTimeSelector, [396](#)
- FactoryReset, [396](#)
- FileAccessBuffer, [396](#)
- FileAccessLength, [396](#)
- FileAccessOffset, [396](#)
- FileOpenMode, [396](#)
- FileOperationExecute, [396](#)
- FileOperationResult, [396](#)
- FileOperationSelector, [397](#)
- FileOperationStatus, [397](#)
- FileSelector, [397](#)
- FileSize, [397](#)
- Gain, [397](#)
- GainAuto, [397](#)
- GainAutoBalance, [397](#)
- GainSelector, [397](#)
- Gamma, [398](#)
- GammaEnable, [398](#)
- GevActiveLinkCount, [398](#)
- GevCCP, [398](#)
- GevCurrentDefaultGateway, [398](#)
- GevCurrentIPAddress, [398](#)
- GevCurrentIPConfigurationDHCP, [398](#)
- GevCurrentIPConfigurationLLA, [398](#)
- GevCurrentIPConfigurationPersistentIP, [399](#)
- GevCurrentPhysicalLinkConfiguration, [399](#)
- GevCurrentSubnetMask, [399](#)
- GevDiscoveryAckDelay, [399](#)
- GevFirstURL, [399](#)
- GevGVCPExtendedStatusCodes, [399](#)
- GevGVCPExtendedStatusCodesSelector, [399](#)
- GevGVCPHeartbeatDisable, [399](#)
- GevGVCPPendingAck, [400](#)
- GevGVCPPendingTimeout, [400](#)
- GevGVSPExtendedIDMode, [400](#)
- GevHeartbeatTimeout, [400](#)
- GevIEEE1588, [400](#)
- GevIEEE1588ClockAccuracy, [400](#)
- GevIEEE1588Mode, [400](#)
- GevIEEE1588Status, [400](#)

GevIPConfigurationStatus, 401
GevInterfaceSelector, 401
GevMACAddress, 401
GevMCDA, 401
GevMCPHostPort, 401
GevMCRC, 401
GevMCSP, 401
GevMCTT, 401
GevNumberOfInterfaces, 402
GevPAUSEFrameReception, 402
GevPAUSEFrameTransmission, 402
GevPersistentDefaultGateway, 402
GevPersistentIPAddress, 402
GevPersistentSubnetMask, 402
GevPhysicalLinkConfiguration, 402
GevPrimaryApplicationIPAddress, 402
GevPrimaryApplicationSocket, 403
GevPrimaryApplicationSwitchoverKey, 403
GevSCCFGAllInTransmission, 403
GevSCCFGExtendedChunkData, 403
GevSCCFGPacketResendDestination, 403
GevSCCFGUnconditionalStreaming, 403
GevSCDA, 403
GevSCPDirection, 404
GevSCPHostPort, 404
GevSCPInterfaceIndex, 404
GevSCPSBigEndian, 404
GevSCPSPDoNotFragment, 404
GevSCPSPFireTestPacket, 404
GevSCPSPPacketSize, 404
GevSCPD, 403
GevSCSP, 404
GevSCZoneConfigurationLock, 405
GevSCZoneCount, 405
GevSCZoneDirectionAll, 405
GevSecondURL, 405
GevStreamChannelSelector, 405
GevSupportedOption, 405
GevSupportedOptionSelector, 405
GevTimestampTickFrequency, 405
GuiXmlManifestAddress, 406
Height, 406
HeightMax, 406
ImageComponentEnable, 406
ImageComponentSelector, 406
ImageCompressionBitrate, 406
ImageCompressionJPEGFormatOption, 406
ImageCompressionMode, 406
ImageCompressionQuality, 407
ImageCompressionRateOption, 407
IspEnable, 407
LUTEnable, 409
LUTIndex, 410
LUTSelector, 410
LUTValue, 410
LUTValueAll, 410
LineFilterWidth, 407
LineFormat, 407
LineInputFilterSelector, 407
LineInverter, 407
LineMode, 407
LinePitch, 408
LineSelector, 408
LineSource, 408
LineStatus, 408
LineStatusAll, 408
LinkErrorCount, 408
LinkUptime, 408
LogicBlockLUTInputActivation, 408
LogicBlockLUTInputSelector, 409
LogicBlockLUTInputSource, 409
LogicBlockLUTOutputValue, 409
LogicBlockLUTOutputValueAll, 409
LogicBlockLUTRowIndex, 409
LogicBlockLUTSelector, 409
LogicBlockSelector, 409
MaxDeviceResetTime, 410
OffsetX, 410
OffsetY, 410
PacketResendRequestCount, 410
PayloadSize, 411
PixelColorFilter, 411
PixelDynamicRangeMax, 411
PixelDynamicRangeMin, 411
PixelFormat, 411
PixelFormatInfoID, 411
PixelFormatInfoSelector, 411
PixelSize, 411
PowerSupplyCurrent, 412
PowerSupplyVoltage, 412
RegionDestination, 412
RegionMode, 412
RegionSelector, 412
ReverseX, 412
ReverseY, 412
RgbTransformLightSource, 412
Saturation, 413
SaturationEnable, 413
Scan3dAxisMax, 413
Scan3dAxisMin, 413
Scan3dCoordinateOffset, 413
Scan3dCoordinateReferenceSelector, 413
Scan3dCoordinateReferenceValue, 413
Scan3dCoordinateScale, 413
Scan3dCoordinateSelector, 414
Scan3dCoordinateSystem, 414
Scan3dCoordinateSystemReference, 414
Scan3dCoordinateTransformSelector, 414
Scan3dDistanceUnit, 414
Scan3dInvalidDataFlag, 414
Scan3dInvalidDataValue, 414
Scan3dOutputMode, 414
Scan3dTransformValue, 415
SensorDescription, 415
SensorDigitizationTaps, 415
SensorHeight, 415

- SensorShutterMode, [415](#)
- SensorTaps, [415](#)
- SensorWidth, [415](#)
- SequencerConfigurationMode, [415](#)
- SequencerConfigurationValid, [416](#)
- SequencerFeatureEnable, [416](#)
- SequencerMode, [416](#)
- SequencerPathSelector, [416](#)
- SequencerSetActive, [416](#)
- SequencerSetLoad, [416](#)
- SequencerSetNext, [416](#)
- SequencerSetSave, [416](#)
- SequencerSetSelector, [417](#)
- SequencerSetStart, [417](#)
- SequencerSetValid, [417](#)
- SequencerTriggerActivation, [417](#)
- SequencerTriggerSource, [417](#)
- SerialPortBaudRate, [417](#)
- SerialPortDataBits, [417](#)
- SerialPortParity, [417](#)
- SerialPortSelector, [418](#)
- SerialPortSource, [418](#)
- SerialPortStopBits, [418](#)
- SerialReceiveFramingErrorCount, [418](#)
- SerialReceiveParityErrorCount, [418](#)
- SerialReceiveQueueClear, [418](#)
- SerialReceiveQueueCurrentCharacterCount, [418](#)
- SerialReceiveQueueMaxCharacterCount, [418](#)
- SerialTransmitQueueCurrentCharacterCount, [419](#)
- SerialTransmitQueueMaxCharacterCount, [419](#)
- Sharpening, [419](#)
- SharpeningAuto, [419](#)
- SharpeningEnable, [419](#)
- SharpeningThreshold, [419](#)
- SoftwareSignalPulse, [419](#)
- SoftwareSignalSelector, [419](#)
- SourceCount, [420](#)
- SourceSelector, [420](#)
- TLParamsLocked, [422](#)
- Test0001, [420](#)
- TestEventGenerate, [420](#)
- TestPattern, [420](#)
- TestPatternGeneratorSelector, [420](#)
- TestPendingAck, [420](#)
- TimerDelay, [420](#)
- TimerDuration, [421](#)
- TimerReset, [421](#)
- TimerSelector, [421](#)
- TimerStatus, [421](#)
- TimerTriggerActivation, [421](#)
- TimerTriggerSource, [421](#)
- TimerValue, [421](#)
- Timestamp, [421](#)
- TimestampLatch, [422](#)
- TimestampLatchValue, [422](#)
- TimestampReset, [422](#)
- TransferAbort, [422](#)
- TransferBlockCount, [422](#)
- TransferBurstCount, [422](#)
- TransferComponentSelector, [422](#)
- TransferControlMode, [423](#)
- TransferOperationMode, [423](#)
- TransferPause, [423](#)
- TransferQueueCurrentBlockCount, [423](#)
- TransferQueueMaxBlockCount, [423](#)
- TransferQueueMode, [423](#)
- TransferQueueOverflowCount, [423](#)
- TransferResume, [423](#)
- TransferSelector, [424](#)
- TransferStart, [424](#)
- TransferStatus, [424](#)
- TransferStatusSelector, [424](#)
- TransferStop, [424](#)
- TransferStreamChannel, [424](#)
- TransferTriggerActivation, [424](#)
- TransferTriggerMode, [424](#)
- TransferTriggerSelector, [425](#)
- TransferTriggerSource, [425](#)
- TriggerActivation, [425](#)
- TriggerDelay, [425](#)
- TriggerDivider, [425](#)
- TriggerEventTest, [425](#)
- TriggerMode, [425](#)
- TriggerMultiplier, [425](#)
- TriggerOverlap, [426](#)
- TriggerSelector, [426](#)
- TriggerSoftware, [426](#)
- TriggerSource, [426](#)
- UserOutputSelector, [426](#)
- UserOutputValue, [426](#)
- UserOutputValueAll, [426](#)
- UserOutputValueAllMask, [426](#)
- UserSetDefault, [427](#)
- UserSetFeatureEnable, [427](#)
- UserSetLoad, [427](#)
- UserSetSave, [427](#)
- UserSetSelector, [427](#)
- V3_3Enable, [427](#)
- WhiteClip, [427](#)
- WhiteClipSelector, [427](#)
- Width, [428](#)
- WidthMax, [428](#)
- QuickSpin Access, [126](#)
 - quickSpinInit, [126](#)
 - quickSpinInitEx, [126](#)
 - quickSpinTLDeviceInit, [127](#)
 - quickSpinTLInterfaceInit, [127](#)
 - quickSpinTLStreamInit, [127](#)
 - quickSpinTLSystemInit, [127](#)
- quickSpinBooleanNode
 - QuickSpinDefsC.h, [502](#)
- quickSpinCommandNode
 - QuickSpinDefsC.h, [502](#)
- QuickSpinDefsC.h
 - quickSpinBooleanNode, [502](#)
 - quickSpinCommandNode, [502](#)

- quickSpinEnumerationNode, [502](#)
- quickSpinFloatNode, [502](#)
- quickSpinIntegerNode, [503](#)
- quickSpinRegisterNode, [503](#)
- quickSpinStringNode, [503](#)
- quickSpinEnumerationNode
 - QuickSpinDefsC.h, [502](#)
- quickSpinFloatNode
 - QuickSpinDefsC.h, [502](#)
- quickSpinInit
 - QuickSpin Access, [126](#)
- quickSpinInitEx
 - QuickSpin Access, [126](#)
- quickSpinIntegerNode
 - QuickSpinDefsC.h, [503](#)
- quickSpinRegisterNode
 - QuickSpinDefsC.h, [503](#)
- quickSpinStringNode
 - QuickSpinDefsC.h, [503](#)
- quickSpinTLDevice, [428](#)
 - DeviceAccessStatus, [429](#)
 - DeviceCurrentSpeed, [429](#)
 - DeviceDisplayName, [429](#)
 - DeviceDriverVersion, [429](#)
 - DeviceEndianessMechanism, [429](#)
 - DeviceID, [430](#)
 - DeviceInstanceId, [430](#)
 - DevicesUpdater, [430](#)
 - DeviceLinkSpeed, [430](#)
 - DeviceLocation, [430](#)
 - DeviceModelName, [430](#)
 - DeviceMulticastMonitorMode, [430](#)
 - DeviceSerialNumber, [430](#)
 - DeviceType, [431](#)
 - DeviceU3VProtocol, [431](#)
 - DeviceUserID, [431](#)
 - DeviceVendorName, [431](#)
 - DeviceVersion, [431](#)
 - GUXMLLocation, [434](#)
 - GUXMLPath, [434](#)
 - GenICamXMLLocation, [431](#)
 - GenICamXMLPath, [431](#)
 - GevCCP, [431](#)
 - GevDeviceAutoForceIP, [432](#)
 - GevDeviceDiscoverMaximumPacketSize, [432](#)
 - GevDeviceForceGateway, [432](#)
 - GevDeviceForceIPAddress, [432](#)
 - GevDeviceForceIP, [432](#)
 - GevDeviceForceSubnetMask, [432](#)
 - GevDeviceGateway, [432](#)
 - GevDeviceIPAddress, [432](#)
 - GevDevicesWrongSubnet, [433](#)
 - GevDeviceMACAddress, [433](#)
 - GevDeviceMaximumPacketSize, [433](#)
 - GevDeviceMaximumRetryCount, [433](#)
 - GevDeviceModelsBigEndian, [433](#)
 - GevDevicePort, [433](#)
 - GevDeviceReadAndWriteTimeout, [433](#)
 - GevDeviceSubnetMask, [433](#)
 - GevVersionMajor, [434](#)
 - GevVersionMinor, [434](#)
- quickSpinTLDeviceInit
 - QuickSpin Access, [127](#)
- quickSpinTLInterface, [434](#)
 - ActionCommand, [435](#)
 - DeviceAccessStatus, [435](#)
 - DeviceCount, [435](#)
 - DeviceID, [436](#)
 - DeviceModelName, [436](#)
 - DeviceSelector, [436](#)
 - DeviceSerialNumber, [436](#)
 - DeviceUnlock, [436](#)
 - DeviceUpdateList, [436](#)
 - DeviceVendorName, [436](#)
 - FilterDriverStatus, [436](#)
 - GevActionDeviceKey, [437](#)
 - GevActionGroupKey, [437](#)
 - GevActionGroupMask, [437](#)
 - GevActionTime, [437](#)
 - GevDeviceAutoForceIP, [437](#)
 - GevDeviceForceGateway, [437](#)
 - GevDeviceForceIPAddress, [437](#)
 - GevDeviceForceIP, [437](#)
 - GevDeviceForceSubnetMask, [438](#)
 - GevDeviceGateway, [438](#)
 - GevDeviceIPAddress, [438](#)
 - GevDeviceMACAddress, [438](#)
 - GevDeviceSubnetMask, [438](#)
 - GevInterfaceGateway, [438](#)
 - GevInterfaceGatewaySelector, [438](#)
 - GevInterfaceMACAddress, [438](#)
 - GevInterfaceMTU, [439](#)
 - GevInterfaceReceiveLinkSpeed, [439](#)
 - GevInterfaceSubnetIPAddress, [439](#)
 - GevInterfaceSubnetMask, [439](#)
 - GevInterfaceSubnetSelector, [439](#)
 - GevInterfaceTransmitLinkSpeed, [439](#)
 - HostAdapterDriverVersion, [439](#)
 - HostAdapterName, [439](#)
 - HostAdapterVendor, [440](#)
 - IncompatibleDeviceCount, [440](#)
 - IncompatibleDeviceID, [440](#)
 - IncompatibleDeviceModelName, [440](#)
 - IncompatibleDeviceSelector, [440](#)
 - IncompatibleDeviceVendorName, [440](#)
 - IncompatibleGevDeviceIPAddress, [440](#)
 - IncompatibleGevDeviceMACAddress, [440](#)
 - IncompatibleGevDeviceSubnetMask, [441](#)
 - InterfaceDisplayName, [441](#)
 - InterfaceID, [441](#)
 - InterfaceType, [441](#)
 - POEStatus, [441](#)
- quickSpinTLInterfaceInit
 - QuickSpin Access, [127](#)
- quickSpinTLStream, [442](#)
 - GevFailedPacketCount, [442](#)

- GevMaximumNumberResendRequests, [442](#)
- GevPacketResendMode, [442](#)
- GevPacketResendTimeout, [443](#)
- GevResendPacketCount, [443](#)
- GevResendRequestCount, [443](#)
- GevTotalPacketCount, [443](#)
- StreamAnnounceBufferMinimum, [443](#)
- StreamAnnouncedBufferCount, [443](#)
- StreamBlockTransferSize, [443](#)
- StreamBufferAlignment, [443](#)
- StreamBufferCountManual, [444](#)
- StreamBufferCountMax, [444](#)
- StreamBufferCountMode, [444](#)
- StreamBufferCountResult, [444](#)
- StreamBufferHandlingMode, [444](#)
- StreamCRCCheckEnable, [444](#)
- StreamChunkCountMaximum, [444](#)
- StreamDeliveredFrameCount, [444](#)
- StreamFailedBufferCount, [445](#)
- StreamID, [445](#)
- StreamInputBufferCount, [445](#)
- StreamIsGrabbing, [445](#)
- StreamLostFrameCount, [445](#)
- StreamOutputBufferCount, [445](#)
- StreamStartedFrameCount, [445](#)
- StreamType, [445](#)
- quickSpinTLStreamInit
 - QuickSpin Access, [127](#)
- quickSpinTLSystem, [446](#)
 - EnumerateGEVInterfaces, [446](#)
 - GenTLSFNCVersionMajor, [446](#)
 - GenTLSFNCVersionMinor, [447](#)
 - GenTLSFNCVersionSubMinor, [447](#)
 - GenTLVersionMajor, [447](#)
 - GenTLVersionMinor, [447](#)
 - GevInterfaceDefaultGateway, [447](#)
 - GevInterfaceDefaultIPAddress, [447](#)
 - GevInterfaceDefaultSubnetMask, [447](#)
 - GevInterfaceMACAddress, [447](#)
 - GevVersionMajor, [448](#)
 - GevVersionMinor, [448](#)
 - InterfaceDisplayName, [448](#)
 - InterfaceID, [448](#)
 - InterfaceSelector, [448](#)
 - InterfaceUpdateList, [448](#)
 - TLDisplayName, [448](#)
 - TLFileName, [448](#)
 - TLID, [449](#)
 - TLModelName, [449](#)
 - TLPath, [449](#)
 - TLType, [449](#)
 - TLVendorName, [449](#)
 - TLVersion, [449](#)
- quickSpinTLSystemInit
 - QuickSpin Access, [127](#)
- RegionDestination
 - quickSpin, [412](#)
- RegionMode
 - quickSpin, [412](#)
- RegionSelector
 - quickSpin, [412](#)
- reserved
 - spinAVIOption, [450](#)
 - spinBMPOption, [451](#)
 - spinH264Option, [458](#)
 - spinJPEGOption, [459](#)
 - spinJPG2Option, [460](#)
 - spinMJPEGOption, [462](#)
 - spinPGMOption, [463](#)
 - spinPNGOption, [464](#)
 - spinPPMOption, [465](#)
 - spinTIFFOption, [466](#)
- ReverseX
 - quickSpin, [412](#)
- ReverseY
 - quickSpin, [412](#)
- RgbTransformLightSource
 - quickSpin, [412](#)
- SPINNAKERC_API
 - SpinnakerPlatformC.h, [524](#)
- Saturation
 - quickSpin, [413](#)
- SaturationEnable
 - quickSpin, [413](#)
- Scan3dAxisMax
 - quickSpin, [413](#)
- Scan3dAxisMin
 - quickSpin, [413](#)
- Scan3dCoordinateOffset
 - quickSpin, [413](#)
- Scan3dCoordinateReferenceSelector
 - quickSpin, [413](#)
- Scan3dCoordinateReferenceValue
 - quickSpin, [413](#)
- Scan3dCoordinateScale
 - quickSpin, [413](#)
- Scan3dCoordinateSelector
 - quickSpin, [414](#)
- Scan3dCoordinateSystem
 - quickSpin, [414](#)
- Scan3dCoordinateSystemReference
 - quickSpin, [414](#)
- Scan3dCoordinateTransformSelector
 - quickSpin, [414](#)
- Scan3dDistanceUnit
 - quickSpin, [414](#)
- Scan3dInvalidDataFlag
 - quickSpin, [414](#)
- Scan3dInvalidDataValue
 - quickSpin, [414](#)
- Scan3dOutputMode
 - quickSpin, [414](#)
- Scan3dTransformValue
 - quickSpin, [415](#)
- SensorDescription
 - quickSpin, [415](#)

- SensorDigitizationTaps
 - [quickSpin](#), [415](#)
- SensorHeight
 - [quickSpin](#), [415](#)
- SensorShutterMode
 - [quickSpin](#), [415](#)
- SensorTaps
 - [quickSpin](#), [415](#)
- SensorWidth
 - [quickSpin](#), [415](#)
- SequencerConfigurationMode
 - [quickSpin](#), [415](#)
- SequencerConfigurationValid
 - [quickSpin](#), [416](#)
- SequencerFeatureEnable
 - [quickSpin](#), [416](#)
- SequencerMode
 - [quickSpin](#), [416](#)
- SequencerPathSelector
 - [quickSpin](#), [416](#)
- SequencerSetActive
 - [quickSpin](#), [416](#)
- SequencerSetLoad
 - [quickSpin](#), [416](#)
- SequencerSetNext
 - [quickSpin](#), [416](#)
- SequencerSetSave
 - [quickSpin](#), [416](#)
- SequencerSetSelector
 - [quickSpin](#), [417](#)
- SequencerSetStart
 - [quickSpin](#), [417](#)
- SequencerSetValid
 - [quickSpin](#), [417](#)
- SequencerTriggerActivation
 - [quickSpin](#), [417](#)
- SequencerTriggerSource
 - [quickSpin](#), [417](#)
- SerialPortBaudRate
 - [quickSpin](#), [417](#)
- SerialPortDataBits
 - [quickSpin](#), [417](#)
- SerialPortParity
 - [quickSpin](#), [417](#)
- SerialPortSelector
 - [quickSpin](#), [418](#)
- SerialPortSource
 - [quickSpin](#), [418](#)
- SerialPortStopBits
 - [quickSpin](#), [418](#)
- SerialReceiveFramingErrorCount
 - [quickSpin](#), [418](#)
- SerialReceiveParityErrorCount
 - [quickSpin](#), [418](#)
- SerialReceiveQueueClear
 - [quickSpin](#), [418](#)
- SerialReceiveQueueCurrentCharacterCount
 - [quickSpin](#), [418](#)
- SerialReceiveQueueMaxCharacterCount
 - [quickSpin](#), [418](#)
- SerialTransmitQueueCurrentCharacterCount
 - [quickSpin](#), [419](#)
- SerialTransmitQueueMaxCharacterCount
 - [quickSpin](#), [419](#)
- Sharpening
 - [quickSpin](#), [419](#)
- SharpeningAuto
 - [quickSpin](#), [419](#)
- SharpeningEnable
 - [quickSpin](#), [419](#)
- SharpeningThreshold
 - [quickSpin](#), [419](#)
- SoftwareSignalPulse
 - [quickSpin](#), [419](#)
- SoftwareSignalSelector
 - [quickSpin](#), [419](#)
- SourceCount
 - [quickSpin](#), [420](#)
- SourceSelector
 - [quickSpin](#), [420](#)
- spinAVIOption, [450](#)
 - [frameRate](#), [450](#)
 - [reserved](#), [450](#)
- spinAccessMode
 - [Spinnaker C GenICam Enumerations](#), [305](#)
- spinAcquisitionModeEnums
 - [Camera Enumerations](#), [41](#)
- spinAcquisitionStatusSelectorEnums
 - [Camera Enumerations](#), [41](#)
- spinActionUnconditionalModeEnums
 - [Camera Enumerations](#), [42](#)
- spinAdcBitDepthEnums
 - [Camera Enumerations](#), [42](#)
- spinArrivalEventFunction
 - [Spinnaker C Function Signatures](#), [237](#)
- spinAutoAlgorithmSelectorEnums
 - [Camera Enumerations](#), [42](#)
- spinAutoExposureControlPriorityEnums
 - [Camera Enumerations](#), [43](#)
- spinAutoExposureLightingModeEnums
 - [Camera Enumerations](#), [43](#)
- spinAutoExposureMeteringModeEnums
 - [Camera Enumerations](#), [43](#)
- spinAutoExposureTargetGreyValueAutoEnums
 - [Camera Enumerations](#), [44](#)
- spinBMPOption, [450](#)
 - [indexedColor_8bit](#), [451](#)
 - [reserved](#), [451](#)
- spinBalanceRatioSelectorEnums
 - [Camera Enumerations](#), [44](#)
- spinBalanceWhiteAutoEnums
 - [Camera Enumerations](#), [45](#)
- spinBalanceWhiteAutoProfileEnums
 - [Camera Enumerations](#), [45](#)
- spinBinningHorizontalModeEnums
 - [Camera Enumerations](#), [45](#)

- spinBinningSelectorEnums
 - Camera Enumerations, [46](#)
- spinBinningVerticalModeEnums
 - Camera Enumerations, [46](#)
- spinBlackLevelAutoBalanceEnums
 - Camera Enumerations, [46](#)
- spinBlackLevelAutoEnums
 - Camera Enumerations, [47](#)
- spinBlackLevelSelectorEnums
 - Camera Enumerations, [47](#)
- spinBooleanGetValue
 - IBoolean Access, [290](#)
- spinBooleanSetValue
 - IBoolean Access, [291](#)
- spinCachingMode
 - Spinnaker C GenICam Enumerations, [306](#)
- spinCamera
 - Spinnaker C Handles, [234](#)
- spinCameraBeginAcquisition
 - Camera Access, [168](#)
- spinCameraDeInit
 - Camera Access, [169](#)
- spinCameraDiscoverMaxPacketSize
 - Spinnaker C API, [129](#)
- spinCameraEndAcquisition
 - Camera Access, [169](#)
- spinCameraForceIP
 - SpinnakerC.h, [512](#)
- spinCameraGetAccessMode
 - Camera Access, [169](#)
- spinCameraGetGuiXml
 - Camera Access, [170](#)
- spinCameraGetNextImage
 - Camera Access, [170](#)
- spinCameraGetNextImageEx
 - Camera Access, [171](#)
- spinCameraGetNodeMap
 - Camera Access, [171](#)
- spinCameraGetTLDeviceNodeMap
 - Camera Access, [172](#)
- spinCameraGetTLStreamNodeMap
 - Camera Access, [172](#)
- spinCameraGetUniqueID
 - Camera Access, [173](#)
- spinCameraInit
 - Camera Access, [173](#)
- spinCamerasInitialized
 - Camera Access, [174](#)
- spinCamerasStreaming
 - Camera Access, [174](#)
- spinCamerasValid
 - Camera Access, [175](#)
- spinCameraList
 - Spinnaker C Handles, [234](#)
- spinCameraListAppend
 - CameraList Access, [153](#)
- spinCameraListClear
 - CameraList Access, [154](#)
- spinCameraListCreateEmpty
 - CameraList Access, [154](#)
- spinCameraListDestroy
 - CameraList Access, [155](#)
- spinCameraListGet
 - CameraList Access, [155](#)
- spinCameraListGetBySerial
 - CameraList Access, [156](#)
- spinCameraListGetSize
 - CameraList Access, [156](#)
- spinCameraListRemove
 - CameraList Access, [157](#)
- spinCameraListRemoveBySerial
 - CameraList Access, [157](#)
- spinCameraReadPort
 - Camera Access, [175](#)
- spinCameraRegisterDeviceEventHandler
 - Camera Access, [175](#)
- spinCameraRegisterDeviceEventHandlerEx
 - Camera Access, [176](#)
- spinCameraRegisterImageEventHandler
 - Camera Access, [176](#)
- spinCameraRelease
 - Camera Access, [177](#)
- spinCameraUnregisterDeviceEventHandler
 - Camera Access, [177](#)
- spinCameraUnregisterImageEventHandler
 - Camera Access, [178](#)
- spinCameraWritePort
 - Camera Access, [178](#)
- spinCategoryGetFeatureByIndex
 - ICategory Access, [294](#)
- spinCategoryGetNumFeatures
 - ICategory Access, [295](#)
- spinChunkBlackLevelSelectorEnums
 - Camera Enumerations, [47](#)
- spinChunkCounterSelectorEnums
 - Camera Enumerations, [47](#)
- spinChunkData, [451](#)
 - m_blackLevel, [452](#)
 - m_cRC, [453](#)
 - m_counterValue, [452](#)
 - m_encoderValue, [453](#)
 - m_exposureEndLineStatusAll, [453](#)
 - m_exposureTime, [453](#)
 - m_frameID, [453](#)
 - m_gain, [453](#)
 - m_height, [453](#)
 - m_image, [453](#)
 - m_inferenceConfidence, [454](#)
 - m_inferenceFrameId, [454](#)
 - m_inferenceResult, [454](#)
 - m_linePitch, [454](#)
 - m_lineStatusAll, [454](#)
 - m_offsetX, [454](#)
 - m_offsetY, [454](#)
 - m_partSelector, [454](#)
 - m_pixelDynamicRangeMax, [455](#)

- [m_pixelDynamicRangeMin](#), [455](#)
 - [m_scan3dAxisMax](#), [455](#)
 - [m_scan3dAxisMin](#), [455](#)
 - [m_scan3dCoordinateOffset](#), [455](#)
 - [m_scan3dCoordinateReferenceValue](#), [455](#)
 - [m_scan3dCoordinateScale](#), [455](#)
 - [m_scan3dInvalidDataValue](#), [455](#)
 - [m_scan3dTransformValue](#), [456](#)
 - [m_scanLineSelector](#), [456](#)
 - [m_sequencerSetActive](#), [456](#)
 - [m_serialDataLength](#), [456](#)
 - [m_streamChannelID](#), [456](#)
 - [m_timerValue](#), [456](#)
 - [m_timestamp](#), [456](#)
 - [m_timestampLatchValue](#), [456](#)
 - [m_transferBlockID](#), [457](#)
 - [m_transferQueueCurrentBlockCount](#), [457](#)
 - [m_width](#), [457](#)
- [spinChunkEncoderSelectorEnums](#)
 - [Camera Enumerations](#), [48](#)
- [spinChunkEncoderStatusEnums](#)
 - [Camera Enumerations](#), [48](#)
- [spinChunkExposureTimeSelectorEnums](#)
 - [Camera Enumerations](#), [48](#)
- [spinChunkGainSelectorEnums](#)
 - [Camera Enumerations](#), [49](#)
- [spinChunkImageComponentEnums](#)
 - [Camera Enumerations](#), [49](#)
- [spinChunkPixelFormatEnums](#)
 - [Camera Enumerations](#), [50](#)
- [spinChunkRegionIDEnums](#)
 - [Camera Enumerations](#), [50](#)
- [spinChunkScan3dCoordinateReferenceSelectorEnums](#)
 - [Camera Enumerations](#), [50](#)
- [spinChunkScan3dCoordinateSelectorEnums](#)
 - [Camera Enumerations](#), [51](#)
- [spinChunkScan3dCoordinateSystemEnums](#)
 - [Camera Enumerations](#), [51](#)
- [spinChunkScan3dCoordinateSystemReferenceEnums](#)
 - [Camera Enumerations](#), [51](#)
- [spinChunkScan3dCoordinateTransformSelectorEnums](#)
 - [Camera Enumerations](#), [52](#)
- [spinChunkScan3dDistanceUnitEnums](#)
 - [Camera Enumerations](#), [52](#)
- [spinChunkScan3dOutputModeEnums](#)
 - [Camera Enumerations](#), [53](#)
- [spinChunkSelectorEnums](#)
 - [Camera Enumerations](#), [53](#)
- [spinChunkSourceIDEnums](#)
 - [Camera Enumerations](#), [54](#)
- [spinChunkTimerSelectorEnums](#)
 - [Camera Enumerations](#), [54](#)
- [spinChunkTransferStreamIDEnums](#)
 - [Camera Enumerations](#), [55](#)
- [spinCIConfigurationEnums](#)
 - [Camera Enumerations](#), [55](#)
- [spinCITimeSlotsCountEnums](#)
 - [Camera Enumerations](#), [55](#)
- [spinColorProcessingAlgorithm](#)
 - [Spinnaker C Enumerations](#), [241](#)
- [spinColorTransformationSelectorEnums](#)
 - [Camera Enumerations](#), [56](#)
- [spinColorTransformationValueSelectorEnums](#)
 - [Camera Enumerations](#), [56](#)
- [spinCommandExecute](#)
 - [ICommand Access](#), [292](#)
- [spinCommandIsDone](#)
 - [ICommand Access](#), [293](#)
- [spinCompressionMethod](#)
 - [Spinnaker C Structures](#), [248](#)
- [spinCounterEventActivationEnums](#)
 - [Camera Enumerations](#), [57](#)
- [spinCounterEventSourceEnums](#)
 - [Camera Enumerations](#), [57](#)
- [spinCounterResetActivationEnums](#)
 - [Camera Enumerations](#), [58](#)
- [spinCounterResetSourceEnums](#)
 - [Camera Enumerations](#), [58](#)
- [spinCounterSelectorEnums](#)
 - [Camera Enumerations](#), [58](#)
- [spinCounterStatusEnums](#)
 - [Camera Enumerations](#), [59](#)
- [spinCounterTriggerActivationEnums](#)
 - [Camera Enumerations](#), [59](#)
- [spinCounterTriggerSourceEnums](#)
 - [Camera Enumerations](#), [59](#)
- [spinCxpConnectionTestModeEnums](#)
 - [Camera Enumerations](#), [60](#)
- [spinCxpLinkConfigurationEnums](#)
 - [Camera Enumerations](#), [60](#)
- [spinCxpLinkConfigurationPreferredEnums](#)
 - [Camera Enumerations](#), [61](#)
- [spinCxpLinkConfigurationStatusEnums](#)
 - [Camera Enumerations](#), [62](#)
- [spinCxpPoCxpStatusEnums](#)
 - [Camera Enumerations](#), [63](#)
- [spinDecimationHorizontalModeEnums](#)
 - [Camera Enumerations](#), [64](#)
- [spinDecimationSelectorEnums](#)
 - [Camera Enumerations](#), [64](#)
- [spinDecimationVerticalModeEnums](#)
 - [Camera Enumerations](#), [64](#)
- [spinDefectCorrectionModeEnums](#)
 - [Camera Enumerations](#), [64](#)
- [spinDeinterlacingEnums](#)
 - [Camera Enumerations](#), [65](#)
- [spinDeviceArrivalEventHandler](#)
 - [Spinnaker C Handles](#), [234](#)
- [spinDeviceArrivalEventHandlerCreate](#)
 - [Event Access](#), [208](#)
- [spinDeviceArrivalEventHandlerDestroy](#)
 - [Event Access](#), [209](#)
- [spinDeviceCharacterSetEnums](#)
 - [Camera Enumerations](#), [65](#)
- [spinDeviceClockSelectorEnums](#)
 - [Camera Enumerations](#), [65](#)

- spinDeviceConnectionStatusEnums
 - Camera Enumerations, [66](#)
- spinDeviceEventData
 - Spinnaker C Handles, [234](#)
- spinDeviceEventFunction
 - Spinnaker C Function Signatures, [237](#)
- spinDeviceEventGetId
 - Device Event Data Access, [229](#)
- spinDeviceEventGetName
 - Device Event Data Access, [230](#)
- spinDeviceEventGetPayloadData
 - Device Event Data Access, [230](#)
- spinDeviceEventGetPayloadDataSize
 - Device Event Data Access, [231](#)
- spinDeviceEventHandler
 - Spinnaker C Handles, [234](#)
- spinDeviceEventHandlerCreate
 - Event Access, [209](#)
- spinDeviceEventHandlerDestroy
 - Event Access, [210](#)
- spinDeviceIndicatorModeEnums
 - Camera Enumerations, [66](#)
- spinDeviceLinkHeartbeatModeEnums
 - Camera Enumerations, [66](#)
- spinDeviceLinkThroughputLimitModeEnums
 - Camera Enumerations, [68](#)
- spinDevicePowerSupplySelectorEnums
 - Camera Enumerations, [68](#)
- spinDeviceRegistersEndiannessEnums
 - Camera Enumerations, [68](#)
- spinDeviceRemovalEventHandler
 - Spinnaker C Handles, [235](#)
- spinDeviceRemovalEventHandlerCreate
 - Event Access, [210](#)
- spinDeviceRemovalEventHandlerDestroy
 - Event Access, [211](#)
- spinDeviceScanTypeEnums
 - Camera Enumerations, [69](#)
- spinDeviceSerialPortBaudRateEnums
 - Camera Enumerations, [69](#)
- spinDeviceSerialPortSelectorEnums
 - Camera Enumerations, [69](#)
- spinDeviceStreamChannelEndiannessEnums
 - Camera Enumerations, [69](#)
- spinDeviceStreamChannelTypeEnums
 - Camera Enumerations, [70](#)
- spinDeviceTLTypeEnums
 - Camera Enumerations, [72](#)
- spinDeviceTapGeometryEnums
 - Camera Enumerations, [70](#)
- spinDeviceTemperatureSelectorEnums
 - Camera Enumerations, [71](#)
- spinDeviceTypeEnums
 - Camera Enumerations, [72](#)
- spinDisplayNotation
 - Spinnaker C GenICam Enumerations, [306](#)
- spinEncoderModeEnums
 - Camera Enumerations, [72](#)
- spinEncoderOutputModeEnums
 - Camera Enumerations, [73](#)
- spinEncoderResetActivationEnums
 - Camera Enumerations, [73](#)
- spinEncoderResetSourceEnums
 - Camera Enumerations, [74](#)
- spinEncoderSelectorEnums
 - Camera Enumerations, [75](#)
- spinEncoderSourceAEnums
 - Camera Enumerations, [75](#)
- spinEncoderSourceBEnums
 - Camera Enumerations, [75](#)
- spinEncoderStatusEnums
 - Camera Enumerations, [76](#)
- spinEndianness
 - Spinnaker C GenICam Enumerations, [306](#)
- spinEnumerationEntryGetEnumValue
 - IEnumEntry Access, [287](#)
- spinEnumerationEntryGetIntValue
 - IEnumEntry Access, [288](#)
- spinEnumerationEntryGetSymbolic
 - IEnumEntry Access, [288](#)
- spinEnumerationGetCurrentEntry
 - IEnumeration Access, [283](#)
- spinEnumerationGetEntryByIndex
 - IEnumeration Access, [284](#)
- spinEnumerationGetEntryByName
 - IEnumeration Access, [284](#)
- spinEnumerationGetNumEntries
 - IEnumeration Access, [285](#)
- spinEnumerationSetEnumValue
 - IEnumeration Access, [285](#)
- spinEnumerationSetIntValue
 - IEnumeration Access, [286](#)
- spinError
 - Spinnaker C Enumerations, [242](#)
- spinErrorGetLast
 - Error Handling, [130](#)
- spinErrorGetLastBuildDate
 - Error Handling, [131](#)
- spinErrorGetLastBuildTime
 - Error Handling, [131](#)
- spinErrorGetLastFileName
 - Error Handling, [132](#)
- spinErrorGetLastFullMessage
 - Error Handling, [132](#)
- spinErrorGetLastFunctionName
 - Error Handling, [133](#)
- spinErrorGetLastLineNumber
 - Error Handling, [133](#)
- spinErrorGetLastMessage
 - Error Handling, [134](#)
- spinEventNotificationEnums
 - Camera Enumerations, [76](#)
- spinEventSelectorEnums
 - Camera Enumerations, [76](#)
- spinExposureActiveModeEnums
 - Camera Enumerations, [77](#)

- spinExposureAutoEnums
 - Camera Enumerations, [77](#)
- spinExposureModeEnums
 - Camera Enumerations, [77](#)
- spinExposureTimeModeEnums
 - Camera Enumerations, [78](#)
- spinExposureTimeSelectorEnums
 - Camera Enumerations, [78](#)
- spinFileOpenModeEnums
 - Camera Enumerations, [79](#)
- spinFileOperationSelectorEnums
 - Camera Enumerations, [79](#)
- spinFileOperationStatusEnums
 - Camera Enumerations, [79](#)
- spinFileSelectorEnums
 - Camera Enumerations, [80](#)
- spinFloatGetMax
 - IFloat Access, [278](#)
- spinFloatGetMin
 - IFloat Access, [279](#)
- spinFloatGetRepresentation
 - IFloat Access, [279](#)
- spinFloatGetUnit
 - IFloat Access, [280](#)
- spinFloatGetValue
 - IFloat Access, [280](#)
- spinFloatGetValueEx
 - IFloat Access, [281](#)
- spinFloatSetValuel
 - IFloat Access, [281](#)
- spinFloatSetValueEx
 - IFloat Access, [282](#)
- spinGainAutoBalanceEnums
 - Camera Enumerations, [80](#)
- spinGainAutoEnums
 - Camera Enumerations, [80](#)
- spinGainSelectorEnums
 - Camera Enumerations, [81](#)
- spinGevCCPEnums
 - Camera Enumerations, [81](#)
- spinGevCurrentPhysicalLinkConfigurationEnums
 - Camera Enumerations, [81](#)
- spinGevGVCPExtendedStatusCodesSelectorEnums
 - Camera Enumerations, [81](#)
- spinGevGVSPExtendedIDModeEnums
 - Camera Enumerations, [82](#)
- spinGevIEEE1588ClockAccuracyEnums
 - Camera Enumerations, [82](#)
- spinGevIEEE1588ModeEnums
 - Camera Enumerations, [82](#)
- spinGevIEEE1588StatusEnums
 - Camera Enumerations, [83](#)
- spinGevIPConfigurationStatusEnums
 - Camera Enumerations, [83](#)
- spinGevPhysicalLinkConfigurationEnums
 - Camera Enumerations, [83](#)
- spinGevSupportedOptionSelectorEnums
 - Camera Enumerations, [84](#)
- spinH264Option, [457](#)
 - bitrate, [458](#)
 - frameRate, [458](#)
 - height, [458](#)
 - reserved, [458](#)
 - width, [458](#)
- spinImage
 - Spinnaker C Handles, [235](#)
- spinImageCalculateStatistics
 - Image Access, [181](#)
- spinImageCheckCRC
 - Image Access, [182](#)
- spinImageChunkDataGetFloatValue
 - Chunk data access, [232](#)
- spinImageChunkDataGetIntValue
 - Chunk data access, [232](#)
- spinImageComponentSelectorEnums
 - Camera Enumerations, [85](#)
- spinImageCompressionJPEGFormatOptionEnums
 - Camera Enumerations, [85](#)
- spinImageCompressionModeEnums
 - Camera Enumerations, [86](#)
- spinImageCompressionRateOptionEnums
 - Camera Enumerations, [86](#)
- spinImageConvert
 - Image Access, [182](#)
- spinImageConvertEx
 - Image Access, [183](#)
- spinImageCreate
 - Image Access, [183](#)
- spinImageCreateEmpty
 - Image Access, [184](#)
- spinImageCreateEx
 - Image Access, [184](#)
- spinImageDeepCopy
 - Image Access, [185](#)
- spinImageDestroy
 - Image Access, [185](#)
- spinImageEventFunction
 - Spinnaker C Function Signatures, [237](#)
- spinImageEventHandler
 - Spinnaker C Handles, [235](#)
- spinImageEventHandlerCreate
 - Event Access, [211](#)
- spinImageEventHandlerDestroy
 - Event Access, [212](#)
- spinImageFileFormat
 - Spinnaker C Enumerations, [243](#)
- spinImageGetBitsPerPixel
 - Image Access, [186](#)
- spinImageGetBufferSize
 - Image Access, [186](#)
- spinImageGetChunkLayoutID
 - Image Access, [187](#)
- spinImageGetColorProcessing
 - Image Access, [187](#)
- spinImageGetData
 - Image Access, [188](#)

- spinImageGetDefaultColorProcessing
 - Image Access, [188](#)
- spinImageGetFrameID
 - Image Access, [188](#)
- spinImageGetHeight
 - Image Access, [189](#)
- spinImageGetID
 - Image Access, [189](#)
- spinImageGetOffsetX
 - Image Access, [190](#)
- spinImageGetOffsetY
 - Image Access, [190](#)
- spinImageGetPaddingX
 - Image Access, [191](#)
- spinImageGetPaddingY
 - Image Access, [191](#)
- spinImageGetPayloadType
 - Image Access, [192](#)
- spinImageGetPixelFormat
 - Image Access, [192](#)
- spinImageGetPixelFormatName
 - Image Access, [193](#)
- spinImageGetPrivateData
 - Image Access, [193](#)
- spinImageGetSize
 - Image Access, [194](#)
- spinImageGetStatus
 - Image Access, [194](#)
- spinImageGetStatusDescription
 - Image Access, [195](#)
- spinImageGetStride
 - Image Access, [195](#)
- spinImageGetTLPayloadType
 - Image Access, [196](#)
- spinImageGetTLPixelFormat
 - Image Access, [197](#)
- spinImageGetTLPixelFormatNamespace
 - Image Access, [197](#)
- spinImageGetTimeStamp
 - Image Access, [196](#)
- spinImageGetValidPayloadSize
 - Image Access, [198](#)
- spinImageGetWidth
 - Image Access, [198](#)
- spinImageHasCRC
 - Image Access, [199](#)
- spinImageIsIncomplete
 - Image Access, [199](#)
- spinImageRelease
 - Image Access, [200](#)
- spinImageReset
 - Image Access, [200](#)
- spinImageResetEx
 - Image Access, [201](#)
- spinImageSave
 - Image Access, [202](#)
- spinImageSaveBmp
 - Image Access, [202](#)
- spinImageSaveFromExt
 - Image Access, [203](#)
- spinImageSaveJpeg
 - Image Access, [203](#)
- spinImageSaveJpg2
 - Image Access, [204](#)
- spinImageSavePgm
 - Image Access, [204](#)
- spinImageSavePng
 - Image Access, [205](#)
- spinImageSavePpm
 - Image Access, [205](#)
- spinImageSaveTiff
 - Image Access, [206](#)
- spinImageSetDefaultColorProcessing
 - Image Access, [206](#)
- spinImageStatistics
 - Spinnaker C Handles, [235](#)
- spinImageStatisticsCreate
 - ImageStatistics Access, [216](#)
- spinImageStatisticsDestroy
 - ImageStatistics Access, [216](#)
- spinImageStatisticsDisableAll
 - ImageStatistics Access, [216](#)
- spinImageStatisticsEnableAll
 - ImageStatistics Access, [217](#)
- spinImageStatisticsEnableGreyOnly
 - ImageStatistics Access, [217](#)
- spinImageStatisticsEnableHslOnly
 - ImageStatistics Access, [218](#)
- spinImageStatisticsEnableRgbOnly
 - ImageStatistics Access, [218](#)
- spinImageStatisticsGetAll
 - ImageStatistics Access, [219](#)
- spinImageStatisticsGetChannelStatus
 - ImageStatistics Access, [219](#)
- spinImageStatisticsGetHistogram
 - ImageStatistics Access, [220](#)
- spinImageStatisticsGetMean
 - ImageStatistics Access, [220](#)
- spinImageStatisticsGetNumPixelValues
 - ImageStatistics Access, [221](#)
- spinImageStatisticsGetPixelValueRange
 - ImageStatistics Access, [221](#)
- spinImageStatisticsGetRange
 - ImageStatistics Access, [222](#)
- spinImageStatisticsSetChannelStatus
 - ImageStatistics Access, [222](#)
- spinImageStatus
 - Spinnaker C Enumerations, [244](#)
- spinIncMode
 - Spinnaker C GenICam Enumerations, [307](#)
- spinInputDirection
 - Spinnaker C GenICam Enumerations, [307](#)
- spinIntegerGetInc
 - Integer Access, [273](#)
- spinIntegerGetMax
 - Integer Access, [274](#)

- spinIntegerGetMin
 - Integer Access, [274](#)
- spinIntegerGetRepresentation
 - Integer Access, [275](#)
- spinIntegerGetValue
 - Integer Access, [275](#)
- spinIntegerGetValueEx
 - Integer Access, [276](#)
- spinIntegerSetValue
 - Integer Access, [276](#)
- spinIntegerSetValueEx
 - Integer Access, [277](#)
- spinInterface
 - Spinnaker C Handles, [235](#)
- spinInterfaceEventHandler
 - Spinnaker C Handles, [235](#)
- spinInterfaceEventHandlerCreate
 - Event Access, [212](#)
- spinInterfaceEventHandlerDestroy
 - Event Access, [213](#)
- spinInterfaceGetCameras
 - Interface Access, [160](#)
- spinInterfaceGetCamerasEx
 - Interface Access, [160](#)
- spinInterfaceGetTLNodeMap
 - Interface Access, [161](#)
- spinInterfaceIsInUse
 - Interface Access, [161](#)
- spinInterfaceList
 - Spinnaker C Handles, [236](#)
- spinInterfaceListClear
 - InterfaceList Access, [149](#)
- spinInterfaceListCreateEmpty
 - InterfaceList Access, [150](#)
- spinInterfaceListDestroy
 - InterfaceList Access, [150](#)
- spinInterfaceListGet
 - InterfaceList Access, [151](#)
- spinInterfaceListGetSize
 - InterfaceList Access, [151](#)
- spinInterfaceRegisterDeviceArrivalEventHandler
 - Interface Access, [162](#)
- spinInterfaceRegisterDeviceRemovalEventHandler
 - Interface Access, [162](#)
- spinInterfaceRegisterInterfaceEventHandler
 - Interface Access, [163](#)
- spinInterfaceRelease
 - Interface Access, [163](#)
- spinInterfaceSendActionCommand
 - Interface Access, [164](#)
- spinInterfaceType
 - Spinnaker C GenICam Enumerations, [307](#)
- spinInterfaceUnregisterDeviceArrivalEventHandler
 - Interface Access, [164](#)
- spinInterfaceUnregisterDeviceRemovalEventHandler
 - Interface Access, [165](#)
- spinInterfaceUnregisterInterfaceEventHandler
 - Interface Access, [165](#)
- spinInterfaceUpdateCameras
 - Interface Access, [166](#)
- spinJPEGOption, [459](#)
 - progressive, [459](#)
 - quality, [459](#)
 - reserved, [459](#)
- spinJPG2Option, [460](#)
 - quality, [460](#)
 - reserved, [460](#)
- spinLUTSelectorEnums
 - Camera Enumerations, [90](#)
- spinLibraryVersion, [461](#)
 - build, [461](#)
 - major, [461](#)
 - minor, [461](#)
 - type, [461](#)
- spinLineFormatEnums
 - Camera Enumerations, [86](#)
- spinLineInputFilterSelectorEnums
 - Camera Enumerations, [87](#)
- spinLineModeEnums
 - Camera Enumerations, [87](#)
- spinLineSelectorEnums
 - Camera Enumerations, [87](#)
- spinLineSourceEnums
 - Camera Enumerations, [88](#)
- spinLinkType
 - Spinnaker C GenICam Enumerations, [308](#)
- spinLogDataGetCategoryName
 - Logging Event Data Access, [224](#)
- spinLogDataGetLogMessage
 - Logging Event Data Access, [225](#)
- spinLogDataGetNDC
 - Logging Event Data Access, [225](#)
- spinLogDataGetPriority
 - Logging Event Data Access, [226](#)
- spinLogDataGetPriorityName
 - Logging Event Data Access, [226](#)
- spinLogDataGetThreadName
 - Logging Event Data Access, [227](#)
- spinLogDataGetTimestamp
 - Logging Event Data Access, [227](#)
- spinLogEventData
 - Spinnaker C Handles, [236](#)
- spinLogEventFunction
 - Spinnaker C Function Signatures, [238](#)
- spinLogEventHandler
 - Spinnaker C Handles, [236](#)
- spinLogEventHandlerCreate
 - Event Access, [213](#)
- spinLogEventHandlerDestroy
 - Event Access, [214](#)
- spinLogicBlockLUTInputActivationEnums
 - Camera Enumerations, [88](#)
- spinLogicBlockLUTInputSelectorEnums
 - Camera Enumerations, [89](#)
- spinLogicBlockLUTInputSourceEnums
 - Camera Enumerations, [89](#)

- spinLogicBlockLUTSelectorEnums
 - Camera Enumerations, [90](#)
- spinLogicBlockSelectorEnums
 - Camera Enumerations, [90](#)
- spinMJPGOption, [462](#)
 - frameRate, [462](#)
 - quality, [462](#)
 - reserved, [462](#)
- spinNameSpace
 - Spinnaker C GenICam Enumerations, [309](#)
- spinNodeCallbackFunction
 - Spinnaker C GenICam Handles, [301](#)
- spinNodeCallbackHandle
 - Spinnaker C GenICam Handles, [301](#)
- spinNodeDeregisterCallback
 - Node Access, [255](#)
- spinNodeFromString
 - IValue Access, [266](#)
- spinNodeFromStringEx
 - IValue Access, [267](#)
- spinNodeGetAccessMode
 - Node Access, [255](#)
- spinNodeGetCachingMode
 - Node Access, [256](#)
- spinNodeGetDescription
 - Node Access, [256](#)
- spinNodeGetDisplayName
 - Node Access, [257](#)
- spinNodeGetImposedAccessMode
 - Node Access, [258](#)
- spinNodeGetImposedVisibility
 - Node Access, [258](#)
- spinNodeGetName
 - Node Access, [258](#)
- spinNodeGetNameSpace
 - Node Access, [259](#)
- spinNodeGetPollingTime
 - Node Access, [259](#)
- spinNodeGetToolTip
 - Node Access, [260](#)
- spinNodeGetType
 - Node Access, [260](#)
- spinNodeGetVisibility
 - Node Access, [261](#)
- spinNodeHandle
 - Spinnaker C GenICam Handles, [301](#)
- spinNodeInvalidateNode
 - Node Access, [261](#)
- spinNodeIsAvailable
 - Node Access, [262](#)
- spinNodeIsEqual
 - Node Access, [262](#)
- spinNodeIsImplemented
 - Node Access, [263](#)
- spinNodeIsReadable
 - Node Access, [263](#)
- spinNodeIsWritable
 - Node Access, [264](#)
- spinNodeMapGetNode
 - Node Map Access, [251](#)
- spinNodeMapGetNodeByIndex
 - Node Map Access, [252](#)
- spinNodeMapGetNumNodes
 - Node Map Access, [252](#)
- spinNodeMapHandle
 - Spinnaker C GenICam Handles, [302](#)
- spinNodeMapPoll
 - Node Map Access, [253](#)
- spinNodeRegisterCallback
 - Node Access, [264](#)
- spinNodeToString
 - IValue Access, [267](#)
- spinNodeToStringEx
 - IValue Access, [268](#)
- spinNodeType
 - Spinnaker C GenICam Enumerations, [309](#)
- spinPGMOption, [463](#)
 - binaryFile, [463](#)
 - reserved, [463](#)
- spinPNGOption, [464](#)
 - compressionLevel, [464](#)
 - interlaced, [464](#)
 - reserved, [464](#)
- spinPPMOption, [465](#)
 - binaryFile, [465](#)
 - reserved, [465](#)
- spinPayloadTypeInfoFoldIds
 - Spinnaker C Enumerations, [245](#)
- spinPixelColorFilterEnums
 - Camera Enumerations, [91](#)
- spinPixelFormatEnums
 - Camera Enumerations, [91](#)
- spinPixelFormatInfoSelectorEnums
 - Camera Enumerations, [97](#)
- spinPixelFormatNamespaceID
 - Spinnaker C Enumerations, [245](#)
- spinPixelSizeEnums
 - Camera Enumerations, [102](#)
- spinRegionDestinationEnums
 - Camera Enumerations, [103](#)
- spinRegionModeEnums
 - Camera Enumerations, [103](#)
- spinRegionSelectorEnums
 - Camera Enumerations, [104](#)
- spinRegisterGet
 - IRegister Access, [296](#)
- spinRegisterGetAddress
 - IRegister Access, [297](#)
- spinRegisterGetEx
 - IRegister Access, [297](#)
- spinRegisterGetLength
 - IRegister Access, [298](#)
- spinRegisterSet
 - IRegister Access, [299](#)
- spinRegisterSetEx
 - IRegister Access, [299](#)

- spinRegisterSetReference
 - IRegister Access, [300](#)
- spinRemovalEventFunction
 - Spinnaker C Function Signatures, [238](#)
- spinRepresentation
 - Spinnaker C GenICam Enumerations, [310](#)
- spinRgbTransformLightSourceEnums
 - Camera Enumerations, [104](#)
- spinScan3dCoordinateReferenceSelectorEnums
 - Camera Enumerations, [104](#)
- spinScan3dCoordinateSelectorEnums
 - Camera Enumerations, [105](#)
- spinScan3dCoordinateSystemEnums
 - Camera Enumerations, [105](#)
- spinScan3dCoordinateSystemReferenceEnums
 - Camera Enumerations, [105](#)
- spinScan3dCoordinateTransformSelectorEnums
 - Camera Enumerations, [106](#)
- spinScan3dDistanceUnitEnums
 - Camera Enumerations, [106](#)
- spinScan3dOutputModeEnums
 - Camera Enumerations, [107](#)
- spinSensorDigitizationTapsEnums
 - Camera Enumerations, [107](#)
- spinSensorShutterModeEnums
 - Camera Enumerations, [108](#)
- spinSensorTapsEnums
 - Camera Enumerations, [108](#)
- spinSequencerConfigurationModeEnums
 - Camera Enumerations, [109](#)
- spinSequencerConfigurationValidEnums
 - Camera Enumerations, [109](#)
- spinSequencerModeEnums
 - Camera Enumerations, [109](#)
- spinSequencerSetValidEnums
 - Camera Enumerations, [109](#)
- spinSequencerTriggerActivationEnums
 - Camera Enumerations, [110](#)
- spinSequencerTriggerSourceEnums
 - Camera Enumerations, [110](#)
- spinSerialPortBaudRateEnums
 - Camera Enumerations, [110](#)
- spinSerialPortParityEnums
 - Camera Enumerations, [111](#)
- spinSerialPortSelectorEnums
 - Camera Enumerations, [111](#)
- spinSerialPortSourceEnums
 - Camera Enumerations, [112](#)
- spinSerialPortStopBitsEnums
 - Camera Enumerations, [112](#)
- spinSign
 - Spinnaker C GenICam Enumerations, [310](#)
- spinSlope
 - Spinnaker C GenICam Enumerations, [310](#)
- spinSoftwareSignalSelectorEnums
 - Camera Enumerations, [112](#)
- spinSourceSelectorEnums
 - Camera Enumerations, [113](#)
- spinStandardNameSpace
 - Spinnaker C GenICam Enumerations, [311](#)
- spinStatisticsChannel
 - Spinnaker C Enumerations, [246](#)
- spinStringGetMaxLength
 - String Access, [269](#)
- spinStringGetValue
 - String Access, [270](#)
- spinStringGetValueEx
 - String Access, [270](#)
- spinStringSetValue
 - String Access, [271](#)
- spinStringSetValueEx
 - String Access, [271](#)
- spinSystem
 - Spinnaker C Handles, [236](#)
- spinSystemGetCameras
 - System Access, [136](#)
- spinSystemGetCamerasEx
 - System Access, [137](#)
- spinSystemGetInstance
 - System Access, [137](#)
- spinSystemGetInterfaces
 - System Access, [139](#)
- spinSystemGetLibraryVersion
 - System Access, [139](#)
- spinSystemGetLoggingLevel
 - System Access, [139](#)
- spinSystemGetTLNodeMap
 - System Access, [140](#)
- spinSystemIsInUse
 - System Access, [140](#)
- spinSystemRegisterDeviceArrivalEventHandler
 - System Access, [141](#)
- spinSystemRegisterDeviceRemovalEventHandler
 - System Access, [141](#)
- spinSystemRegisterInterfaceEventHandler
 - System Access, [142](#)
- spinSystemRegisterLogEventHandler
 - System Access, [142](#)
- spinSystemReleaseInstance
 - System Access, [143](#)
- spinSystemSendActionCommand
 - System Access, [143](#)
- spinSystemSetLoggingLevel
 - System Access, [144](#)
- spinSystemUnregisterAllLogEventHandlers
 - System Access, [145](#)
- spinSystemUnregisterDeviceArrivalEventHandler
 - System Access, [145](#)
- spinSystemUnregisterDeviceRemovalEventHandler
 - System Access, [145](#)
- spinSystemUnregisterInterfaceEventHandler
 - System Access, [146](#)
- spinSystemUnregisterLogEventHandler
 - System Access, [146](#)
- spinSystemUpdateCameras
 - System Access, [147](#)

- spinSystemUpdateCamerasEx
 - System Access, [147](#)
- spinTIFFOption, [465](#)
 - compression, [466](#)
 - reserved, [466](#)
- spinTLDeviceAccessStatusEnums
 - Transport Layer Enumerations, [318](#)
- spinTLDeviceCurrentSpeedEnums
 - Transport Layer Enumerations, [320](#)
- spinTLDeviceEndianessMechanismEnums
 - Transport Layer Enumerations, [320](#)
- spinTLDeviceTypeEnums
 - Transport Layer Enumerations, [320](#)
- spinTLFilterDriverStatusEnums
 - Transport Layer Enumerations, [321](#)
- spinTLGUIXMLLocationEnums
 - Transport Layer Enumerations, [322](#)
- spinTLGenICamXMLLocationEnums
 - Transport Layer Enumerations, [321](#)
- spinTLGevCCPEnums
 - Transport Layer Enumerations, [321](#)
- spinTLInterfaceTypeEnums
 - Transport Layer Enumerations, [322](#)
- spinTLPOEStatusEnums
 - Transport Layer Enumerations, [322](#)
- spinTLStreamBufferCountModeEnums
 - Transport Layer Enumerations, [323](#)
- spinTLStreamBufferHandlingModeEnums
 - Transport Layer Enumerations, [323](#)
- spinTLStreamTypeEnums
 - Transport Layer Enumerations, [324](#)
- spinTLTLTypeEnums
 - Transport Layer Enumerations, [324](#)
- spinTestPatternEnums
 - Camera Enumerations, [113](#)
- spinTestPatternGeneratorSelectorEnums
 - Camera Enumerations, [113](#)
- spinTimerSelectorEnums
 - Camera Enumerations, [114](#)
- spinTimerStatusEnums
 - Camera Enumerations, [114](#)
- spinTimerTriggerActivationEnums
 - Camera Enumerations, [114](#)
- spinTimerTriggerSourceEnums
 - Camera Enumerations, [115](#)
- spinTransferComponentSelectorEnums
 - Camera Enumerations, [116](#)
- spinTransferControlModeEnums
 - Camera Enumerations, [116](#)
- spinTransferOperationModeEnums
 - Camera Enumerations, [117](#)
- spinTransferQueueModeEnums
 - Camera Enumerations, [117](#)
- spinTransferSelectorEnums
 - Camera Enumerations, [117](#)
- spinTransferStatusSelectorEnums
 - Camera Enumerations, [118](#)
- spinTransferTriggerActivationEnums
 - Camera Enumerations, [118](#)
- spinTransferTriggerModeEnums
 - Camera Enumerations, [118](#)
- spinTransferTriggerSelectorEnums
 - Camera Enumerations, [119](#)
- spinTransferTriggerSourceEnums
 - Camera Enumerations, [119](#)
- spinTriggerActivationEnums
 - Camera Enumerations, [120](#)
- spinTriggerModeEnums
 - Camera Enumerations, [121](#)
- spinTriggerOverlapEnums
 - Camera Enumerations, [121](#)
- spinTriggerSelectorEnums
 - Camera Enumerations, [121](#)
- spinTriggerSourceEnums
 - Camera Enumerations, [121](#)
- spinUserOutputSelectorEnums
 - Camera Enumerations, [122](#)
- spinUserSetDefaultEnums
 - Camera Enumerations, [122](#)
- spinUserSetSelectorEnums
 - Camera Enumerations, [123](#)
- spinVideo
 - Spinnaker C Handles, [236](#)
- SpinVideo Recording Access, [314](#)
 - spinVideoAppend, [314](#)
 - spinVideoClose, [314](#)
 - spinVideoOpenH264, [315](#)
 - spinVideoOpenMJPEG, [315](#)
 - spinVideoOpenUncompressed, [315](#)
 - spinVideoSetMaximumFileSize, [315](#)
- spinVideoAppend
 - SpinVideo Recording Access, [314](#)
- spinVideoClose
 - SpinVideo Recording Access, [314](#)
- spinVideoOpenH264
 - SpinVideo Recording Access, [315](#)
- spinVideoOpenMJPEG
 - SpinVideo Recording Access, [315](#)
- spinVideoOpenUncompressed
 - SpinVideo Recording Access, [315](#)
- spinVideoSetMaximumFileSize
 - SpinVideo Recording Access, [315](#)
- spinVisibility
 - Spinnaker C GenICam Enumerations, [311](#)
- spinWhiteClipSelectorEnums
 - Camera Enumerations, [123](#)
- spinXMLValidation
 - Spinnaker C GenICam Enumerations, [311](#)
- spinYesNo
 - Spinnaker C GenICam Enumerations, [313](#)
- Spinnaker C API, [128](#)
 - spinCameraDiscoverMaxPacketSize, [129](#)
- Spinnaker C Definitions, [7](#)
 - bool8_t, [8](#)
 - False, [8](#)
 - True, [8](#)

- Spinnaker C Enumerations, [239](#)
 - spinColorProcessingAlgorithm, [241](#)
 - spinError, [242](#)
 - spinImageFileFormat, [243](#)
 - spinImageStatus, [244](#)
 - spinPayloadTypeInfoIDs, [245](#)
 - spinPixelFormatNamespaceID, [245](#)
 - spinStatisticsChannel, [246](#)
 - spinnakerLogLevel, [244](#)
- Spinnaker C Function Signatures, [237](#)
 - spinArrivalEventFunction, [237](#)
 - spinDeviceEventFunction, [237](#)
 - spinImageEventFunction, [237](#)
 - spinLogEventFunction, [238](#)
 - spinRemovalEventFunction, [238](#)
- Spinnaker C GenICam API, [249](#)
- Spinnaker C GenICam Enumerations, [303](#)
 - spinAccessMode, [305](#)
 - spinCachingMode, [306](#)
 - spinDisplayNotation, [306](#)
 - spinEndianess, [306](#)
 - spinIncMode, [307](#)
 - spinInputDirection, [307](#)
 - spinInterfaceType, [307](#)
 - spinLinkType, [308](#)
 - spinNameSpace, [309](#)
 - spinNodeType, [309](#)
 - spinRepresentation, [310](#)
 - spinSign, [310](#)
 - spinSlope, [310](#)
 - spinStandardNameSpace, [311](#)
 - spinVisibility, [311](#)
 - spinXMLValidation, [311](#)
 - spinYesNo, [313](#)
- Spinnaker C GenICam Handles, [301](#)
 - spinNodeCallbackFunction, [301](#)
 - spinNodeCallbackHandle, [301](#)
 - spinNodeHandle, [301](#)
 - spinNodeMapHandle, [302](#)
- Spinnaker C Handles, [233](#)
 - spinCamera, [234](#)
 - spinCameraList, [234](#)
 - spinDeviceArrivalEventHandler, [234](#)
 - spinDeviceEventData, [234](#)
 - spinDeviceEventHandler, [234](#)
 - spinDeviceRemovalEventHandler, [235](#)
 - spinImage, [235](#)
 - spinImageEventHandler, [235](#)
 - spinImageStatistics, [235](#)
 - spinInterface, [235](#)
 - spinInterfaceEventHandler, [235](#)
 - spinInterfaceList, [236](#)
 - spinLogEventData, [236](#)
 - spinLogEventHandler, [236](#)
 - spinSystem, [236](#)
 - spinVideo, [236](#)
- Spinnaker C QuickSpin API, [125](#)
- Spinnaker C Structures, [247](#)
 - actionCommandStatus, [248](#)
 - spinCompressionMethod, [248](#)
- SpinnakerC.h
 - spinCameraForceIP, [512](#)
- spinnakerLogLevel
 - Spinnaker C Enumerations, [244](#)
- SpinnakerPlatformC.h
 - SPINNAKERC_API, [524](#)
- Status
 - actionCommandResult, [331](#)
- StreamAnnounceBufferMinimum
 - quickSpinTLStream, [443](#)
- StreamAnnouncedBufferCount
 - quickSpinTLStream, [443](#)
- StreamBlockTransferSize
 - quickSpinTLStream, [443](#)
- StreamBufferAlignment
 - quickSpinTLStream, [443](#)
- StreamBufferCountManual
 - quickSpinTLStream, [444](#)
- StreamBufferCountMax
 - quickSpinTLStream, [444](#)
- StreamBufferCountMode
 - quickSpinTLStream, [444](#)
- StreamBufferCountResult
 - quickSpinTLStream, [444](#)
- StreamBufferHandlingMode
 - quickSpinTLStream, [444](#)
- StreamCRCCheckEnable
 - quickSpinTLStream, [444](#)
- StreamChunkCountMaximum
 - quickSpinTLStream, [444](#)
- StreamDeliveredFrameCount
 - quickSpinTLStream, [444](#)
- StreamFailedBufferCount
 - quickSpinTLStream, [445](#)
- StreamID
 - quickSpinTLStream, [445](#)
- StreamInputBufferCount
 - quickSpinTLStream, [445](#)
- StreamIsGrabbing
 - quickSpinTLStream, [445](#)
- StreamLostFrameCount
 - quickSpinTLStream, [445](#)
- StreamOutputBufferCount
 - quickSpinTLStream, [445](#)
- StreamStartedFrameCount
 - quickSpinTLStream, [445](#)
- StreamType
 - quickSpinTLStream, [445](#)
- String Access, [269](#)
 - spinStringGetMaxLength, [269](#)
 - spinStringGetValue, [270](#)
 - spinStringGetValueEx, [270](#)
 - spinStringSetValue, [271](#)
 - spinStringSetValueEx, [271](#)
- System Access, [135](#)
 - spinSystemGetCameras, [136](#)

- spinSystemGetCamerasEx, [137](#)
- spinSystemGetInstance, [137](#)
- spinSystemGetInterfaces, [139](#)
- spinSystemGetLibraryVersion, [139](#)
- spinSystemGetLoggingLevel, [139](#)
- spinSystemGetTLNodeMap, [140](#)
- spinSystemIsInUse, [140](#)
- spinSystemRegisterDeviceArrivalEventHandler, [141](#)
- spinSystemRegisterDeviceRemovalEventHandler, [141](#)
- spinSystemRegisterInterfaceEventHandler, [142](#)
- spinSystemRegisterLogEventHandler, [142](#)
- spinSystemReleaseInstance, [143](#)
- spinSystemSendActionCommand, [143](#)
- spinSystemSetLoggingLevel, [144](#)
- spinSystemUnregisterAllLogEventHandlers, [145](#)
- spinSystemUnregisterDeviceArrivalEventHandler, [145](#)
- spinSystemUnregisterDeviceRemovalEventHandler, [145](#)
- spinSystemUnregisterInterfaceEventHandler, [146](#)
- spinSystemUnregisterLogEventHandler, [146](#)
- spinSystemUpdateCameras, [147](#)
- spinSystemUpdateCamerasEx, [147](#)
- TLDevice Structures, [326](#)
- TLDisplayName
 - quickSpinTLSystem, [448](#)
- TLFileName
 - quickSpinTLSystem, [448](#)
- TLID
 - quickSpinTLSystem, [449](#)
- TLInterface Structures, [327](#)
- TLModelName
 - quickSpinTLSystem, [449](#)
- TLParamsLocked
 - quickSpin, [422](#)
- TLPath
 - quickSpinTLSystem, [449](#)
- TLStream Structures, [328](#)
- TLSystem Structures, [329](#)
- TLType
 - quickSpinTLSystem, [449](#)
- TLVendorName
 - quickSpinTLSystem, [449](#)
- TLVersion
 - quickSpinTLSystem, [449](#)
- Test0001
 - quickSpin, [420](#)
- TestEventGenerate
 - quickSpin, [420](#)
- TestPattern
 - quickSpin, [420](#)
- TestPatternGeneratorSelector
 - quickSpin, [420](#)
- TestPendingAck
 - quickSpin, [420](#)
- TimerDelay
 - quickSpin, [420](#)
- TimerDuration
 - quickSpin, [421](#)
- TimerReset
 - quickSpin, [421](#)
- TimerSelector
 - quickSpin, [421](#)
- TimerStatus
 - quickSpin, [421](#)
- TimerTriggerActivation
 - quickSpin, [421](#)
- TimerTriggerSource
 - quickSpin, [421](#)
- TimerValue
 - quickSpin, [421](#)
- Timestamp
 - quickSpin, [421](#)
- TimestampLatch
 - quickSpin, [422](#)
- TimestampLatchValue
 - quickSpin, [422](#)
- TimestampReset
 - quickSpin, [422](#)
- TransferAbort
 - quickSpin, [422](#)
- TransferBlockCount
 - quickSpin, [422](#)
- TransferBurstCount
 - quickSpin, [422](#)
- TransferComponentSelector
 - quickSpin, [422](#)
- TransferControlMode
 - quickSpin, [423](#)
- TransferOperationMode
 - quickSpin, [423](#)
- TransferPause
 - quickSpin, [423](#)
- TransferQueueCurrentBlockCount
 - quickSpin, [423](#)
- TransferQueueMaxBlockCount
 - quickSpin, [423](#)
- TransferQueueMode
 - quickSpin, [423](#)
- TransferQueueOverflowCount
 - quickSpin, [423](#)
- TransferResume
 - quickSpin, [423](#)
- TransferSelector
 - quickSpin, [424](#)
- TransferStart
 - quickSpin, [424](#)
- TransferStatus
 - quickSpin, [424](#)
- TransferStatusSelector
 - quickSpin, [424](#)
- TransferStop
 - quickSpin, [424](#)
- TransferStreamChannel

- quickSpin, [424](#)
- TransferTriggerActivation
 - quickSpin, [424](#)
- TransferTriggerMode
 - quickSpin, [424](#)
- TransferTriggerSelector
 - quickSpin, [425](#)
- TransferTriggerSource
 - quickSpin, [425](#)
- Transport Layer Enumerations, [317](#)
 - spinTLDeviceAccessStatusEnums, [318](#)
 - spinTLDeviceCurrentSpeedEnums, [320](#)
 - spinTLDeviceEndianessMechanismEnums, [320](#)
 - spinTLDeviceTypeEnums, [320](#)
 - spinTLFilterDriverStatusEnums, [321](#)
 - spinTLGUIXMLLocationEnums, [322](#)
 - spinTLGenICamXMLLocationEnums, [321](#)
 - spinTLGevCCPEnums, [321](#)
 - spinTLInterfaceTypeEnums, [322](#)
 - spinTLPOEStatusEnums, [322](#)
 - spinTLStreamBufferCountModeEnums, [323](#)
 - spinTLStreamBufferHandlingModeEnums, [323](#)
 - spinTLStreamTypeEnums, [324](#)
 - spinTLTLTypeEnums, [324](#)
- TriggerActivation
 - quickSpin, [425](#)
- TriggerDelay
 - quickSpin, [425](#)
- TriggerDivider
 - quickSpin, [425](#)
- TriggerEventTest
 - quickSpin, [425](#)
- TriggerMode
 - quickSpin, [425](#)
- TriggerMultiplier
 - quickSpin, [425](#)
- TriggerOverlap
 - quickSpin, [426](#)
- TriggerSelector
 - quickSpin, [426](#)
- TriggerSoftware
 - quickSpin, [426](#)
- TriggerSource
 - quickSpin, [426](#)
- True
 - Spinnaker C Definitions, [8](#)
- type
 - spinLibraryVersion, [461](#)
- UserOutputSelector
 - quickSpin, [426](#)
- UserOutputValue
 - quickSpin, [426](#)
- UserOutputValueAll
 - quickSpin, [426](#)
- UserOutputValueAllMask
 - quickSpin, [426](#)
- UserSetDefault
 - quickSpin, [427](#)
- UserSetFeatureEnable
 - quickSpin, [427](#)
- UserSetLoad
 - quickSpin, [427](#)
- UserSetSave
 - quickSpin, [427](#)
- UserSetSelector
 - quickSpin, [427](#)
- V3_3Enable
 - quickSpin, [427](#)
- WhiteClip
 - quickSpin, [427](#)
- WhiteClipSelector
 - quickSpin, [427](#)
- Width
 - quickSpin, [428](#)
- width
 - spinH264Option, [458](#)
- WidthMax
 - quickSpin, [428](#)